Camera Station Manual

Software and devices (in the order they are worked on):

1. Blackmagic camera (main tech desk)
2. PTZ camera (back exit)
3. PTZ remote control
4. HDMI cabling to the switcher
5. The KCC Technical app (camera checklist)

Station Definition

This station provides the video that goes to the livestream and the recording. We run two cameras, and each has a fixed job so the stream always has a good picture: the **Blackmagic camera** takes the close-ups and the **PTZ camera** takes the wide shots.

Camera	Where	Job	How it is controlled	Connection
Blackmagic camera	Near the main tech desk	Close-up shots (speaker, singers)	Operated by a person at the camera	HDMI
PTZ camera	Near the back exit	Wide shots of the stage and room	Remote control for now. A joystick controller is planned.	HDMI

Both cameras are left on automatic white balance and exposure. Items marked **[CONFIRM]** are details only the camera lead can fill in.

Before Service

Arrive at the call time (9:00 AM on Sundays). Open the Service Day page in the KCC Technical app and tick each item on the Camera Station checklist as you finish it:

1. **Check each camera is powered on.** Switch on the Blackmagic camera and the PTZ camera. Check the battery or power adapter on the Blackmagic camera. **[CONFIRM: power-on order and where the switches are]**
2. **Verify the video feed is clear.** Confirm both pictures arrive at the switcher over HDMI. If a picture is missing, reseat the HDMI cable at both ends.
3. **Check white balance.** Both cameras are on Auto. Check that skin tones look natural on the stage under the service lights, and tell the lighting station if the picture looks too orange or blue.
4. **Confirm recording is not active.** Make sure no camera or recorder is recording before the service starts.

5. **Test pan/tilt movement.** With the remote, move the PTZ camera across the stage and back. It must not hit anything or stop short. Send it to its wide-shot position and leave it there.

Then focus the Blackmagic camera on the speaker's spot and tell the Streaming station that the cameras are ready.

Shots and Framing

Moment	Camera	Shot
Pre-service, announcements	PTZ	Wide shot of the stage
Worship	Blackmagic	Close-ups of the worship leader and singers, with the PTZ wide shot between songs
Prayer	PTZ	Wide, steady, no movement
Sermon	Blackmagic	Close-up of the speaker, framed from the chest up
Offering, dismissal	PTZ	Wide shot

Framing rules:

- Leave a little space above the head. Never cut off the top of someone's head.
- Keep the horizon level and keep the camera steady. Move slowly and smoothly, and never while the picture is live on the stream.
- Do not pan or zoom during prayer.
- Avoid pointing directly into stage lights, which can wash out the picture.
- Never film the congregation unless the service lead has approved it. **[CONFIRM: church policy on filming the audience]**

During Service

- Follow the order of service in the app so you know what comes next and can get the right shot ready before it is needed.
- Set up the next shot on the camera that is **not** live, then let the switcher take it. The Streaming station decides which camera is live.
- The PTZ camera moves only when it is not live, unless a slow move has been agreed beforehand.
- If the speaker moves, adjust the Blackmagic camera slowly. If the picture looks dark or washed out, tell the Lighting station. Do not change settings on the camera mid-service.
- Keep your eyes on the picture. If a camera freezes or loses its picture, tell the Streaming station straight away so they can switch to the other camera.

After Service

1. Wait until the stream or recording has ended before switching cameras off.
2. Return the PTZ camera to its home position, then switch off both cameras. **[CONFIRM: power-off order]**
3. Put the lens cap on the Blackmagic camera. Charge or switch off its battery, and put the camera and any loose items in their usual place. **[CONFIRM: storage place]**
4. Coil and store the HDMI cables, and put the PTZ remote back in its place.
5. Report any fault in the app (see Using the KCC Technical App) so it is fixed before next week.

Troubleshooting

Problem	Check first	Then
No picture from a camera	Is it powered on?	Reseat the HDMI cable at both ends, then try another cable. Power-cycle the camera if needed.
Picture flickers or drops out	The HDMI cable and connectors	Replace the cable. Long HDMI runs are less reliable, so keep cables short and well seated.
PTZ camera does not respond to the remote	The remote's batteries	Point the remote at the camera, check the camera is powered, and check the camera ID the remote is set to. Power-cycle the camera if it still fails.
PTZ camera moves to the wrong place	Its home or preset position	Send it home, then move it to the wide shot again.
Picture too dark or too bright	The stage lights	Tell the Lighting station. Both cameras are on Auto, so do not change settings mid-service.
Colours look wrong	White balance	Check the camera is on Auto and ask the Lighting station if a colour wash is the cause.
Blackmagic camera stops or turns off	Its battery or power adapter	Replace the battery or reconnect power.

If a camera cannot be fixed before service, tell the service lead and the Streaming station. Run the service on the camera that works, and report the fault in the app.

Using the KCC Technical App

- **Service Day checklist:** open Service Day, find the Camera station and tick items as you go.
- **Gear:** cameras, batteries, cables and the remote are tracked under Gear. Check equipment out and back in when it leaves the room.
- **Report a fault:** if a camera or cable is faulty, send a tech request so it is tracked.
- **Training:** complete the Camera training modules in the Training Hub. Your progress shows on the station card.

Future: a joystick controller for the PTZ camera is planned. This manual will be updated when it is installed.

Contacts

Role	Name	Phone
Camera lead	**[CONFIRM]**	**[CONFIRM]**
Technical admin	Isaac Ojo	587-664-3421
Backup	**[CONFIRM]**	**[CONFIRM]**