



KNEEBOARD SUITE

A-10C/C II



CHECKLISTS, Pt. 1
2

CHECKLISTS, Pt. 2
3

RWR THREATS
4

HOTAS TABLE
5

ORDNANCE. WIND CORRECTION.
6

COCKPIT DIAGRAM. QUICKSTART.
7

“LOAD DSMS” OR “LOAD ALL” MUST BE PERFORMED AFTER EACH REARMING

Max IN-FLIGHT weight: 51,000 lbs.
Max TAXI / TAKEOFF / LAND weight: 46,000 lbs.
At near max taxi weight prefer wide turns at max 5 kts. Limit sharp turns to max 3 kts.

INT CHECK / PRIOR TO ENGINE START

- 1 UHF radio ARC-164 rmb BOTH, set
- 2 PINKY switch AFT exterior lights manual
- 3 Accelerometer Reset
- 4 Exterior and interior lights Set
- 5 Battery / Inverter PWR / rmb STBY
- 6 Flap lever Set to indicated flap position

FIRE DETECT TEST. SIGNAL LIGHTS TEST.
OXY IND TEST. FUEL IND TEST.
FUEL DISPLAY SELECTOR - SET AS REQUIRED.

- 7 APU switch START (ready within 30sec)
- 8 APU GEN switch PWR
- 9 (AAP) CDU, EGI ON

FOR FAST ALIGN (90 sec): WITHIN 30 sec AFTER COMPLETION OF CDU STARTUP TEST PRESS
CDU LSK “INS” > “ALT ALIGN” > “FAST”
VERIFY ASTERISK NEXT TO “*FAST”

STARTING ENGINES

- 1 Left throttle IDLE

WAIT FOR THE “ENG START CYCLE” LIGHT TO GO OFF BEFORE STARTING THE NEXT ENGINE. SHOULD THE RIGHT ENGINE BE STARTED FIRST, PULL THE EMERGENCY BRAKE HANDLE.

- 2 Right throttle IDLE

BEFORE TAXIING

- 1 VHF radios ARC-186 TR, set
- 2 VHF/UHF radio ARC-210 TR, set
- 3 IFF Set, MASTER - STBY
- 4 Emergency brake handle Full forward
- 5 CMSP Set, MODE - STBY
- 6 TACAN / ILS T/R, set / rmb PWR
- 7 Takeoff trim button Hold 2 sec
- 8 CDU Verify align “4.0 0.8” or “1.4 7.2”
LSK “NAV”
- 9 NMSP EGI ON
STR PT, ANCHR, or TCN as required

BEFORE TAXIING (CONT'D)

- 10 IFFCC switch rmb TEST, then UFC ENT
to initiate test (50 sec)
- 11 JTRS switch ON
- 12 CICU switch ON
- 13 MFCD L/R rmb As required
- 14 MFCD “DTS UPLOAD” page “LOAD ALL”
- 15 TGP switch As required
- 16 SAI knob Hold rmb and drag to uncage
- 17 SAS Engage
- 18 IFFCC switch Verify “Testing complete”
rmb ON
- 19 Altimeter Set
- 20 APU GEN OFF prior to APU shutdown
- 21 APU switch OFF
- 22 Ladder / Chocks Stowed / Removed
- 23 EAC switch ARM
- 24 HMCS Power switch rmb ON
- 25 Nosewheel steering Engage

BEFORE TAKEOFF

- 1 Flaps Set for takeoff (7° MVR)
- 2 Speed brakes CLOSED
- 3 IFF As required
- 4 Oxygen, defog, deice As required
- 5 Canopy / Seat Closed, locked / ARMED
- 6 Exterior lights As required

LINEUP CHECK

- 1 Anti-skid switch ANTI-SKID
- 2 Pitot heat switch PITOT HEAT

DISENGAGE NWS AT ABOUT 70 kts.
FLAPS UP 10 knots ABOVE TAKEOFF SPEED.

EXT. LIGHTS		POSIT	ANTICOL	FORMATION	LAND/TAXI
GROUND		FLASH	OFF	ON DURING NIGHT OPS	AS REQUIRED
RWY ENTRY		STEADY	ON		

Lat Long Decimal SEMI-PRECISE	DD° MM.mmm E(0) 41° 47.878 Lat Long Decimal Minutes / LLDM				F10 map ✓
4+4 DCS JTAC SEMI-PRECISE	BB	[CCCD]	[EEEE]		
	KM	[9087]	[7280]		
5+5 MGRS PRECISE	AAA	BB	[CCCD]	[EEEE]	
	38T	KM	[90874]	[72809]	
Trailing zeros to JTAC's will be auto-added on entry					

DESCENT / BEFORE LANDING	
1	Altimeter Check
2	Defog, deice As required
3	Anti-skid switch ANTI-SKID
4	NMSP PTR switch (ADI bars) ... As required
5	Landing lights As required
6	NVIS / NVGs As required / Stow

AFTER CLEARING RUNWAY	
1	Anti-skid switch OFF
2	Seat / Canopy SAFE / As desired
3	TACAN, ILS OFF
4	IFF MASTER - STBY
5	HUD night/day filter DAY
6	Landing/taxi lights As required
7	CMSP all systems and MODE OFF
8	Pitot heat switch / Defog / Deice OFF
9	Position lights Flash
10	Anti-collision lights OFF
11	Flaps As required

ENGINE SHUTDOWN	
1	Chocks Set (<i>hold brakes until set</i>)
2	HMCS Power switch <i>lmb</i> OFF
3	IFF MASTER - OFF
4	SAI knob <i>Pull and scroll to cage</i>
5	Master Arm, Gun/Pac, Laser <i>lmb</i> SAFE
6	TGP, CICU, JTRS, IFFCC <i>rmb</i> OFF
7	MFC D L/R OFF
8	(AAP) EGI, CDU OFF
9	Seat <i>Hold lmb</i> Full up

LEFT ENGINE SHUTDOWN AFTER 5 min AT IDLE. TAXI TIME AT CORE RPM <80% MAY BE INCLUDED. DO NOT SHUTDOWN IF THE APU IS RUNNING.	
RIGHT ENGINE SHUTDOWN ONCE LEFT ENGINE CORE RPM IS BELOW 5% AND ITT IS BELOW 200°C.	
10	Left throttle OFF
11	Right throttle OFF
12	Inverter, Battery <i>rmb</i> OFF
13	VHF, UHF, VHF/UHF radios ALL OFF
14	Oxygen SUPPLY lever OFF
15	Interior, Exterior, Emergency lights ... OFF

AFTER TAKEOFF — PRE STRIKE — POST STRIKE	
FIRE CONTROL	• AHCP switches
	• DSMS
	• Laser codes
	• MAV prepare
ENGINES	• Gauges
	• Fuel
NAVIGATION	• AAP knobs
	• NMSP, HSI
COMMS	• Radios
EMITTERS	• Exterior lights
	• IFF set / M-3, M-C
	• TACAN
	• ECM
	• Chaff, Flare

AIR REFUELING	KC-135
HOT ARMAMENT SAFETY CHECK	
1	Master Arm, Gun/Pac, Laser SAFE
2	"DSMS" page Deselect all stations EO PWR OFF
PRECONTACT CHECKS	
1	IFF / TACAN / ECM STBY / A/A REC / OFF
2	Refueling light rheostats ON
3	Exterior lights As required
4	Fill disable switches As required
5	Air refuel control OPEN
6	READY light Verify ON
POST REFUELING (<i>NWS/AR to disconnect</i>)	
1	Air refuel control CLOSED
2	TACAN, IFF, Exterior lights As required

PRIOR TO FARP ENTRY	HOT REFUELING
"AFTER CLEARING RUNWAY" - COMPLETE	
APU GEN, APU - OFF	DE-ARMING - COMPLETE
MASTER ARM - SAFE	APU GEN or APU - OFF
GUN/PAC, LASER - SAFE	TGP - OFF
TGP - OFF	
"DSMS" PAGE - DESELECT ALL STATIONS, EO PWR OFF	
PRIOR TO REFUELING	
CANOPY - AS REQUIRED	CANOPY - AS DESIRED
FUEL DISPLAY SELECTOR - MAIN	
TANK GATE SWITCH - CLOSED	
After refueling: Taxi clear of refueling area and configure aircraft as required by mission plan.	

4

RWR THREATS

ALL RANGES WERE MEASURED FOR THE F/A-18C. TREAT AS ESTIMATES.

A-10C/C II

DimOn

14	F-14A/GR/B	123 88	21	MiG-21Bis	12 09	37	AJS-37 Viggen	2 06	JF	JF-17	23 46
15	F-15C	123 49	23	MiG-23MLD	12 14	50	A-50 / KJ-2000	AWACS	M2	M-2000C	12 26
	F-15E	23 49	25	MiG-25PD	12 25	64	AH-64D BLK.II	3 05		Mirage 2000-5	123 24
	F-15E S4+	123 49	29	MiG-29A/G	12 38		(with or w/o MMA)		U	A-6E	2 04
16	F-16A	123 38		MiG-29S	123 33	E2	E-2D	AWACS		AH-64D (old)	3 05
	F-16A MLU	23 38		Su-27/33	12 32	E3	E-3A	AWACS		C-101CC	2 04
	F-16C/CM	23 38		J-11A	123 32	F1	Mirage F1	12 22		H-6J	BOMBER
18	F/A-18A	12 27	30	Su-30	123 37	F2	Tornado GR4	2 04		Tornado IDS	2 04
	F/A-18C	123 42	31	MiG-31	12 37	F4	F-4E-45MC	12 27		Tu-95MS	BOMBER
19	MiG-19P	2 03	34	Su-34	123 35	F5	F-5E/E-3/FC	2 04		SH-60B	HELO

SURFACE					NAVAL				
S	Nebo 1L13 / Nebo 55G6 / AN/FPS-117			EWR	15	Project 22160 Tor-M2	CORVETTE	C	10/39
	Flat Face B	[2-3-5]		SR	40	LHA-1 Tarawa	CV	F	08/13
BB	Big Bird	[10]		long-range SR	49	Oliver Hazard Perry	FRIGATE	C	26/++
CS	Clam Shell	[10]		low-altitude SR	AE	Arleigh Burke	DESTROYER	C	80/++
DE	Dog Ear Sborka	[13-15-19]		MCC-SR		Ticonderoga	CRUISER	C	37/++
FC	Fire Can SON-9			AAA FDR	FR	CV-59 Forrestal	CV	C	10/24
HQ	HQ-7B	[7]		SR	HN	Type 052C	DESTROYER	C	90/++
SD	Snow Drift	[11]		SR		Pyotr Velikiy	CRUISER	C	86/++
TS	Tin Shield	[5-10]		SR	HP	Grisha (2025)	CORVETTE	C	07/17
U	Freya / Würzburg		WWII Assets Pack	EWR		Grisha (old)	TO BE REMOVED	C	08/15
	Silkworm		anti-ship	SR	IV	HMS Invincible	CV	C	47/++
	Tall King	[5]		SR	LC	La Combattante	FAST ATTACK CRAFT	E	04/10
2	C 27/++	SA-2 Guideline	S-75	Fan Song TR	MR	Type 052B	DESTROYER	C	31/++
				Amazonka RF		Type 054A	FRIGATE	C	33/++
3	C 13/++	SA-3 Goa	S-125	Low Blow TR	PS	Type 071 Amphib.dock	TRANSPORT	E	06/10
5	C 160/+	SA-5 Gammon	S-200	Square Pair TR		Molniya	CORVETTE	E	03/09
6	C 18/27	SA-6 Gainful	Kub	Straight Flush STR	SC	LS Ropucha	BDK-775 TRANSPORT	E	06/09
7	E 10/18	HQ-7B		TELAR	SS	CVN-71 Roosevelt	CV		
8	C 07/17	SA-8 Gecko	Osa	TELAR		CVN-72 Lincoln	CV		
10	C 48/++	SA-10 Grumble	S-300PS	Flap Lid A & B TR		CVN-73 Washington	cv	C	10/24
11	C 29/++	SA-11 Gadfly	Buk	Fire Dome TELAR		CVN-74 Stennis	CV	F	08/13
13	F 03/12	SA-13 Gopher	Strela-10M	TELAR		CVN-75 Truman	cv		
15	C 09/20	SA-15 Gauntlet	Tor	TELAR	SW	Kuznetsov 2017	cv	C	08/20
	C 10/39	SA-15 Gauntlet	M2 Tor-M2	TELAR		Kuznetsov (old)	cv	C	08/20
19	E 05/12	SA-19 Grison	Tunguska	SPAAW	T2	Moskva	CRUISER	C	48/++
22	C 11/33	SA-22 Greyhound	Pantsir-S1	SPAAW		Project 22160	CORVETTE	E	04/13
A	E 03/10	Gepard		SPAAA	TP	Condell-class	FRIGATE	E	02/07
	E 02/06	Vulcan		SPAAA		CNS Almirante Condell / CNS Almirante Lynch			
	E 02/07	ZSU-23-4	Shilka	SPAAA		Leander-class	FRIGATE	E	06/11
CR	E 02/05	LPWS Centurion	Phalanx	C-RAM		HMS Achilles / HMS Andromeda / HMS Ariadne			
HK	C 14/++	Hawk		CWAR / SR / TR		Neustrashimy	FRIGATE	C	08/20
IT	F 22/++	IRIS-T	SLM	STR		Rezky	FRIGATE	C	08/15
NS	C 13/35	NASAMS AIM-120B		SR	U	ARA Veinticinco de Mayo	CV	E	02/10
	C 13/40	NASAMS AIM-120C		SR		Essex Class 1944	CV	E	02/07
P	C 60/++	Patriot		STR		Type 021-1	MISSILE BOAT	E	02/12
RO	C 05/20	Roland		EWR / ADS					
RP	E 05/10	Rapier with Blindfire	Radar	TR					
RT	E 05/10	Rapier with or without	Tracker	LN					
U	E 10/20	HQ-7 'Player'	AI- or user-controlled	TELAR					

L = LONG PRESS			TAD	TGP	HUD	AIM-9	MAV
D M S	FWD		ZOOM+	ZOOM+ TST: FOCUS+	NEXT STEERPOINT		ADJUST BORESIGHT RETICLE UP
	AFT		ZOOM-	ZOOM- TST: FOCUS-	PREV STEERPOINT		ADJUST BORESIGHT RETICLE DOWN
	LEFT			FLIR AUTOFOCUS	GUNSIGHT / PROFILE CYCLE	A-A PROFILE CYCLE	ADJUST BORESIGHT RETICLE LEFT
		L	BROADCAST SPI				
	RIGHT		CENTER / DEPRESSED	LASER / IR TOGGLE	GUNSIGHT / PROFILE CYCLE	A-A PROFILE CYCLE	ADJUST BORESIGHT RETICLE RIGHT
		L		LSS TOGGLE			
T M S	FWD		HOOK SYMBOL	AREA / POINT TRACK	TDC GROUND STABILIZE	CONIC SCAN	TRACK
		L	Set SOI as SPI generator ("Make SPI")				
	AFT		UNHOOK SYMBOL	INR TRACK	SET SPI SUBMODE	BREAK LOCK	GROUND STAB
		L	RESET SPI TO STEERPOINT				
	LEFT		ACKNOWLEDGE WCN (warnings, cautions, notes) on HUD & MFCDs				
		L					
	RIGHT		CREATE MARKPOINT			CREATE MARK	CREATE MARKPOINT
			TAD	TGP	HUD	AIM-9	MAV
C H I N A	FWD		FOV		SET MAV AS SOI	UNCAGE	FOV
		L	SLAVE ALL TO SPI			SLAVE AIM-9 TO TGP LOS	SLAVE ALL TO SPI
	AFT		RESET CURSOR	BORESIGHT TGP	CAGE TDC TO TVV	MISSILE STEP	
		L	SLAVE TGP TO STEERPOINT				
B O A T	FWD		TGP FLIR BHOT				BLACK HOT
	AFT		TGP FLIR WHOT				WHITE HOT
	CTR		TGP CCD				HOLD 2s: FORCE CORRELATE

CMS	LONG – NEXT PROG ▲ FWD – 1 FLARE	
	PRESS (Z) – RUN/STOP PROG LONG – ECM TOGGLE	RIGHT ► 6 CHAFF
	▼ AFT – 1 CHAFF LONG – PREV PROG	

C O O L I E	UP	SOI HUD	
		L	MSG QUICKLOOK
	DOWN	SWAP MFCDs	
		L	DSMS QUICKLOOK
	LEFT	CYCLE LMFC D	
		L	SOI LMFC D
	RIGHT	CYCLE RMFC D	
		L	SOI RMFC D

P I N K Y	FWD	DEFAULT	E X T L I G H T S
	AFT	MANUAL	
	CTR	OFF	

L = LONG PRESS			TAD	TGP	HUD	AIM-9	MAV	HMCS	
D M S	FWD		ZOOM+	ZOOM+ TST: FOCUS+	NEXT STEERPOINT	NEXT STEERPOINT	ADJ BORESIGHT RETICLE UP	BRT+	
		L	MAP TOGGLE				GYRO STAB (HOLD)		
	AFT		ZOOM-	ZOOM- TST: FOCUS-	PREV STEERPOINT	PREV STEERPOINT	ADJ BORESIGHT RETICLE DOWN	BRT-	
		L	TAD-CTR-OPT						
	LEFT		GEN- / DEP, CNTR	RMFCD TO HMD	GUNSIGHT / PROFILE CYCLE	A-A PROFILE CYCLE	ADJ BORESIGHT RETICLE LEFT	RMFCD TO HMD	
		L	HMD ON / OFF						
	RIGHT		CYCLE TAD CENTRE	LASER / IR TOGGLE	GUNSIGHT / PROFILE CYCLE	A-A PROFILE CYCLE	ADJ BORESIGHT RETICLE RIGHT	CYCLE HMCS PROFILES	
		L	SLAVE TGP TO HMCS LOS					SLAVE MAV TO HMCS	SLAVE TGP TO HMCS
T M S	FWD		HOOK SYMBOL	AREA / POINT TRACK*	TDC GROUND STABILIZE	CONIC SCAN	TRACK	HOOK SYMBOL	
		L	Set SOI as SPI generator ("Make SPI")						
	AFT		UNHOOK SYMBOL	INR TRACK*	SET SPI SUBMODE*	BREAK LOCK	GROUND STAB	UNHOOK SYMBOL	
		L	RESET SPI TO STEERPOINT						
	LEFT		ACKNOWLEDGE WCN (warnings, cautions, notes) on HUD & MFCDs						
		L	BROADCAST SPI						
	RIGHT		CREATE MARKPOINT				CREATE MARK	CREATE MARKPOINT	
		L	MAKE LAST MARKPOINT SPI						
			TAD	TGP	HUD	AIM-9	MAV	HMCS	
C H I N A	FWD		FOV EXP*	FOV	SET MAV AS SOI*	UNCAGE*	FOV*	FOV	
		L	SLAVE ALL TO SPI				SLAVE AIM-9 TO TGP LOS*	SLAVE ALL TO SPI	
	AFT		RESET CURSOR	LSS TOGGLE	CAGE TDC TO TVV	RE-CAGE / MANUAL SEQUENCE		CAGE HDC TO ±	
		L	SLAVE TGP TO STEERPOINT						
B O A T	FWD		TGP FLIR BHOT					BLACK HOT LMAV: CODE	
	AFT		TGP FLIR WHOT					WHITE HOT LMAV: CURSOR	
	CTR		TGP CCD					HOLD 2s: FORCE CORRELATE	


CMS	LONG – NEXT PROG ▲ FWD – 1 FLARE		RIGHT ► 6 CHAFF
	PRESS (Z) – RUN/STOP PROG LONG – ECM TOGGLE		
	▼ AFT – 1 CHAFF LONG – PREV PROG		
◀ LEFT 6 FLARES			

C O O L I E	UP	SOI HUD	
		L	MSG QUICKLOOK
	DOWN	SOI HMCS	
		L	DSMS QUICKLOOK
	LEFT	CYCLE LMFC D	
		L	SOI LMFC D
	RIGHT	CYCLE RMFC D	
		L	SOI RMFC D

P I N K Y	FWD	DEFAULT	E X T L I G H T S
	AFT	MANUAL	
	CTR	OFF	

* - the actual in-game function that doesn't correspond to the manual.
In-strikethrough - the function is listed in the manual, but doesn't work in DCS.

BOXED ITEMS = A-10C II ONLY



BOMBS

- Mk-82 500 lbs
- Mk-82 AIR ballute 500 lbs
- Mk-84 2000 lbs
- GBU-12 laser 500 lbs
- GBU-10 laser 2000 lbs
- GBU-38 JDAM 500 lbs
- GBU-54B JDAM+laser 500 lbs
- GBU-31(V)1/B JDAM 2000 lbs
- GBU-31(V)3/B JDAM 2000 lbs penetrator warhead

CLUSTER:

- CBU-87 soft targets
- CBU-97 anti-armour seeker
- CBU-103 WCMD soft targets
- CBU-105 WCMD anti-armour skr

MISC / TRAINING:

- LUU-2 parachute flares
- BDU-33 025 lbs
- BDU-50LD 500 lbs
- BDU-50HD ballute 500 lbs
- BDU-50LGB laser 500 lbs

A-G MISSILES

- M151 HE APKWS laser soft targets
- M282 MPP APKWS laser penetrator

MAVERICK:

- AGM-65D IIR 125 lbs, no FC
- AGM-65G IIR 300 lbs
- AGM-65H CCD 125 lbs
- AGM-65K CCD 300 lbs
- AGM-65L CCD laser 300 lbs

MISC / TRAINING:

- TGM-65D (IIR)
- TGM-65G (IIR)
- TGM-65H (CCD)
- CATM-65K (CCD)

A-A MISSILES

- AIM-9L Sidewinder
- AIM-9M Sidewinder
- MISC / TRAINING: Captive AIM-9M

ROCKETS

- M151 HE soft targets
- MK5 HE(AT) anti-armour
- MISC / TRAINING: M257 parachute flares
- M274 smoke
- M156 white phosphorus
- Mk1 practice
- Mk 61 practice
- WTU-1/B practice

PODS / TANKS

- AN/AAQ-28 Litening (St 2, 10)
- ALQ-131 jammer (St 1, 11)
- ALQ-184 jammer (St 1, 11)
- ALQ-184 Long jammer (St 1, 11)
- Fuel tank FT600 (St 4, 6, 8)
- MISC / TRAINING: AN/ASQ-T50 ACMI pod (St 1,11)
- MXU-648 Travel pod
- Smokewinder

CONVERTING NAV WIND (EDITOR / BRIEFING) TO METEO

BRIEFING LAYER EXAMPLE:

At 2000m 4 m/s, 115°. Ground temp +10°C

(2000m × 3) + 10% = 6600 feet, round up to 7000

(4 m/s × 2) = 08 knots

(To 115° true + 180°) - 6° magvar* = From 289° mag

(2°C for every 1000 feet of altitude) × 7 = 14°C

+10°C - 14°C = -4°C at 7000 ft

CONVERSION RESULT:

Layer at 7000ft: 289° / 08 kts / -4°C

APPLYING A-10C WIND CORRECTION LAYER

CDU > SYS > "LASTE" > "WIND":

ALT 07 WIND 28908 TEMP 4 (LSK to change to -4)

* Caucasus -6° Nevada -10° Normandy +1°
Syria -4° Persian Gulf / Marianas / The Channel 0°
South Atlantic -2° (islands) / -7° to -12° (mainland)

Note: due to DCS interpolation, wind at 500m / 1700 ft is twice as strong as at the ground level


CMS PROGRAMS

- A 20 CHAFF SLOW < OLD RDR
- B 20 CHAFF FAST < NEW RDR
- C 40 FLARE SLOW < INFRARED
- D 20 CHAFF SLOW < MIXED OR
20 FLARE SLOW < UNKNOWN
- E 20 CHAFF FAST
20 FLARE FAST
- F 40 CHAFF SLOW
40 FLARE SLOW
- G 40 CHAFF FAST
40 FLARE FAST
- H 1 CHAFF
- I 2 CHAFF
- J 1 FLARE
- K 2 FLARE
- L 20 CHAFF SLOW
- M 20 FLARE SLOW

JAMMER MODES

- AIR
AIRBORNE
RADARS
- SAM 1
OLDER
RADAR SAMs
SA-3, SA-6, SA-8 etc.
- SAM 2
NEWER
RADAR SAMs
SA-10, SA-11, SA-15,
SA-19 etc.
- AAA
ANTI-AIRCRAFT
GUNS
SHILKA, GEPARD etc.

1. LANDING GEAR HANDLE
2. FLAP POSITION INDICATOR
3. HUD MODE DAY/NIGHT
4. LASER ARM
5. ANTI-SKID
6. LAND/TAXI LIGHTS
7. LEFT MFCD OFF/DAY/NIGHT
8. MASTER ARM
9. GUN/PAC ARM
10. EXTERNAL STORES JETTISON
11. ACCELEROMETER (RESET)
12. AHCP (ARMAMENT/ HUD CONTROL PANEL)
13. UFC (UP FRONT CONTROLLER)
14. CMSC (CNTRMEAS. SET CONTROL)
15. ALTIMETER (BARO PRESSURE)
16. RIGHT MFCD OFF/DAY/NIGHT
17. INTERSTATE TURBINE TEMP (ITT)
18. ENGINE CORE RPM
19. APU RPM
20. FUEL IND TEST
21. FUEL DISPLAY SELECTOR




LEFT CONSOLE

32. SEAT HEIGHT ADJUSTMENT
33. EMERGENCY BRAKE HANDLE
34. SIGNAL LIGHTS TEST & FIRE DET. / BLEED AIR LEAK TEST
35. SAS (STABILITY AUGMENTATION SYSTEM)
36. T/O TRIM BUTTON
37. IFF CONTROL PANEL
38. EMERGENCY FLIGHT CONTROL PANEL
39. INTERCOM VOLUME CTRL
40. ARC-186 VHF FM RADIO
41. ARC-164 UHF RADIO
42. ARC-186 VHF AM RADIO (WARTHOG ONLY)
43. ARC-210 VHF/UHF RADIO (TANK KILLER ONLY)
44. EJECTION SEAT ARM
45. EAC SWITCH (LASTE PANEL)
46. FLAP LEVER
47. APU START SWITCH
48. FUEL SYSTEM CONTROLS
49. AIR REFUEL CONTROL HANDLE
50. REFUELING LIGHT RHEOSTAT

RIGHT CONSOLE

51. CMSP (COUNTERMEASURES SET PROCESSOR) / EWMU
52. CAUTION ANNUNCIATION PANEL
53. CDU (CONTROL DISPLAY UNIT)





QUICKSTART SEQUENCE

41 Both | 40 TR | 42 or 43 TR | 64, 66 | Req. by Maple Flag: 34, 36, 20, 62 | 47 > wait 30s > 67 | 54 |
 L throttle IDLE (RAlt+Home) > wait 50s > R throttle IDLE (RCtrl+Home) | ON: 28, 29, 30, 31 | 7, 16 |
 46 MVR (half) | 51 as desired | 35 all four | 53 > wait for align '4.0 0.8' > then press LSK 'NAV' |
 On either display > LSK 'LOAD ALL' | 24 | 45 | 57 | 69 | 44 | 60 | 4 ARM | 5 | OFF: 67, 47 |
 Radio menu > request chocks removal

KNEEBOARD SUITE

A-10C/C II



CHECKLISTS, Pt. 1
2

CHECKLISTS, Pt. 2
3

RWR THREATS
4

HOTAS TABLE
5

ORDNANCE. WIND CORRECTION.
6

COCKPIT DIAGRAM. QUICKSTART.
7

“LOAD DSMS” OR “LOAD ALL” MUST BE PERFORMED AFTER EACH REARMING

Max IN-FLIGHT weight: 51,000 lbs.
Max TAXI / TAKEOFF / LAND weight: 46,000 lbs.
At near max taxi weight prefer wide turns at max 5 kts. Limit sharp turns to max 3 kts.

INT CHECK / PRIOR TO ENGINE START

- 1 UHF radio ARC-164 rmb BOTH, set
- 2 PINKY switch AFT exterior lights manual
- 3 Accelerometer Reset
- 4 Exterior and interior lights Set
- 5 Battery / Inverter PWR / rmb STBY
- 6 Flap lever Set to indicated flap position

FIRE DETECT TEST. SIGNAL LIGHTS TEST.
OXY IND TEST. FUEL IND TEST.
FUEL DISPLAY SELECTOR - SET AS REQUIRED.

- 7 APU switch START (ready within 30sec)
- 8 APU GEN switch PWR
- 9 (AAP) CDU, EGI ON

FOR FAST ALIGN (90 sec): WITHIN 30 sec AFTER COMPLETION OF CDU STARTUP TEST PRESS
CDU LSK “INS” > “ALT ALIGN” > “FAST”
VERIFY ASTERISK NEXT TO “*FAST”

STARTING ENGINES

- 1 Left throttle IDLE

WAIT FOR THE “ENG START CYCLE” LIGHT TO GO OFF BEFORE STARTING THE NEXT ENGINE. SHOULD THE RIGHT ENGINE BE STARTED FIRST, PULL THE EMERGENCY BRAKE HANDLE.

- 2 Right throttle IDLE

BEFORE TAXIING

- 1 VHF radios ARC-186 TR, set
- 2 VHF/UHF radio ARC-210 TR, set
- 3 IFF Set, MASTER - STBY
- 4 Emergency brake handle Full forward
- 5 CMSP Set, MODE - STBY
- 6 TACAN / ILS T/R, set / rmb PWR
- 7 Takeoff trim button Hold 2 sec
- 8 CDU Verify align “4.0 0.8” or “1.4 7.2”
LSK “NAV”
- 9 NMSP EGI ON
STR PT, ANCHR, or TCN as required

BEFORE TAXIING (CONT’D)

- 10 IFFCC switch rmb TEST, then UFC ENT
to initiate test (50 sec)
- 11 JTRS switch ON
- 12 CICU switch ON
- 13 MFCD L/R rmb As required
- 14 MFCD “DTS UPLOAD” page “LOAD ALL”
- 15 TGP switch As required
- 16 SAI knob Hold rmb and drag to uncage
- 17 SAS Engage
- 18 IFFCC switch Verify “Testing complete”
rmb ON
- 19 Altimeter Set
- 20 APU GEN OFF prior to APU shutdown
- 21 APU switch OFF
- 22 Ladder / Chocks Stowed / Removed
- 23 EAC switch ARM
- 24 HMCS Power switch rmb ON
- 25 Nosewheel steering Engage

BEFORE TAKEOFF

- 1 Flaps Set for takeoff (7° MVR)
- 2 Speed brakes CLOSED
- 3 IFF As required
- 4 Oxygen, defog, deice As required
- 5 Canopy / Seat Closed, locked / ARMED
- 6 Exterior lights As required

LINEUP CHECK

- 1 Anti-skid switch ANTI-SKID
- 2 Pitot heat switch PITOT HEAT

Disengage NWS at about 70 kts.
Flaps up 10 knots above takeoff speed.

EXT. LIGHTS	POSIT	ANTICOL	FORMATION	LAND/TAXI
GROUND	FLASH	OFF	ON DURING NIGHT OPS	AS REQUIRED
RWY ENTRY	STEADY	ON		

Lat Long Decimal SEMI-PRECISE	DD°MM.mmm E(0)41°47.878 Lat Long Decimal Minutes / LLDM	F10 map ✓
4+4 DCS JTAC SEMI-PRECISE	BB [CCCD] KM [9087]	[EEEF] [7280]
5+5 MGRS PRECISE	AAA BB [CCCD] 38T KM [90874]	[EEEFF] [72809]
Trailing zeros to JTAC's will be auto-added on entry		

DESCENT / BEFORE LANDING	
1	Altimeter Check
2	Defog, deice As required
3	Anti-skid switch ANTI-SKID
4	NMSP PTR switch (ADI bars) ... As required
5	Landing lights As required
6	NVIS / NVGs As required / Stow
AFTER CLEARING RUNWAY	
1	Anti-skid switch OFF
2	Seat / Canopy SAFE / As desired
3	TACAN, ILS OFF
4	IFF MASTER - STBY
5	HUD night/day filter DAY
6	Landing/taxi lights As required
7	CMSP all systems and MODE OFF
8	Pitot heat switch / Defog / Deice OFF
9	Position lights Flash
10	Anti-collision lights OFF
11	Flaps As required
ENGINE SHUTDOWN	
1	Chocks Set (<i>hold brakes until set</i>)
2	HMCS Power switch <i>lmb</i> OFF
3	IFF MASTER - OFF
4	SAI knob <i>Pull and scroll to cage</i>
5	Master Arm, Gun/Pac, Laser <i>lmb</i> SAFE
6	TGP, CICU, JTRS, IFFCC <i>rmb</i> OFF
7	MFCD L/R OFF
8	(AAP) EGI, CDU OFF
9	Seat <i>Hold lmb</i> Full up
LEFT ENGINE SHUTDOWN AFTER 5 min AT IDLE. TAXI TIME AT CORE RPM <80% MAY BE INCLUDED. DO NOT SHUTDOWN IF THE APU IS RUNNING.	
RIGHT ENGINE SHUTDOWN ONCE LEFT ENGINE CORE RPM IS BELOW 5% AND ITT IS BELOW 200°C.	
10	Left throttle OFF
11	Right throttle OFF
12	Inverter, Battery <i>rmb</i> OFF
13	VHF, UHF, VHF/UHF radios ALL OFF
14	Oxygen SUPPLY lever OFF
15	Interior, Exterior, Emergency lights ... OFF

AFTER TAKEOFF — PRE STRIKE — POST STRIKE	
FIRE CONTROL	• AHCP switches
	• DSMS
	• Laser codes
	• MAV prepare
ENGINES	• Gauges
	• Fuel
NAVIGATION	• AAP knobs
	• NMSP, HSI
COMMS	• Radios
EMITTERS	• Exterior lights
	• IFF set / M-3, M-C
	• TACAN
	• ECM
	• Chaff, Flare

AIR REFUELING	KC-135
HOT ARMAMENT SAFETY CHECK	
1	Master Arm, Gun/Pac, Laser SAFE
2	“DSMS” page Deselect all stations EO PWR OFF
PRECONTACT CHECKS	
1	IFF / TACAN / ECM STBY / A/A REC / OFF
2	Refueling light rheostats ON
3	Exterior lights As required
4	Fill disable switches As required
5	Air refuel control OPEN
6	READY light Verify ON
POST REFUELING (NWS/AR to disconnect)	
1	Air refuel control CLOSED
2	TACAN, IFF, Exterior lights As required

PRIOR TO FARP ENTRY	HOT REFUELING
“AFTER CLEARING RUNWAY” - COMPLETE	
APU GEN, APU - OFF	DE-ARMING - COMPLETE
	APU GEN or APU - OFF
MASTER ARM - SAFE	TGP - OFF
GUN/PAC, LASER - SAFE	
TGP - OFF	
“DSMS” PAGE - DESELECT ALL STATIONS, EO PWR OFF	
PRIOR TO REFUELING	
CANOPY - AS REQUIRED	CANOPY - AS DESIRED
FUEL DISPLAY SELECTOR - MAIN	
TANK GATE SWITCH - CLOSED	
After refueling: Taxi clear of refueling area and configure aircraft as required by mission plan.	

4

RWR THREATS

ALL RANGES WERE MEASURED FOR THE F/A-18C. TREAT AS ESTIMATES.

A-10C/C II

DimOn

14	F-14A/GR/B	123 88	21	MiG-21Bis	12 09	37	AJS-37 Viggen	2 06	JF	JF-17	23 46
15	F-15C	123 49	23	MiG-23MLD	12 14	50	A-50 / KJ-2000	AWACS	M2	M-2000C	12 26
	F-15E	23 49	25	MiG-25PD	12 25	64	AH-64D BLK.II	3 05		Mirage 2000-5	123 24
	F-15E S4+	123 49	29	MiG-29A/G	12 38		(with or w/o MMA)		U	A-6E	2 04
16	F-16A	123 38		MiG-29S	123 33	E2	E-2D	AWACS		AH-64D (old)	3 05
	F-16A MLU	23 38		Su-27/33	12 32	E3	E-3A	AWACS		C-101CC	2 04
	F-16C/CM	23 38		J-11A	123 32	F1	Mirage F1	12 22		H-6J	BOMBER
18	F/A-18A	12 27	30	Su-30	123 37	F2	Tornado GR4	2 04		Tornado IDS	2 04
	F/A-18C	123 42	31	MiG-31	12 37	F4	F-4E-45MC	12 27		Tu-95MS	BOMBER
19	MiG-19P	2 03	34	Su-34	123 35	F5	F-5E/E-3/FC	2 04		SH-60B	HEL0

SURFACE					NAVAL				
S	Nebo 1L13 / Nebo 55G6 / AN/FPS-117			EWR	15	Project 22160 Tor-M2	CORVETTE	C	10/39
	Flat Face B	[2-3-5]		SR	40	LHA-1 Tarawa	CV	F	08/13
BB	Big Bird	[10]		long-range SR	49	Oliver Hazard Perry	FRIGATE	C	26/++
CS	Clam Shell	[10]		low-altitude SR	AE	Arleigh Burke	DESTROYER	C	80/++
DE	Dog Ear Sborka	[13-15-19]		MCC-SR		Ticonderoga	CRUISER	C	37/++
FC	Fire Can SON-9			AAA FDR	FR	CV-59 Forrestal	CV	C	10/24
HQ	HQ-7B	[7]		SR	HN	Type 052C	DESTROYER	C	90/++
SD	Snow Drift	[11]		SR		Pyotr Velikiy	CRUISER	C	86/++
TS	Tin Shield	[5-10]		SR	HP	Grisha (2025)	CORVETTE	C	07/17
U	Freya / Würzburg			WWII Assets Pack EWR		Grisha (old)	TO BE REMOVED	C	08/15
	Silkworm			anti-ship SR	IV	HMS Invincible	CV	C	47/++
	Tall King	[5]		SR	LC	La Combattante	FAST ATTACK CRAFT	E	04/10
2	C 27/++	SA-2 Guideline	S-75	Fan Song TR	MR	Type 052B	DESTROYER	C	31/++
				Amazonka RF		Type 054A	FRIGATE	C	33/++
3	C 13/++	SA-3 Goa	S-125	Low Blow TR	PS	Type 071 Amphib.dock	TRANSPORT	E	06/10
5	C 160/+	SA-5 Gammon	S-200	Square Pair TR		Molniya	CORVETTE	E	03/09
6	C 18/27	SA-6 Gainful	Kub	Straight Flush STR	SC	LS Ropucha	BDK-775 TRANSPORT	E	06/09
7	E 10/18	HQ-7B		TELAR	SS	CVN-71 Roosevelt	CV	C 10/24 F 08/13	
8	C 07/17	SA-8 Gecko	Osa	TELAR		CVN-72 Lincoln	CV		
10	C 48/++	SA-10 Grumble	S-300PS	Flap Lid A & B TR		CVN-73 Washington	CV		
11	C 29/++	SA-11 Gadfly	Buk	Fire Dome TELAR		CVN-74 Stennis	CV		
13	F 03/12	SA-13 Gopher	Strela-10M	TELAR		CVN-75 Truman	CV		
15	C 09/20	SA-15 Gauntlet	Tor	TELAR	SW	Kuznetsov 2017	CV	C	08/20
	C 10/39	SA-15 Gauntlet	M2 Tor-M2	TELAR		Kuznetsov (old)	CV	C	08/20
19	E 05/12	SA-19 Grison	Tunguska	SPAAW	T2	Moskva	CRUISER	C	48/++
22	C 11/33	SA-22 Greyhound	Pantsir-S1	SPAAW		Project 22160	CORVETTE	E	04/13
A	E 03/10	Gepard		SPAAA	TP	Condell-class	FRIGATE	E	02/07
	E 02/06	Vulcan		SPAAA		CNS Almirante Condell / CNS Almirante Lynch			
	E 02/07	ZSU-23-4 Shilka		SPAAA		Leander-class	FRIGATE	E	06/11
CR	E 02/05	LPWS Centurion	Phalanx	C-RAM		HMS Achilles / HMS Andromeda / HMS Ariadne			
HK	C 14/++	Hawk		CWAR / SR / TR		Neustrashimy	FRIGATE	C	08/20
IT	F 22/++	IRIS-T	SLM	STR		Rezky	FRIGATE	C	08/15
NS	C 13/35	NASAMS AIM-120B		SR	U	ARA Veinticinco de Mayo	CV	E	02/10
	C 13/40	NASAMS AIM-120C		SR		Essex Class 1944	CV	E	02/07
P	C 60/++	Patriot		STR		Type 021-1	MISSILE BOAT	E	02/12
RO	C 05/20	Roland		EWR / ADS					
RP	E 05/10	Rapier with Blindfire Radar		TR					
RT	E 05/10	Rapier with or without Tracker		LN					
U	E 10/20	HQ-7 'Player'	AI- or user-controlled	TELAR					

L = LONG PRESS			TAD	TGP	HUD	AIM-9	MAV
D M S	FWD		ZOOM+	ZOOM+ TST: FOCUS+	NEXT STEERPOINT		ADJUST BORESIGHT RETICLE UP
	AFT		ZOOM-	ZOOM- TST: FOCUS-	PREV STEERPOINT		ADJUST BORESIGHT RETICLE DOWN
	LEFT			FLIR AUTOFOCUS	GUNSIGHT / PROFILE CYCLE	A-A PROFILE CYCLE	ADJUST BORESIGHT RETICLE LEFT
		L	BROADCAST SPI				
	RIGHT		CENTER / DEPRESSED	LASER / IR TOGGLE	GUNSIGHT / PROFILE CYCLE	A-A PROFILE CYCLE	ADJUST BORESIGHT RETICLE RIGHT
		L		LSS TOGGLE			
T M S	FWD		HOOK SYMBOL	AREA / POINT TRACK	TDC GROUND STABILIZE	CONIC SCAN	TRACK
		L	Set SOI as SPI generator ("Make SPI")				
	AFT		UNHOOK SYMBOL	INR TRACK	SET SPI SUBMODE	BREAK LOCK	GROUND STAB
		L	RESET SPI TO STEERPOINT				
	LEFT		ACKNOWLEDGE WCN (warnings, cautions, notes) on HUD & MFCDs				
		L					SPACE STABILIZE
	RIGHT		CREATE MARKPOINT			CREATE MARK	CREATE MARKPOINT
			TAD	TGP	HUD	AIM-9	MAV
C H I N A	FWD		FOV		SET MAV AS SOI	UNCAGE	FOV
		L	SLAVE ALL TO SPI			SLAVE AIM-9 TO TGP LOS	SLAVE ALL TO SPI
	AFT		RESET CURSOR	BORESIGHT TGP	CAGE TDC TO TVV	MISSILE STEP	
		L	SLAVE TGP TO STEERPOINT				
B O A T	FWD		TGP FLIR BHOT				BLACK HOT
	AFT		TGP FLIR WHOT				WHITE HOT
	CTR		TGP CCD				HOLD 2s: FORCE CORRELATE

CMS

LONG – NEXT PROG
▲ FWD – 1 FLARE

PRESS (Z) –
RUN/STOP PROG
LONG – ECM TOGGLE

▼ AFT – 1 CHAFF
LONG – PREV PROG

RIGHT ►
6 CHAFF

C
O
O
L
I
E

UP

L SOI HUD
MSG QUICKLOOK

DOWN

L SWAP MFCDs
DSMS QUICKLOOK

LEFT

L CYCLE LMFCDD
SOI LMFCDD

RIGHT

L CYCLE RMFCDD
SOI RMFCDD

P
I
N
K
Y

FWD

DEFAULT

AFT

MANUAL

CTR

OFF

E
X
T

L
I
G
H
T
S

The diagram illustrates the cockpit control panel layout, divided into three main sections: CMS, COOLIE, and PINKY.

CMS (Crew Member Station):

- Top Left:** LONG - NEXT PROG (Red text), ▲ FWD - 1 FLARE (Green text).
- Top Right:** RIGHT ► 6 CHAFF (Green text).
- Bottom Left:** ◀ LEFT 6 FLARES (Green text).
- Bottom Center:** PRESS (Z) - RUN/STOP PROG (Green text), LONG - ECM TOGGLE (Red text), ▼ AFT - 1 CHAFF (Green text), LONG - PREV PROG (Red text).

COOLIE (Cooling Unit):

- UP:** SOI HUD (Blue text), L MSG QUICKLOOK (Blue text).
- DOWN:** SOI HMCS (Blue text), L DSMS QUICKLOOK (Blue text).
- LEFT:** CYCLE LMFCF (Blue text), L SOI LMFCF (Blue text).
- RIGHT:** CYCLE RMFCF (Blue text), L SOI RMFCF (Blue text).


PINKY (Pilot's Instrument):

- FWD:** DEFAULT (Blue text).
- AFT:** MANUAL (Blue text).
- CTR:** OFF (Blue text).

EXT LIGHTS (External Lights):

- Default position: DEFAULT (Blue text).
- Manual position: MANUAL (Blue text).
- Off position: OFF (Blue text).

BOXED ITEMS = A-10C II ONLY



BOMBS

- Mk-82 500 lbs
- Mk-82 AIR ballute 500 lbs
- Mk-84 2000 lbs
- GBU-12 laser 500 lbs
- GBU-10 laser 2000 lbs
- GBU-38 JDAM 500 lbs
- GBU-54B JDAM+laser 500 lbs
- GBU-31(V)1/B JDAM 2000 lbs
- GBU-31(V)3/B JDAM 2000 lbs penetrator warhead

CLUSTER:

- CBU-87 soft targets
- CBU-97 anti-armour seeker
- CBU-103 WCMD soft targets
- CBU-105 WCMD anti-armour skr

MISC / TRAINING:

- LUU-2 parachute flares
- BDU-33 025 lbs
- BDU-50LD 500 lbs
- BDU-50HD ballute 500 lbs
- BDU-50LGB laser 500 lbs

A-G MISSILES

- M151 HE APKWS laser soft targets
- M282 MPP APKWS laser penetrator

MAVERICK:

- AGM-65D IIR 125 lbs, no FC
- AGM-65G IIR 300 lbs
- AGM-65H CCD 125 lbs
- AGM-65K CCD 300 lbs
- AGM-65L CCD laser 300 lbs

MISC / TRAINING:

- TGM-65D (IIR)
- TGM-65G (IIR)
- TGM-65H (CCD)
- CATM-65K (CCD)

A-A MISSILES

- AIM-9L Sidewinder
- AIM-9M Sidewinder
- MISC / TRAINING: Captive AIM-9M

ROCKETS

- M151 HE soft targets
- MK5 HE(AT) anti-armour
- MISC / TRAINING: M257 parachute flares
- M274 smoke
- M156 white phosphorus
- Mk1 practice
- Mk 61 practice
- WTU-1/B practice

PODS / TANKS

- AN/AAQ-28 Litening (St 2, 10)
- ALQ-131 jammer (St 1, 11)
- ALQ-184 jammer (St 1, 11)
- ALQ-184 Long jammer (St 1, 11)
- Fuel tank FT600 (St 4, 6, 8)
- MISC / TRAINING: AN/ASQ-T50 ACMI pod (St 1,11)
- MXU-648 Travel pod
- Smokewinder

CONVERTING NAV WIND (EDITOR/BRIEFING) TO METEO

BRIEFING LAYER EXAMPLE:

At 2000m 4 m/s, 115°. Ground temp +10°C

(2000m × 3) + 10% = 6600 feet, round up to 7000
(4 m/s × 2) = 08 knots
(To 115° true + 180°) - 6° magvar* = From 289° mag
(2°C for every 1000 feet of altitude) × 7 = 14°C
+10°C - 14°C = -4°C at 7000 ft

CONVERSION RESULT:

Layer at 7000ft: 289° / 08 kts / -4°C

APPLYING A-10C WIND CORRECTION LAYER

CDU > SYS > "LASTE" > "WIND":

ALT 07 WIND 28908 TEMP 4 (LSK to change to -4)

* Caucasus -6° Nevada -10° Normandy +1°
Syria -4° Persian Gulf / Marianas / The Channel 0°
South Atlantic -2° (islands) / -7° to -12° (mainland)

Note: due to DCS interpolation, wind at 500m / 1700 ft is twice as strong as at the ground level


CMS PROGRAMS

- A 20 CHAFF SLOW < OLD RDR
- B 20 CHAFF FAST < NEW RDR
- C 40 FLARE SLOW < INFRARED
- D 20 CHAFF SLOW < MIXED OR
20 FLARE SLOW < UNKNOWN
- E 20 CHAFF FAST
20 FLARE FAST
- F 40 CHAFF SLOW
40 FLARE SLOW
- G 40 CHAFF FAST
40 FLARE FAST
- H 1 CHAFF
- I 2 CHAFF
- J 1 FLARE
- K 2 FLARE
- L 20 CHAFF SLOW
- M 20 FLARE SLOW

JAMMER MODES

- AIR
AIRBORNE
RADARS
- SAM 1
OLDER
RADAR SAMs
SA-3, SA-6, SA-8 etc.
- SAM 2
NEWER
RADAR SAMs
SA-10, SA-11, SA-15,
SA-19 etc.
- AAA
ANTI-AIRCRAFT
GUNS
SHILKA, GEPARD etc.

1. LANDING GEAR HANDLE
2. FLAP POSITION INDICATOR
3. HUD MODE DAY/NIGHT
4. LASER ARM
5. ANTI-SKID
6. LAND/TAXI LIGHTS
7. LEFT MFCD OFF/DAY/NIGHT
8. MASTER ARM
9. GUN/PAC ARM
10. EXTERNAL STORES JETTISON
11. ACCELEROMETER (RESET)
12. AHCP (ARMAMENT / HUD CONTROL PANEL)
13. UFC (UP FRONT CONTROLLER)
14. CMSC (CNTRMEAS. SET CONTROL)
15. ALTIMETER (BARO PRESSURE)
16. RIGHT MFCD OFF/DAY/NIGHT
17. INTERSTATE TURBINE TEMP (ITT)
18. ENGINE CORE RPM
19. APU RPM
20. FUEL IND TEST
21. FUEL DISPLAY SELECTOR




LEFT CONSOLE

32. SEAT HEIGHT ADJUSTMENT
33. EMERGENCY BRAKE HANDLE
34. SIGNAL LIGHTS TEST & FIRE DET. / BLEED AIR LEAK TEST
35. SAS (STABILITY AUGMENTATION SYSTEM)
36. T/O TRIM BUTTON
37. IFF CONTROL PANEL
38. EMERGENCY FLIGHT CONTROL PANEL
39. INTERCOM VOLUME CTRL
40. ARC-186 VHF FM RADIO
41. ARC-164 UHF RADIO
42. ARC-186 VHF AM RADIO (WARTHOG ONLY)
43. ARC-210 VHF/UHF RADIO (TANK KILLER ONLY)
44. EJECTION SEAT ARM
45. EAC SWITCH (LASTE PANEL)
46. FLAP LEVER
47. APU START SWITCH
48. FUEL SYSTEM CONTROLS
49. AIR REFUEL CONTROL HANDLE
50. REFUELING LIGHT RHEOSTAT

RIGHT CONSOLE

51. CMSP (COUNTERMEASURES SET PROCESSOR) / EWMU
52. CAUTION ANNUNCIATION PANEL
53. CDU (CONTROL DISPLAY UNIT)



54. CDU & EGI SWITCHES (AAP: AVIONICS AUX. PANEL)
55. TACAN CONTROL PANEL
56. ILS CONTROL PANEL
57. HMCS (HELMET-MOUNTED CUEING SYSTEM) ON/OFF (TANK KILLER ONLY)

58. LIGHTING CONTROL PANEL
59. CANOPY LOCK LEVER
60. PITOT HEAT SWITCH
61. DEFOG / DEICE PANEL
62. OXY IND TEST BUTTON
63. OXYGEN SUPPLY LEVER
64. BATTERY SWITCH
65. EMERGENCY FLOOD LIGHTS SWITCH
66. INVERTER SWITCH
67. APU GEN SWITCH
68. CANOPY JETTISON
69. CANOPY CONTROL

QUICKSTART SEQUENCE

41 Both | 40 TR | 42 or 43 TR | 64, 66 | Req. by Maple Flag: 34, 36, 20, 62 | 47 > wait 30s > 67 | 54 | L throttle IDLE (RAlt+Home) > wait 50s > R throttle IDLE (RCtrl+Home) | ON: 28, 29, 30, 31 | 7, 16 | 46 MVR (half) | 51 as desired | 35 all four | 53 > wait for align '4.0 0.8' > then press LSK 'NAV-' | On either display > LSK 'LOAD ALL' | 24 | 45 | 57 | 69 | 44 | 60 | 4 ARM | 5 | OFF: 67, 47 |

Radio menu > request chocks removal