
USER MANUAL

SeaQ Snap Layout

Snap layouts for KDE Plasma 6.
Snap bar, screen edges, window magnet and keyboard shortcuts.



Version 1.9.0
KWin script for Plasma 6 · Wayland & X11

SeaQ
github.com/Swenix-dev/KDE-Snap-Layout

Contents

Everything SeaQ Snap Layout can do, page by page – from the first snap to your own layouts.

1 Introduction 3

2 The snap bar at a glance 4

3 Installation 5

4 Quick start – your first snap 6

5 Opening the settings 7

6 The settings editor 8

6.1 General · 6.2 Appearance · 6.3 Behavior & Animation · 6.4 Layouts · 6.5 Layout designer

6.6 Screen edges · 6.7 Window magnet · 6.8 Keyboard shortcuts · 6.9 About & Help

7 Key reference 19

8 Languages 20

9 Recommended values 21

10 Troubleshooting & FAQ 22

11 Files, uninstalling & license 23

How to read this manual

1 Orange numbers in a screenshot point to a control. The list below the picture explains each one.

Button Grey labels are text you see on the screen: buttons, switches, menu entries.

`command` Monospaced text is typed into a terminal.

Tip
Ideas that make daily use quicker.

Note
Background information worth knowing.


Important
Read this before you continue.

Screenshots
The pictures show the light Breeze color scheme in English. SeaQ Snap Layout always uses your own colors, window decoration and system language, so it may look slightly different on your desktop.

CHAPTER 1

1 Introduction

SeaQ Snap Layout brings snap layouts to KDE Plasma 6. Drag a window towards the top edge of the screen, a bar with layouts slides down, and you drop the window onto the zone where it should go. Since version 1.7 there are three more ways to snap – each one can be switched on and off on its own.



Drag, drop, done

No shortcuts to learn – it works with the mouse movement you already know.

Your own layouts

Six layouts ready to go, plus a designer for any split you like – up to 16 zones.

Fits your desktop

System, light or dark colors, any accent. The editor uses your color scheme, decoration and language.

Feels right

Distances, delays, slide speed and six motion curves – drag a snapped window out and it gets its old size back.

Screen edges

Push a window against an edge or corner: maximize, halves, quarters – and it fits around windows that are already snapped.

Window magnet

Windows stick to each other and to the screen edges while you move or resize them.

Keyboard shortcuts

20 actions – halves, quarters, thirds, maximize, center. Ready-made key schemes or your own keys.


Pure KWin script

No extra program running in the background. Install from the KDE Store with two clicks.

CHAPTER 2

2 The snap bar at a glance

The snap bar only appears while you move a window. It never takes space on your screen otherwise.




1. **Handle** – a small pill that appears first when the window gets close to the top. It tells you the bar is ready.
2. **Snap bar** – slides down once the cursor reaches the top edge. It always appears on the screen you are working on.
3. **Layout** – a small picture of your screen. The bar shows all layouts marked **In bar**.
4. **Zone** – one area of a layout. Hover it to select it.
5. **Highlighted zone** – drawn in the accent color. Releasing the mouse now snaps the window here.
6. **Name line** (optional) – shows the layout and zone name, e.g. "Four quarters · Zone 3".

The landing preview

While a zone is highlighted, a translucent rectangle in the accent color shows on the desktop exactly where the window will land – including gaps and panels. Move away from the bar and the preview disappears.

Built-in layouts



CHAPTER 3

3 Installation

SeaQ Snap Layout is a KWin script. It installs into your home folder, needs no administrator rights and adds no background program.

Requirement	Details
Desktop	KDE Plasma 6 (KWin 6) – Wayland or X11
Distribution	Any: Fedora, Arch, openSUSE, KDE neon, Kubuntu, Debian ...
Extra packages	None – everything it needs ships with Plasma

Option A – KDE Store (recommended)

1. Open **System Settings** → **Window Management** → **KWin Scripts**.
2. Click **Get New...** at the top right, search for **SeaQ Snap Layout** and click **Install**.
3. Tick the checkbox next to **SeaQ Snap Layout** and click **Apply**.

Option B – file from GitHub

1. Download `kdesnaplayout-<version>.kwinscript` from the **Releases** page.
2. In **KWin Scripts** click **Install from File...** and choose the file.
3. Tick **SeaQ Snap Layout** and click **Apply**.

Option C – terminal


```
# install
kpackagetool6 --type KWin/Script --install kdesnaplayout-1.9.0.kwinscript
# update to a newer version
kpackagetool6 --type KWin/Script --upgrade kdesnaplayout-1.9.0.kwinscript
# switch it on
kwriteconfig6 --file kwinrc --group Plugins --key kdesnaplayoutEnabled true
qdbus6 org.kde.KWin /KWin reconfigure
```

> **After an update: log out once**
> KWin keeps a loaded script in memory. After installing a new version, log out and back in so the new files are used. You can check the version on the **About & Help** page of the settings editor.

CHAPTER 4

4 Quick start – your first snap

Three movements, about two seconds.



1. **Grab a window** by its title bar and hold the left mouse button.
2. **Move it up.** About 140 px below the top edge a small handle appears. Keep going until the cursor touches the top edge – the snap bar slides down.
3. **Point at a zone.** It lights up in your accent color, and a preview on the desktop shows where the window will land.
4. **Let go.** The window fills exactly that zone.

Changed your mind?

Move the cursor away from the bar, or release the window anywhere outside it. Nothing is snapped and the bar slides back up.

Getting the old size back

Grab a snapped window and drag it away – it returns to the size it had before snapping. You can turn this off on the `General` page.

Which windows can snap?

Normal, resizable windows. Dialogs, fullscreen windows and apps on your exclusion list never show the snap bar.

More than one screen?

The bar opens on the screen under the cursor, and zones fill that screen's free area – panels are left uncovered.


Smoother snapping

Plasma has its own edge actions. SeaQ Snap Layout does the same and more, so turn Plasma's off: `System Settings` → `Window Management` → `Screen Edges` → untick `Maximize` and `Tile` for windows dragged to the edges (names vary slightly between Plasma versions). The editor shows an orange hint as long as they are on.

CHAPTER 5

5 Opening the settings

A KWin script has no app icon of its own. Its settings are reached through the gear icon in System Settings, which opens a small quick menu.



1. Open **System Settings** → **Window Management** → **KWin Scripts** and click the **gear icon** 1 next to **SeaQ Snap Layout**.
2. Click **Open Snap Layout settings editor** 2. The hint “Ready – click OK to open the settings editor.” appears.
3. Click **OK**. The settings editor opens within about a second.

Quick settings


3 **Snap bar colors** switches the snap bar between **System**, **Light** and **Dark** without opening the editor. Everything else – appearance, size, animation, behavior and your own layouts – lives in the settings editor.

> **Why the extra click?**
> System Settings only saves the quick menu when you press **OK** or **Apply**. SeaQ Snap Layout notices the saved button press and opens its editor. The button can be used as often as you like.

CHAPTER 6

6 The settings editor

One window, eight pages. Every change is saved and applied immediately – there is no Apply button.




1. **Title bar** – drag to move the window, double-click to maximize. Height, font and alignment follow your window decoration.
2. **Window buttons** – maximize/restore and close, in the order and style of your decoration.
3. **Name and version** of the installed script.
4. **Snap bar** – Appearance, Behavior & Animation and Layouts of the bar at the top edge.
5. **More ways to snap** – Screen edges, Window magnet and Keyboard shortcuts.
6. **Feature switches** – turn the snap bar, screen edges, window magnet and shortcuts on or off with one click.
7. **Page area** – settings are grouped in cards. `Recommended values` at the bottom of a page resets that page.

> **Matches your system**
>
> The editor uses your color scheme, accent color, window decoration and system language – and follows changes live while it is open.

SETTINGS EDITOR

6.1 General

Choose which ways to snap you want, control the previews and leave room between windows.



Setting	What it does	Default
1 **Features**	Four independent switches: **Snap bar**, **Screen edges**, **Window magnet**, **Keyboard shortcuts**. The arrow next to each one opens its page. The same switches sit at the bottom of the sidebar.	all on
2 **Previews**	**Snap bar preview** and **Screen edges preview**, each on its own – off means no preview at all. **Accent color** – off draws a neutral frame. **Pause KDE's edge tiling** hides KDE's own outline.	all on
3 **Restore the original size when dragging a window out**	A snapped window that you drag away gets its earlier size back – also after snapping with the edges or the keyboard.	On
Gap between windows	Space between neighbouring zones (0 – 48 px). Used by the bar, the edges, the shortcuts and – if you like – the magnet.	0 px
Gap to the screen edge	Space between the zones and the edges of the free screen area (0 – 48 px).	0 px
Excluded applications	Window classes that are never snapped – one per line (commas and semicolons work too). Not case-sensitive.	empty


Finding a window class

Open **System Settings** → **Window Management** → **Window Rules** → **Add New…** → **Detect Window Properties** and click the app window. The value under **Window class** (for example `krita` or `steam`) is what you enter here.

SETTINGS EDITOR

6.2 Appearance

Colors, size and shape of the snap bar. The live preview at the top shows every change at once.




1. **Preview** of the snap bar with your current settings.
2. **Color scheme** – **System** follows your Plasma colors; **Light** and **Dark** are fixed. Default: System.
3. **Use the system accent color** – highlights zones in your Plasma accent. Default: on.
4. **Color swatches** – twelve ready-made accents. Turn off ③ first.
5. **Custom color** – the rainbow circle opens a color picker (see below).
6. **Size & shape** – four sliders, see the table.
7. **Layouts per row** – 0 shows all layouts in one row; any other number wraps the bar into several rows.
8. **Show layout and zone names** under the thumbnails. Default: off.
9. **Test on screen** plays the snap bar on your desktop so you can judge the result.

Size & shape	What it does	Default	Range
Snap bar size	Scales the whole bar – handy on high-resolution screens.	100 %	60 – 200 %
Thumbnail width	Width of each layout picture; the height follows your screen's shape.	72 px	48 – 160 px
Corner radius	Roundness of the bar. 0 gives square corners.	8 px	0 – 24 px
Background opacity	How see-through the bar background is.	96 %	40 – 100 %


Colors and styles

A few combinations of the appearance settings.



Picking your own accent color

1. Turn off **Use the system accent color**.
2. Click the **rainbow circle** at the end of the swatches. The color picker opens below.
3. Choose the hue on the **strip**, then brightness and saturation in the **square**.
4. Or type an exact value such as `#3daee9` into the **hex field**.




> **Snap bar vs. editor colors**
> The color scheme and accent on this page only change the **snap bar**. The settings editor itself always uses your system colors.

SETTINGS EDITOR


6.3 Behavior & Animation

When the bar appears, when it hides again and how it moves. The default values are based on Windows 11.



Showing	What it does	Default	Range
A Trigger distance from the top edge	How close the cursor must get to the top edge before the full bar opens.	24 px	2 – 200 px
Show a small handle first	Shows the handle on the way up, so the bar never pops up by surprise.	On	On / Off
B Distance at which the handle appears	Distance from the top edge at which the handle appears.	140 px	20 – 400 px
C Active width along the top edge	Only this centered part of the top edge reacts. 100 % = the whole width.	100 %	10 – 100 %
Delay before showing	Waiting time before the bar opens. Prevents opening while passing by.	40 ms	0 – 600 ms

Hiding	What it does	Default	Range
D Distance before the bar hides again	How far you can move below the bar before it closes – a safety margin.	56 px	0 – 300 px
Delay before hiding	Waiting time after leaving that area before the bar slides up.	150 ms	0 – 1000 ms




1. **Showing** – see the table on the previous page.
2. **Hiding** – see the table on the previous page.
3. **Animation** – see below.
4. **Test animation** plays the bar with the current values.

Animation	What it does	Default	Range
E **How far the bar slides down**	Distance between the top of the free screen area and the bar when it is open.	12 px	0 – 150 px
Slide-in duration	How long the bar takes to slide down.	220 ms	0 – 1000 ms
Slide-out duration	How long it takes to slide back up. Shorter feels snappier.	150 ms	0 – 1000 ms
Motion curve	The character of the movement – see the curves below.	Smooth	6 curves
Fade in and out	Fades the bar while it slides.	On	On / Off

Motion curves

Each curve has a matching reverse for sliding back up, so hiding feels like showing played backwards.




Slow PC or remote desktop?
Set both durations to 0 ms and turn off fading – the bar then appears instantly.

SETTINGS EDITOR

6.4 Layouts

Choose which layouts appear in the snap bar and in which order.



1. **New layout** – creates a layout and opens the designer.
2. **Restore default layouts** – brings back the six built-in layouts. Asks first, because your own layouts and order are lost.
3. **Layout card** – a picture of the layout. **Double-click** to edit it.
4. **Drag handle ⠿** – drag a card to another place to change the order in the bar.
5. **Position** in the snap bar (1 = left).
6. **In bar** – untick to hide a layout from the bar without deleting it.
7. **Edit ✎** – opens the layout designer (shown on card 1).
8. **Duplicate** – copies the layout as a starting point for a variant (card 2).
9. **Delete** – removes the layout after a confirmation (card 3).


Changing the order

1. Press and hold the mouse button on a card.
2. Drag it onto the position where it should go – the other cards move aside.
3. Release. The new order is saved and used the next time the bar opens.

SETTINGS EDITOR

6.5 Layout designer

Split the screen any way you like – up to 16 zones per layout.



1. **Name** of the layout, shown on the card and in the name line.
2. **Split side by side** – cuts the selected zone into a left and a right half.
3. **Split top and bottom** – cuts the selected zone horizontally.
4. **Remove zone** – deletes the selected zone; its neighbour takes the space.
5. **Load template…** – starts from one of eleven ready-made layouts.
6. **Selected zone** – click a zone to select it. Number and size in % are shown inside. **Double-click** splits it along its longer side.
7. **Divider** – drag it to change the sizes of the zones on both sides.
8. **Zone counter** – shows how many of the 16 possible zones are used.
9. **Snap dividers** – dividers click into place at ¼, ⅓, ½, ⅔ and ¾.
10. **Cancel / Save** – discard or keep your changes.


Example: a large main area with two small zones on the right

1. Click **New layout** on the Layouts page and type a name, e.g. *Focus + 2*.
2. Click **Split side by side**, then drag the divider to ⅔.
3. Select the right zone and click **Split top and bottom**. Click **Save**.

MORE WAYS TO SNAP

6.6 Screen edges

Push a window against an edge or a corner of the screen and it fills that part. Works with or without the snap bar.



Edges – the middle of the left or right edge gives a half, the bottom edge the bottom half, the top edge maximizes (or what you choose).

Corners – the outer part of each edge (20 % by default) gives the quarter in that corner.

A small push – the window has to rest against the edge for 60 ms, so passing by does nothing.

Smart fill

The edges always look at what is already snapped. Halves and quarters never cover a snapped window, and the top edge only fills the free space above it.



Nothing snapped below → the top edge maximizes.



A quarter sits at the bottom → only the top half is filled.

Setting	What it does	Default	Range
Use screen edges	Main switch, independent of the snap bar.	On	On / Off
Top edge	What the top edge does.	Maximize	Maximize · Fullscreen · Top half · Off
Left and right edge	Half of the screen.	On	On / Off
Bottom edge	Bottom half.	On	On / Off
Corners	Quarter of the screen.	On	On / Off
Smart fill	Fit around windows that are already snapped.	On	On / Off
Distance to the edge	How close the cursor has to get to the edge.	4 px	1 – 40 px
Push delay	How long the window has to rest against the edge. 0 = at once.	60 ms	0 – 600 ms
Corner size	Part of each side that counts as corner.	20 %	5 – 40 %
Hold to fill	Held longer at the edge, grow up to the next window.	On · 700 ms	200 – 2000 ms

Hold to fill · KDE's own tiling
Keep the window 0.7 s longer at the edge and it grows up to the next window. KDE's own edge tiling pauses meanwhile – your KDE settings stay unchanged.

MORE WAYS TO SNAP

6.7 Window magnet

While you move or resize a window, its edges stick to nearby windows and to the screen edges. Works without the snap bar and without the screen edges.

Setting	What it does	Default	Range
Use the window magnet	Main switch.	On	On / Off
Snap distance	How close an edge has to come before it clicks into place. Larger = stronger magnet.	16 px	2 – 64 px
Resistance against overlapping	A window stops at the edge of another one and only lets go once you push it this far in. 0 = windows can overlap freely.	48 px	0 – 200 px
Stick to other windows	Edges line up with the edges of other visible windows on the same screen.	On	On / Off
Stick to the screen edges	Edges line up with the free screen area (panels are respected).	On	On / Off
Also while resizing	The edge you drag sticks too – the other edges stay where they are.	On	On / Off
Keep the gap between windows	Windows stop at **Gap between windows** from the General page instead of touching.	Off	On / Off

Sticky edges

Windows that touch share their edge. Resize one of them and the others follow live – nothing overlaps, no gap opens, and the gap between them stays as it was.

Setting	What it does	Default
Resize touching windows together	The shared edge of every window that faces the resized one moves along. Edges on the screen border are never linked.	On
Keep stacked windows in line	Windows above each other keep their left and right edges together, windows side by side their top and bottom edges.	On
Shake to let go	Shake the mouse while resizing and the other windows jump back.	On
Fade the other windows	While resizing, windows that do not follow are shown transparent.	On


Plasma has a magnet too

While the magnet is on, SeaQ Snap Layout pauses Plasma's own snap zones so only one magnet pulls at a window (**Pause KDE's snap zones while the magnet is on**). Your KDE settings are not changed – switch it off, disable or remove the script and Plasma's snapping is back.

MORE WAYS TO SNAP

6.8 Keyboard shortcuts

Snap the active window with the keyboard. These are normal KDE global shortcuts – you also find them in System Settings → Shortcuts → KWin.



1. **Use keyboard shortcuts** – off leaves the keys assigned but they do nothing. The sidebar switch **Shortcuts** is the same.
2. **Key scheme** – choose a ready-made set and click **Apply**: all 16 snapping actions get their keys at once (see chapter 7).
3. **Reset all** – gives every action the key of the chosen scheme again.
4. **One row per action** – shows the keys as key caps. The pencil opens the editor; the arrow ↶ appears when a key differs from the scheme and resets it.

Changing a single key

1. Click the action, e.g. *Snap to the left half*. An editor opens below it.
2. **Usual combinations** – one click picks the same key with the modifiers of every scheme, e.g. **Ctrl+Alt+Left**, **Meta+Left**, **Meta+Shift+Left**.
3. **Your own combination** – toggle **Meta** **Ctrl** **Alt** **Shift**, choose the key from the list (letters, digits, arrows, F1–F12, number block …) and click **Set**.
4. **Reset to default** brings back the key of the chosen scheme, **Remove** clears the key of that action.

When a key is already in use

SeaQ Snap Layout asks KDE's shortcut service before it sets a key. If another action already has it, an orange card names the owner – for example *"Ctrl+Alt+F is used by Show Calendar"*:

- **Take it over** – removes the key from the other action and gives it to SeaQ Snap Layout.
- **Take over all** – does that for every conflict in the list.
- **Keep them** – leaves everything as it is; that action keeps no key.

CHAPTER 7

7 Key reference

The 16 snapping actions with their keys in the default scheme and in the number-block scheme. The four on/off actions have no key by default (page 20).

Action	Default – Ctrl+Alt	Number block
HALVES		
Snap to the left half	Ctrl+Alt+Left	Ctrl+Alt+Num+4
Snap to the right half	Ctrl+Alt+Right	Ctrl+Alt+Num+6
Snap to the top half	Ctrl+Alt+Up	Ctrl+Alt+Num+8
Snap to the bottom half	Ctrl+Alt+Down	Ctrl+Alt+Num+2
QUARTERS		
Snap to the top-left quarter	Ctrl+Alt+U	Ctrl+Alt+Num+7
Snap to the top-right quarter	Ctrl+Alt+I	Ctrl+Alt+Num+9
Snap to the bottom-left quarter	Ctrl+Alt+J	Ctrl+Alt+Num+1
Snap to the bottom-right quarter	Ctrl+Alt+K	Ctrl+Alt+Num+3
THIRDS		
Snap to the left third	Ctrl+Alt+D	–
Snap to the center third	Ctrl+Alt+F	–
Snap to the right third	Ctrl+Alt+G	–
Snap to the left two thirds	Ctrl+Alt+E	–
Snap to the right two thirds	Ctrl+Alt+Y	–
WINDOW		
Maximize or restore	Ctrl+Alt+Return	Ctrl+Alt+Num+5
Center the window	Ctrl+Alt+C	Ctrl+Alt+Num+0
Restore the size before snapping	Ctrl+Alt+-	–

Other schemes

Same keys, other modifiers – shown for *Snap to the left half*. **No shortcuts** removes all keys.


Scheme	Example
Meta+Ctrl+Alt + key	Meta+Ctrl+Alt+Left
Meta + key (KDE style)	Meta+Left – replaces Plasma's own quick tiling keys
Meta+Shift + key	Meta+Shift+Left
Ctrl+Shift+Alt + key	Ctrl+Shift+Alt+Left
Ctrl+Alt + number block	Ctrl+Alt+Num+4 – thirds and Restore get no key

Easy to remember

Arrows give halves. U I / J K sit like the four quarters on the keyboard; D F G are the three thirds from left to right, E and Y the two-thirds. On the number block, each key points where the window goes.

SETTINGS EDITOR

6.9 About & Help



Support – **Donate with PayPal** (paypal.me/SeaQSoft) and **Buy me a coffee** (buymeacoffee.com/seaq) open your browser. Below: how snapping works, the other ways to snap, how to open the editor, plus:

- **Version** – the installed version. Check it after an update.
- **Author** – SeaQ
- **License** – GPL-3.0-or-later
- **Settings file** – where your settings and layouts are stored.

Feature shortcuts

Four more actions have no key by default, so they never clash with your own shortcuts. Give them a key on the **Keyboard shortcuts** page or in **System Settings** → **Shortcuts** → **KWin** (search for "Snap Layout").

Action	What it does
Snap bar on/off	Pauses or resumes the snap bar – the same as its switch in the sidebar.
Screen edges on/off	Pauses or resumes the screen edges.
Window magnet on/off	Pauses or resumes the window magnet.
Test the snap bar	Plays the snap bar on the current screen.

CHAPTER 8

8 Languages

The settings editor, the quick menu, the shortcut names and the layout names follow your system language (**System Settings** → **Region & Language**). 62 languages are included – all European languages plus Chinese (simplified and traditional), Japanese, Korean, Hindi, Bengali, Tamil, Telugu, Marathi, Gujarati, Punjabi, Urdu, Arabic, Hebrew, Persian, Indonesian, Malay, Vietnamese, Thai, Filipino, Georgian, Armenian and more. Right-to-left languages are mirrored automatically.

> **Help translate**
> Each language is a plain text file in the `i18n` folder of the repository – one line per text. Corrections and new languages are welcome as pull requests.

CHAPTER 9

9 Recommended values

All defaults at a glance. **Recommended values** on each page restores them for that page.

General	
Snap bar · Screen edges · Window magnet · Shortcuts	all on
Previews (bar, edges)	On
Previews in the accent color	On
Restore original size	On
Gap between windows	0 px
Gap to the screen edge	0 px
Excluded applications	none
Appearance	
Color scheme	System
System accent color	On
Snap bar size	100 %
Thumbnail width	72 px
Corner radius	8 px
Background opacity	96 %
Layouts per row	0 (one row)
Layout and zone names	Off

Behavior	
Trigger distance	24 px
Small handle first	On
Handle distance	140 px
Active width	100 %
Delay before showing	40 ms
Hide distance	56 px
Delay before hiding	150 ms
Animation	
Slide distance	12 px
Slide-in duration	220 ms
Slide-out duration	150 ms
Motion curve	Smooth
Fade in and out	On
Layouts in the bar	
Halves · Two thirds · Three columns · Main + stack · Four quarters · Center focus	

Screen edges	
Top edge	Maximize
Sides · bottom · corners	On
Smart fill	On
Distance · push delay · corner	4 px · 60 ms · 20 %
Window magnet	
Snap distance	16 px
Windows · screen edges · resizing	On
Keep the gap	Off
Resistance	48 px
Sticky edges · in line · shake · fade	On
Keyboard	
Key scheme	Ctrl+Alt + key

CHAPTER 10

10 Troubleshooting & FAQ

Q The snap bar does not appear.

Check that the script is ticked in **KWin Scripts** and that **Active** is on in the editor. Make sure the app is not on your exclusion list and that you drag a normal, resizable window by its title bar. If **Active width along the top edge** is below 100 %, move towards the middle of the top edge.

Q Two things happen when I drag a window to an edge.

Plasma's own edge actions or snap zones are still active. Switch on **Pause KDE's edge tiling and its preview** (Screen edges page) and **Pause KDE's snap zones while the magnet is on** (Window magnet page) – both are on by default.

Q A keyboard shortcut does nothing.

Check the **Shortcuts** switch and that the key is shown on the page. If another program grabs the key first, choose a different scheme or key.

Q I installed an update, but the old version is still running.

KWin keeps loaded scripts in memory. Log out and back in once. The **About & Help** page shows the running version.

Q The quick menu button does nothing.

After **Open Snap Layout settings editor** you have to click **OK** (or **Apply**). The editor appears about one second later.

Q "Could not locate package metadata" in KWin Scripts.

The script folder was removed while KWin still listed it. Install the `.kwinscript` file again, then log out and back in.

Q Can I use it with several monitors?

Yes. The bar opens on the screen under the cursor and zones are calculated for that screen.

Q Something is still wrong – how do I report it?

Collect the log and open an issue on GitHub:

```
journalctl --user -b | grep kdesnaplayout | tail -n 30
```

CHAPTER 11

11 Files, uninstalling & license

Where things are stored

Path	Contents
`~/.config/kde-snaplayout.ini`	All settings of the editor and your layouts. Copy it to move your setup to another PC.
`~/.config/kglobalshortcutsrc` → `[kwin]`	The keys of the shortcuts (managed by KDE).
`~/.config/kwinrc` → `[Script-kdesnaplayout]`	The two quick-menu values (editor button, snap bar colors).
`~/.local/share/kwin/scripts/kdesnaplayout`	The installed script.

> **Privacy**
> SeaQ Snap Layout works completely offline. It sends no data anywhere and only reads window positions while you drag a window.

Uninstalling

In **KWin Scripts**, click the trash icon next to **SeaQ Snap Layout** and then **Apply**. Or in a terminal:

```
kpackagetool6 --type KWin/Script --remove kdesnaplayout
rm ~/.config/kde-snaplayout.ini        # optional: delete your settings
```

License

SeaQ Snap Layout is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License, version 3 or (at your option) any later version. It is distributed in the hope that it will be useful, but without any warranty.

SeaQ Snap Layout

Made by **SeaQ**

Source & issues: github.com/Swenix-dev/KDE-Snap-Layout

Also on the KDE Store