

RustDesk Native Windows Server Setup Guide

Deployment, Key Pair Encryption, Auto-Startup, and Client Configuration (Non-Docker)

Server Type:	Native Windows 64-bit Binaries (No Docker required)
hbbs (ID Server):	RUNNING (Active background process)
hbbr (Relay Server):	RUNNING (Active background process)
Server Host IP:	192.168.1.128
Public Encryption Key:	AiyzL2kd7b0z4smaSpvsE07og9tJEMEV8+QhEXkX6m0=
Auto-Startup:	CONFIGURED in Windows Startup Folder

1. Active Server Daemons & Network Ports

Both server daemons are running natively and bound to standard RustDesk ports:

Port / Protocol	Service Daemon	Functional Purpose
21115 (TCP)	hbbs.exe	NAT type testing and connection negotiation.
21116 (TCP/UDP)	hbbs.exe	TCP: ID registration & heartbeat. UDP: Hole punching.
21117 (TCP)	hbbr.exe	Relay Service: Relays encrypted screen and input data.
21118 / 21119 (TCP)	hbbs / hbbr	Web client WebSocket transport support.

2. How to Connect Clients to Your Private Server

On any computer, tablet, or phone running the RustDesk client application:

1. Open RustDesk Settings

- Click on the **3-dots menu** (■) next to your ID in RustDesk > Select **Network** (or **ID/Relay Server** in Settings).

2. Enter Your Server Coordinates

- **ID Server:** 192.168.1.128:21116 (or your public IP / dynamic DNS domain for WAN access)
- **Relay Server:** 192.168.1.128:21117 (or your public IP / dynamic DNS domain)
- **API Server:** *(leave empty)*
- **Key:** AiyzL2kd7b0z4smaSpvsE07og9tJEMEV8+QhEXkX6m0=

3. Confirm Connection

- Click **OK**. The status indicator in the bottom bar will change to **Ready (Green)**, confirming all connections are routing privately through your own server.

3. PowerShell Server Management Script

A dedicated management script has been placed in rustdesk-server\manage_server.ps1:

Command Syntax	Action Description
----------------	--------------------

<code>.\rustdesk-server\manage_server.ps1 -Action status</code>	Checks running status of hbbs and hbbr processes and active network ports.
<code>.\rustdesk-server\manage_server.ps1 -Action start</code>	Starts both hbbs and hbbr as detached background Windows processes.
<code>.\rustdesk-server\manage_server.ps1 -Action stop</code>	Stops all running server processes.
<code>.\rustdesk-server\manage_server.ps1 -Action key</code>	Displays your public key for pairing client devices.
<code>.\rustdesk-server\manage_server.ps1 -Action setup-startup</code>	Enables auto-start on Windows boot (already created in your Startup folder).