

RustDesk Status & Power Outage Recovery Report

System Audit, Service Inspection, and Power Outage Recovery Recommendations

RustDesk Current Status:	RUNNING (Active in current user desktop session)
Windows Service Status:	NOT INSTALLED (Runs as User Tray Process only)
Auto-Start on Power Outage:	INCOMPLETE / WILL NOT WORK UNATTENDED
Why it won't connect:	1) PC will remain OFF without BIOS setting; 2) RustDesk will NOT start before Windows user signs in.

1. Live Diagnostic Audit Results

Component	Detected State	Implications
Active Processes	Running (PID 9736, 14064) rustdesk.exe	RustDesk is running right now and active for the signed-in user.
User Startup (HKCU\Run)	Configured rustdesk.exe --tray	Starts only <i>after</i> a user physically or remotely logs in.
Windows Service (sc.exe)	Not Installed	Cannot run in background at the Windows lock/login screen.

2. Power Outage Recovery Analysis (3 Key Requirements)

For RustDesk to be accessible remotely after a power outage, three sequential links must work:

Layer	Current System Reality	Required Fix
1. Hardware Power (Motherboard/BIOS)	PCs remain completely OFF by default when AC wall power returns.	Enter BIOS/UEFI & set AC Power Recovery / Restore on AC Power Loss to 'Power On'.
2. OS Startup (Windows Boot)	Windows will boot to the sign-in / lock screen and stop.	Standard behavior; operates properly once background service is installed.
3. RustDesk Service (Remote Connection)	Currently only launches on user desktop session login (HKCU).	Install RustDesk as a Windows Service so it runs before any user logs in.

3. How to Configure True Automatic Startup

Step 1: Install RustDesk Windows Service (Elevated)

- Open the RustDesk application window on your desktop.
- Click on **Install** or **Install Service** (look for the shield/admin icon in RustDesk UI).
- This registers RustDesk as an automatic Windows System Service (Session 0) that starts immediately at system boot, allowing you to connect and enter your Windows credentials remotely.

Step 2: Enable 'Restore on AC Power Loss' in BIOS/UEFI

- Restart computer and tap **DEL** or **F2** during boot to open BIOS/UEFI settings.
- Navigate to **Power Management** (or **APM Configuration / Advanced**).

- Change **Restore on AC Power Loss** (or *AC Back / State After G3*) from *Power Off* to **Power On** (or *Last State*). Save and reboot.

Step 3: Test Unattended Access

- Reboot the PC and let it sit on the Windows lock screen without logging in.
- Connect from your remote device using RustDesk. You should see the Windows login screen and be able to enter your password.