AEGIS PRIME

OFFICIAL
USER MANUAL

Discord Server Administration
Alliance Management & Privacy

VERSION 24.55 | CLOUD READY

SERVER OWNERS / STAFF / ALLIANCE LEADERS / PLAYERS

OCTOBER 2026

CONTENTS

Complete AEGIS PRIME v24.55 user and administrator manual

01	Getting Started
02	Server Control Panel
03	Assigning Players and Alliance Roles
04	Strict Alliance Channel Privacy (v24.55)
05	Alliance Leadership
06	Moderation and Staff Panel
07	Channels and Permissions
08	Announcements, Polls and Events
09	Player Onboarding and Verification
10	Backups and Recovery
11	Dashboard Auto-Cleanup
12	Support and Troubleshooting
13	Frequently Asked Questions

ACCESS NOTE

Native Discord Administrator permissions bypass channel restrictions. AEGIS PRIME cannot hide alliance rooms from native Discord Administrators or the server owner.

CHAPTER 01

Getting Started

Install AEGIS PRIME using its official Discord installation link. A server owner should authorize the requested bot permissions and applications.commands scope. AEGIS must be positioned ABOVE the alliance, staff, and management roles it administers in Discord Server Settings -> Roles. Administrator permission is not required. Run /aegis setup, or use the automatically posted Initial Server Setup dashboard. Complete the ten commissioning steps, including timezone, structure, alliances, onboarding, moderation, announcements, backups, provisioning, and final readiness.

CHAPTER 02

Server Control Panel

The private SERVER CONTROL PANEL provides a Quick Feature Selector as well as shortcuts for alliances, member assignment, channel controls, moderation, announcements, polls, events, settings, and system maintenance. Where practical, choose an action from a dropdown instead of typing its name. The User Manual button opens the published HTTPS documentation link when configured. If no link is configured, the bot can send a local HTML manual attachment.

CHAPTER 03

Assigning Players and Alliance Roles

Open Assign / Move Player in SERVER CONTROL PANEL. Select a Discord member, choose an existing alliance, select R1-R5, and select an action such as assign/move, promote, or demote. Confirm the operation. The bot enforces role hierarchy and access restrictions. Remove Player uses dropdowns and allows removing one alliance assignment or all alliance roles. Alliance R5/R4 operators are restricted to their own authorized ranks and members.

CHAPTER 04

Strict Alliance Channel Privacy (v24.55)

Every AEGIS-managed alliance category is restricted to that alliance's R1-R5 roles and the AEGIS PRIME bot. This applies to the private general text channel, private voice channel, and additional rooms under the alliance category. The leadership control panel is restricted to R5/R4. Other alliances and the AEGIS Admin bot-managed role are not given private-channel access by AEGIS. Existing saved alliance categories are reconciled at bot startup and during repairs, and accidental outside-role or directly-invited-user permissions on alliance rooms are removed. This may revoke legacy custom guest access; verify your permissions before upgrading. Discord's native Administrator permission bypasses channel overwrites, and the server owner has inherent server access. AEGIS cannot conceal these channels from native Discord Administrators; remove that native permission from any staff member who must be excluded. Do not treat this as an end-to-end encrypted space. Members who hold rank roles in multiple alliances may see both alliances; maintain one alliance membership per player. Message edit/delete audit handlers do not forward private alliance message contents into the server-wide moderation logs. Automatic security enforcement continues but logs a generic reason. Older moderation-log messages already present are not erased automatically. Always review permissions on an upgrade and test with a member account, a staff account without Administrator, and an Administrator account.

CHAPTER 05

Alliance Leadership

Alliance R5 and R4 leaders manage alliance membership, rank changes, requests, announcements, polls, and events in their private alliance dashboard. Promotions and role transfers respect the chain of authority. Server owner/AEGIS admins have broader configuration access, while standard members do not.

CHAPTER 06

Moderation and Staff Panel

The private STAFF CONTROL PANEL offers dropdown menus for warnings, timeouts, kicks, bans, reports, tickets, unbans, and purging. The server owner also has moderation controls in SERVER CONTROL PANEL. Select members from a Discord user dropdown where available, then provide the reason and necessary confirmation. Safety confirmations for destructive operations remain typed or explicit buttons. Warnings, logs, staff notes, moderation escalation, protection rules, and timeouts follow server permissions and role hierarchy.

CHAPTER 07

Channels and Permissions

Channel Management supports category and channel selectors for hard locks, read-only mode, hide/show, slow mode, creation, and deletion. The bot must have Manage Channels, Manage Roles, and appropriate permissions on managed channels. Incorrect role position can block repairs even when a permission is enabled. During setup, AEGIS validates required infrastructure. AEGIS-managed channels can be automatically recovered when missing after setup is READY.

CHAPTER 08

Announcements, Polls and Events

Use dropdowns to choose an action and target channel or audience. Compose the announcement text, poll question/options, or event details in text fields. Roles to mention can be chosen with role selectors; R5/R4 permissions continue to limit alliance notices. Available schedule and recurrence controls include dates, times, and intervals. For lists with 25 or fewer records, a record selector can replace a manually entered ID; larger lists retain a manual ID field because Discord limits menu choices.

CHAPTER 09

Player Onboarding and Verification

A new member can select an alliance, request approval, and verify their in-game name. Depending on enabled settings, AEGIS supplies welcome messages, DM onboarding, nickname reminders, player dashboard preferences, support tickets, and rules acceptance. Server owners manage approval settings in the dashboard.

CHAPTER 10

Backups and Recovery

Open Backup / Database in SERVER CONTROL PANEL. Keep automatic backups enabled, run manual backups before every upgrade, and test backup archives periodically. Oracle Cloud installs store persistent state under /mnt/aegis-data and the application under /opt/aegis-prime. Restores are administrative operations and should be planned carefully. Never delete the data volume when upgrading application code.

CHAPTER 11

Dashboard Auto-Cleanup

SERVER CONTROL PANEL, STAFF CONTROL PANEL, and R5/R4 management channels are intended to keep their permanent dashboard messages and remove ordinary channel clutter after actions. Completed private interaction results are automatically dismissed. In-progress interactive dropdowns must remain visible until their workflow ends. Moderation logs, reports, support transcripts, and event posts are excluded from this cleanup; they are records rather than control- panel clutter.

CHAPTER 12

Support and Troubleshooting

Run /aegis info for bot version and installation details, and /aegis readiness for environment checks. If setup fails, examine permissions and role hierarchy first, then inspect Oracle logs using sudo journalctl -u aegis-prime -n 80 --no-pager. Do not send your Discord bot token or SSH private key to anyone. For public support, use AEGIS PRIME | Official Support or your configured support resource.

CHAPTER 13

Frequently Asked Questions

Can a bot reinstall on an existing server? Yes, but existing data and channel IDs may be reused. The guided setup reconciles saved references and validates permissions. Does the bot need Administrator? No; authorize only the requested permissions and keep the bot's role above the roles it must manage. Can the bot be hosted on each server separately? No; your Oracle Cloud installation can serve multiple guilds with separate configuration. When does the manual button link work? After AEGIS_USER_MANUAL_URL points to a real HTTPS page and the service restarts.