AEGIS
PRIME

COMPLETE
USER & ADMIN
MANUAL

All management features, workflows
and step-by-step instructions

VERSION 24.55 | CLOUD READY

SERVER OWNERS / ADMINS / STAFF / ALLIANCE LEADERS / PLAYERS

OCTOBER 2026

CONTENTS

01	Purpose, audience and navigation	04
02	Install AEGIS PRIME on a server	04
03	Access levels and security boundaries	05
04	Ten-step Guided Server Setup	06
05	SERVER CONTROL PANEL overview	07
06	Alliance creation and lifecycle	08
07	Player assignment, transfer and removal	09
08	Alliance leadership tools: R5 and R4	10
09	Strict Alliance Privacy: v24.55	12
10	Member onboarding, verification and player dashboard	13
11	Announcements and message scheduling	14
12	Advanced events and participation	15
13	Polls and voting	17
14	Channel and category management	18
15	Moderation actions	19

CONTENTS (CONTINUED)

16	STAFF CONTROL PANEL and staff security	21
17	Support Center, reports and tickets	22
18	Moderation logs and audit containment	23
19	Security center, anti-raid and lockdown	24
20	Rules, acceptance and verification gate	25
21	Backups, database and restoring state	26
22	Health checks, drift and emergency recovery	27
23	BOT SETTINGS reference	28
24	Timezone, Test Mode, Maintenance Mode and retention	29
25	Developer feedback, support and service communication	30
26	Slash command quick reference	30
27	Privacy, personal data and records	31
28	Oracle Cloud operations and troubleshooting	32
29	Known limitations and planned improvements	33

01 Purpose, audience and navigation

This is the operating manual for AEGIS PRIME v24.55 CLOUD READY. The bot is hosted centrally and serves multiple Discord servers. Server owners install the Discord application, not the Python source. The menu layout can vary between the permanent dashboard and private interaction panels.

How to use this manual

ACCESS: All users

1. Find your task in the contents, then follow its named panel path or slash command.
2. Use dropdowns for members, roles, channels, alliances and actions when offered.
3. Read the access and safety note before confirming changes.
4. If a button is missing, verify permissions and consult the Troubleshooting chapter.

Panel naming

ACCESS: All users

1. SERVER CONTROL PANEL is the main owner/admin dashboard.
2. STAFF CONTROL PANEL is the moderation staff workspace.
3. Alliance control panels belong to the specific R5/R4 leadership team.
4. PLAYER DASH BOARD and Support Center are member-facing interfaces.

02 Install AEGIS PRIME on a server

Use the official Discord app installation link. A public App Directory listing is not required for invite-link installations. Each installed server has its own configuration and state.

Install the bot

ACCESS: Server Owner / authorized installer

1. Sign in to Discord as the server owner or a user authorized to manage the server.
2. Open the official AEGIS PRIME installation link from the developer or an existing installation.
3. Choose the target server, review the requested bot and applications.commands permissions, and authorize.
4. Return to the server and find the initial setup dashboard or run /aegis setup.
5. Complete the setup wizard and verify with /aegis readiness.

Verify installation and role hierarchy

ACCESS: Server Owner

1. Open Server Settings > Roles.
2. Find the AEGIS PRIME BOT role, not the AEGIS Admin role.

3. Position it above the ranks and staff roles it is expected to manage.
4. Confirm Manage Roles, Manage Channels and the relevant moderation/communication permissions are enabled.
5. If permissions were changed after authorization, rerun the setup preflight or repair.

Reinstall on an existing server

ACCESS: Server Owner

1. Create a backup before removing the bot.
2. If it has been kicked, authorize it again with its official link.
3. Do not manually delete old AEGIS roles or channels unless intentionally resetting them.
4. Check bot role hierarchy and permissions first; stale role placement can block Step 3.
5. Run Create / Repair Core Structure, then complete final readiness and test preserved channels.

NOTE: Kicking AEGIS does not necessarily remove its saved cloud data.

03 Access levels and security boundaries

AEGIS separates Discord-native authority from bot-managed privileges. The server owner retains ultimate access. The AEGIS Admin role is a bot-managed administrator and should carry zero native Discord permissions.

Server Owner and AEGIS Admin

ACCESS: Server Owner

1. Use the actual Discord Server Owner account for owner-only controls and emergency recovery.
2. Grant AEGIS Admin only to trusted people who need AEGIS management functions.
3. Leave native Administrator disabled on the AEGIS Admin role.
4. Do not confuse the AEGIS Admin role with the AEGIS PRIME bot's own role.

Moderation staff tiers

ACCESS: Server Owner / AEGIS Admin

1. Bot Moderator handles authorized warnings, timeouts, reports and tickets.
2. Bot Senior Moderator can access additional high-risk moderation actions where configured.
3. Protected targets and Discord role hierarchy can still block a moderation action.
4. Assign staff tiers through Security & System > Staff Security.

Alliance rank boundaries

ACCESS: All alliance members

1. R5 is the alliance leader and can manage R4 and lower within the same alliance.
2. R4 can manage lower alliance ranks, subject to the configured restrictions.

3. R1 through R3 are normal members unless separately authorized.
4. Alliance leadership cannot use its rank to manage other alliances or server-wide systems.

04 Ten-step Guided Server Setup

The current wizard is a ten-step workflow. Complete each step in order; older guides describing a seven-step launch wizard are outdated.

Step 1: Preflight

ACCESS: Server Owner

1. Open /aegis setup or the initial setup dashboard.
2. Run the permission/intents preflight.
3. Correct missing Manage Roles, Manage Channels, and hierarchy problems.
4. Retry until the preflight advances.

Step 2: Timezone

ACCESS: Server Owner / AEGIS Admin

1. Open the timezone selector.
2. Choose a region and local timezone, or explicitly keep UTC.
3. Confirm the value before proceeding.
4. Remember that recurring events and announcements use this timezone.

Step 3: Core server structure

ACCESS: Server Owner / AEGIS Admin

1. Review the selected welcome channel.
2. Press Create / Repair Core Structure once.
3. Allow AEGIS to create or repair managed roles, channels and ticket infrastructure.
4. If it remains on Step 3, check role hierarchy and permissions, then review missing-item details.
5. Continue only after the wizard advances.

Steps 4-7: Feature selections

ACCESS: Server Owner / AEGIS Admin

1. Use the displayed setup choices for alliances, player onboarding, moderation, announcements and related modules.
2. Choose the desired setting for each step and confirm.
3. Verify that member-facing features align with the community's rules.
4. Continue through all four feature steps.

Step 8: Backups

ACCESS: Server Owner / AEGIS Admin

1. Select Enable Backups & Create Baseline.
2. Ensure backup creation completes and persistent data is available.
3. Review retention settings after launch.
4. Continue to apply and validation.

Step 9: Apply and validate

ACCESS: Server Owner / AEGIS Admin

1. Select Apply & Validate Server.
2. Review any permission or infrastructure warnings.
3. Correct missing resources, then run validation again.
4. Proceed only after successful validation.

Step 10: Final readiness and launch

ACCESS: Server Owner / AEGIS Admin

1. Select Run Final Readiness & Launch.
2. Review service, database, backup and channel checks.
3. Confirm the server is READY.
4. Run /aegis readiness again after major configuration changes.

Save and resume setup

ACCESS: Server Owner / AEGIS Admin

1. Use Save & Exit to preserve partial progress.
2. Return to /aegis setup later to continue.
3. Use Back when available to review a prior selection.
4. Do not assume saved progress means final launch has completed.

05 SERVER CONTROL PANEL overview

The permanent management dashboard is intended to remain clean. Most actions open private menus and should not leave ordinary chat clutter in the panel channel.

Open management tools

ACCESS: Server Owner / AEGIS Admin

1. Open the private SERVER CONTROL PANEL channel.
2. Use the Quick Feature Selector or a dedicated button.
3. Choose the desired action in the dropdown or menu.

4. Complete any follow-up fields, then submit or confirm.
5. Close or dismiss the private response when finished.

Refresh or repair the dashboard

ACCESS: Server Owner / AEGIS Admin

1. Use Refresh Panel for a missing or stale dashboard display.
2. If the panel or permissions are damaged, open Security & System > Health & Repair.
3. Run the appropriate targeted repair before Repair Everything.
4. Use the server-owner /aegis recovery command only for more serious failures.

Open the User Manual

ACCESS: All authorized panel users

1. Press User Manual in SERVER CONTROL PANEL.
2. When AEGIS_USER_MANUAL_URL is configured, open the public HTTPS documentation.
3. If no URL is configured, the bot may provide a local manual attachment.
4. If the link is broken, notify the owner to verify GitHub Pages and the bot environment setting.

06 Alliance creation and lifecycle

Alliances receive managed R1-R5 roles and private infrastructure. Do not confuse alliance deletion with removing one player's alliance membership.

Create an alliance

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > Create Alliance.
2. Enter the new alliance name and select or specify the initial R5 leader.
3. Review the name and leadership, then confirm.
4. Verify that AEGIS creates R1-R5 rank roles and the alliance category/control spaces.
5. Test visibility with an ordinary member and leader account.

View alliances

ACCESS: Server Owner / AEGIS Admin

1. Open View Alliances.
2. Review alliance names and current R5 leaders.
3. Inspect the roster or leadership controls for details.
4. Use a separate change workflow to correct membership or leadership.

Delete an alliance

ACCESS: Server Owner / AEGIS Admin

1. Open Delete Alliance.
2. Select the intended alliance and review its managed resources.
3. Create a backup before any deletion.
4. Complete the required confirmation, then verify the result.
5. Do not delete an active alliance just to remove one member.

NOTE: Deletion can remove Discord roles and managed channels; it is a destructive action.

Check privacy after alliance changes

ACCESS: Server Owner / AEGIS Admin

1. Confirm alliance members see their own general and voice channels.
2. Check that outsiders and unrelated AEGIS Admins cannot read them.
3. Verify that R5/R4 leadership channels remain restricted.
4. If access is wrong, use the supported privacy/repair workflow rather than manually adding broad permissions.

07 Player assignment, transfer and removal

Player-management actions use selectable members, alliances and ranks where possible. The Assign / Move Player workflow was tested successfully in v24.55.

Assign a player

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > Assign / Move Player.
2. Select the Discord member.
3. Select the target alliance and rank R1-R5.
4. Select the assignment action and review the summary.
5. Submit, then verify the member has the expected alliance and rank roles.

Move a player

ACCESS: Server Owner / AEGIS Admin

1. Open Assign / Move Player and select the member.
2. Choose the destination alliance and rank.
3. Select Move or the available assign/move action.
4. Confirm; AEGIS should reconcile conflicting configured alliance rank roles.
5. Check the member can no longer see their previous alliance rooms.

Promote or demote

ACCESS: Server Owner / AEGIS Admin / authorized alliance leadership

1. Open the player-management workflow.
2. Select a member and the new rank from the dropdown.
3. Choose Promote or Demote when the action selector is shown.
4. Confirm and check both the Discord role and alliance roster.
5. Verify the requesting operator was allowed to modify that rank.

Remove alliance membership

ACCESS: Server Owner / AEGIS Admin

1. Use SERVER CONTROL PANEL > Remove Alliance Role or the dedicated Remove Player workflow where available.
2. Select the member and, when offered, the alliance or all configured alliance roles.
3. Review the target carefully and confirm.
4. Verify alliance-specific roles were removed and unrelated server roles were retained.
5. Check access to the former alliance channels is now denied.

NOTE: Adding Remove Member directly inside Assign / Move Player is planned for a later release; v24.55 has the separate removal path.

Review or approve alliance requests

ACCESS: Server Owner / AEGIS Admin / authorized R5-R4

1. Open Alliance Requests or the relevant alliance leadership application menu.
2. Select a pending request.
3. Check the target member and alliance.
4. Choose the authorized approval rank or deny action and confirm.
5. Check membership and the roster after approval.

Export roster or view statistics

ACCESS: Authorized alliance leadership

1. Open the alliance leadership panel or Alliance Upgrades.
2. Choose Roster Export or Statistics.
3. Select the intended alliance if requested.
4. Download or read the output privately; share only with authorized people.

08 Alliance leadership tools: R5 and R4

Each alliance has its own private leadership panel. R5/R4 permissions apply only inside that alliance, and R4 cannot take R5-only actions.

Manage recruitment

ACCESS: Alliance R5/R4

1. Open your alliance's private control panel.
2. Choose Recruitment.
3. Set recruitment open or closed and, when prompted, enter a note.
4. Save, then verify the status displayed to applicants.

Review applications

ACCESS: Alliance R5/R4

1. Choose Applications or alliance requests.
2. Select the applicant and review any available profile details.
3. Approve with the permitted rank or deny.
4. Confirm the resulting alliance assignment.

Handle transfers

ACCESS: Alliance R5/R4

1. Open Transfers in the alliance control panel.
2. Review the pending transfer request and origin/destination.
3. Complete the release or acceptance action assigned to your alliance.
4. Check the roster and new rank afterward.

R4 promotion requests

ACCESS: Alliance R5

1. Open R4 Requests from the leadership panel.
2. Review the requesting member.
3. As R5, approve or deny the promotion.
4. Verify only the correct alliance role changed.

Transfer R5 leadership

ACCESS: Alliance R5

1. Open Transfer R5 from the R5 management view.
2. Select the eligible successor.
3. Review the leadership change and confirm using the required safeguard.
4. Verify the prior and new R5 roles and private leadership access.

NOTE: Treat leadership transfers as high impact.

Member limit and inactivity

ACCESS: Alliance R5/R4

1. Open Member Limit to set a cap, or 0 when the interface documents unlimited.
2. Open Inactivity to set the threshold and review inactive members.
3. Save the setting and inspect the resulting reports.
4. Do not assume automatic inactivity posts are enabled; this build keeps them disabled.

Alliance notes

ACCESS: Alliance R5/R4

1. Open Alliance Notes.
2. Add a private leadership note or review existing notes.
3. Clear notes using the provided confirmation when necessary.
4. Keep sensitive details limited to the appropriate leadership audience.

09 Strict Alliance Privacy: v24.55

Private alliance text and voice rooms are limited to that alliance's R1-R5 roles and the AEGIS bot. Leadership controls remain R5/R4-only. This protects separate alliance conversations but is not end-to-end encryption.

Test private text and voice rooms

ACCESS: Server Owner and designated testers

1. As an Alliance A R1 member, confirm Alliance A rooms are visible.
2. Confirm Alliance B rooms are hidden and its voice rooms cannot be joined.
3. Repeat using a member assigned only to Alliance B.
4. Use an AEGIS Admin account without native Administrator to confirm it cannot read either alliance's rooms.

Understand unavoidable exceptions

ACCESS: Server Owner

1. The actual Discord server owner has access to server channels.
2. Anyone with Discord's native Administrator permission bypasses channel privacy settings.
3. An account holding rank roles in two alliances may see both.
4. If an admin must not read alliance rooms, remove native Administrator privilege from that account.

Custom private alliance rooms

ACCESS: Server Owner / authorized channel manager

1. Create a text or voice channel under an AEGIS-managed alliance category.

2. Verify the new room inherits the restricted alliance permissions.
3. Test visibility from another alliance.
4. Do not grant broad staff or guest roles access: privacy reconciliation can revoke those grants.

Repair privacy drift

ACCESS: Server Owner / AEGIS Admin

1. If permissions were changed manually, allow AEGIS's repair process to reconcile them.
2. Use targeted Health & Repair or drift recovery if problems remain.
3. Check R5-only and R4-only rooms remain correctly restricted.
4. Inspect logs if repeated permission writes or Discord HTTP 429 responses occur.

Protect message contents

ACCESS: Server Owner

1. Private alliance message edits and deletions should not be copied into general moderation logs.
2. Old moderation logs created before v24.55 are not automatically scrubbed.
3. Review historical logs before publishing or sharing them.
4. Do not claim private alliance rooms are invisible to native Discord Administrators.

10 Member onboarding, verification and player dashboard

AEGIS supports welcome messages, in-game name collection, optional alliance applications, verification, notification preferences, and rules acceptance.

New member onboarding

ACCESS: Players

1. Join the server and read the welcome/rules channels.
2. Open any onboarding DM sent by AEGIS.
3. Enter the in-game name or use the player dashboard's name workflow.
4. Select or apply to an alliance where configured.
5. Wait for the appropriate approval or verification before expecting alliance access.

Update in-game name

ACCESS: Players

1. Open PLAYER DASH BOARD.
2. Choose Update In-Game Name.
3. Enter the accurate in-game name and submit.

4. Check the displayed profile and server nickname.
5. If nickname changes fail, ask an administrator to inspect Manage Nicknames and role position.

Player profile and verification status

ACCESS: Players

1. Open PLAYER DASH BOARD.
2. Choose My Profile or Verification Status.
3. Read the current profile and verification outcome.
4. Contact a server administrator if information is incorrect.

Configure notifications

ACCESS: Players

1. Open PLAYER DASH BOARD > Notification Preferences.
2. Select desired server and alliance notifications.
3. Use All ON or All OFF shortcuts where provided.
4. Save and verify the preference summary.

Verify a player's name

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > Name Verification.
2. Choose a player from the searchable selector.
3. Compare the claimed in-game name with your server's verification process.
4. Verify or review pending/problem status as appropriate.
5. Check the player's status afterward.

11 Announcements and message scheduling

Server and alliance announcements support immediate posting, one-time scheduling, recurring schedules, and cancellation. Scheduling follows the configured server timezone.

Post an announcement now

ACCESS: Authorized owner/admin or alliance leadership

1. Open SERVER CONTROL PANEL > Announcements, or the alliance Announcements panel.
2. Choose Post Now.
3. Select the target channel and any allowed role mentions.
4. Enter the announcement content.
5. Preview and post; verify the result in the target channel.

Schedule once

ACCESS: Authorized announcer

1. Choose Schedule Once.
2. Select the target channel and enter the content.
3. Enter the future date and time in the configured server timezone.
4. Save and verify the Scheduled list.
5. Cancel or update using the available scheduled-record action when required.

Create recurring announcements

ACCESS: Authorized announcer

1. Choose Recurring in Announcements.
2. Set the start date, repeat interval in days and one or more exact posting times.
3. Choose target channel and authorized mentions.
4. Save and confirm the recurrence appears in Scheduled.
5. Use Cancel to stop it when no longer required.

Alliance event announcements

ACCESS: Alliance R5/R4

1. Open the alliance event controls.
2. Choose Event Announcements.
3. Select Announce Now, Schedule Reminder, Recurring, or the available scheduling action.
4. Set time, channel and message details.
5. Review scheduled reminders and cancel outdated ones.

List or cancel scheduled items

ACCESS: Authorized announcer

1. Open Scheduled or Cancel in the relevant announcement menu.
2. Select the stored announcement record or enter its ID if the interface requires it.
3. Review its target and timing.
4. Confirm cancellation, then check that the record no longer appears as active.

12 Advanced events and participation

Events may be server-wide, cross-alliance or alliance-scoped. Event organizers manage check-in, signup, reminders, completion, history, statistics and export.

Create a server event

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > Advanced Events.
2. Choose Server Event.
3. Set event name, type, start time, description, capacity and eligible audience.
4. Confirm and inspect the created event in Active Events.
5. Test signup/check-in with an ordinary participant.

Create a cross-alliance event

ACCESS: Server Owner / AEGIS Admin

1. Open Advanced Events > Cross-Alliance.
2. Select permitted participating alliances.
3. Enter event schedule and capacity, where prompted.
4. Submit and verify visibility for each eligible alliance.

Manage an existing event

ACCESS: Event manager

1. Open Advanced Events > Manage Event.
2. Select the event from a dropdown or enter its record ID where needed.
3. Choose Open Check-In, Close Check-In, Send Reminder or Set Recurrence.
4. Confirm the action and verify the event status.

Complete or cancel an event

ACCESS: Event manager

1. Choose Manage Event and select the intended event.
2. Select Complete Event or Cancel Event.
3. Review the irreversible effects and confirm.
4. Check History and Statistics for the final state.

Event participation

ACCESS: Eligible players

1. Open the event message or player dashboard event list.
2. Use Sign Up to join or Leave Signup to withdraw.
3. Use available Check-In controls during the event window.
4. Verify your status in the signup/check-in display.

Event exports

ACCESS: Event manager

1. Open Advanced Events > Export All or Export Event.
2. Select an event if necessary.
3. Download the generated data.
4. Review sensitive member information before redistribution.

13 Polls and voting

Polls can serve the whole server, one alliance, or leadership-only audiences. Available controls include anonymous voting, eligible ranks, results and manual closure.

Create a server poll

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > Polls.
2. Choose Server Poll and select the destination channel.
3. Enter the question and two to five answer choices.
4. Set the duration and anonymous-vote setting if offered.
5. Publish and verify voting buttons appear.

Create alliance or R5/R4 poll

ACCESS: Authorized alliance leadership

1. Choose Alliance Poll or R5/R4 Poll.
2. Select the target alliance and audience ranks.
3. Enter the question, options and duration.
4. Publish and confirm unauthorized members cannot vote.

Vote and view results

ACCESS: Eligible voters

1. Open an active poll message.
2. Choose an available response according to poll rules.
3. Read results if the poll allows access.
4. Do not share restricted leadership poll results with unrelated alliances.

Close poll or view active records

ACCESS: Authorized poll manager

1. Open Polls > Active Polls, Results or Close Poll.
2. Select the poll record or provide its ID when needed.

3. Review the result or confirm closure.
4. Verify it no longer accepts new votes.

14 Channel and category management

AEGIS manages text and voice channels, categories, locks, hide/show, read-only states, slow mode, permission snapshots, and server lockdown. Use care with alliance private categories.

Create text or voice channel

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > Channel Management.
2. Choose Create Text or Create Voice.
3. Select the destination category and enter a channel name.
4. Confirm creation.
5. Check inherited permissions and ensure alliance rooms remain private.

Lock or unlock a channel

ACCESS: Server Owner / AEGIS Admin

1. Open Channel Lock or Advanced Channel Management.
2. Select the target channel.
3. Choose Lock/Unlock, Hard Lock/Hard Unlock or Read-Only/End Read-Only.
4. Apply and verify a normal member's send permissions.

Lock or unlock an entire category

ACCESS: Server Owner / AEGIS Admin

1. Open Advanced Channel Management.
2. Choose Lock Category or Unlock Category.
3. Select the category.
4. Confirm the operation.
5. Verify representative channels and role access.

Hide or show a channel

ACCESS: Server Owner / AEGIS Admin

1. Select the intended channel in Channel Management.
2. Choose Hide Channel or Show Channel.
3. Confirm and check the visibility from a regular member account.
4. If restoration fails, inspect stored permission snapshots and run targeted recovery.

Set slow mode

ACCESS: Server Owner / AEGIS Admin

1. Open Channel Management > Slow Mode.
2. Select the channel.
3. Choose or enter the cooldown in seconds.
4. Save and verify the channel setting.

Delete a channel

ACCESS: Server Owner / AEGIS Admin

1. Create a backup if the channel contains important material.
2. Select Delete Channel and choose the target.
3. Verify its name, category and purpose.
4. Complete the confirmation.
5. Check the channel was removed and protected management infrastructure was not disturbed.

NOTE: Deletion may remove message history and cannot be undone from AEGIS.

Server lockdown

ACCESS: Server Owner / AEGIS Admin

1. Open Security & System or Channel Management lockdown controls.
2. Choose SERVER LOCKDOWN for an active incident.
3. Review affected channels and apply.
4. Use End Lockdown after the incident.
5. Verify permission snapshots restore intended channel access.

15 Moderation actions

The moderation suite covers warnings, history, escalation, timeouts, kicks, bans, unbans, purges and staff notes. Actions may be blocked by protections and Discord role hierarchy.

Warn a member

ACCESS: Authorized owner/admin or staff

1. Open SERVER CONTROL PANEL > Moderation or STAFF CONTROL PANEL > Warn.
2. Choose the member from the user selector.
3. Enter the reason and submit.
4. Verify the warning appears in Warning History and the moderation log.

Review or clear warnings

ACCESS: Authorized moderation staff

1. Open Warning History or Clear Warnings.
2. Select the member.
3. Review warning entries and any escalation status.
4. For clearing, complete the required confirmation.
5. Verify the resulting warning count.

Timeout and remove timeout

ACCESS: Authorized moderation staff

1. Choose Timeout / Mute and select the member.
2. Set the duration and reason.
3. Confirm and verify the timeout is active.
4. Use Remove Timeout to end it early when authorized.
5. Check logs and member state.

Kick or ban a member

ACCESS: Authorized senior staff or owner/admin

1. Open Kick or Ban in Moderation or the staff panel.
2. Choose the correct member and enter a reason.
3. Confirm after reviewing protected-role restrictions.
4. Verify the action succeeded and the audit log is populated.
5. Use Test Mode for simulation where supported; real actions occur in live mode.

Unban a member

ACCESS: Authorized senior staff or owner/admin

1. Open Unban.
2. Select a banned user or provide a user ID when no selector is available.
3. Enter the reason if requested.
4. Confirm and verify the user is no longer banned.

Purge messages

ACCESS: Authorized moderation staff

1. Open Purge Messages.
2. Select the target channel and permitted count.
3. Review the reason and confirm.
4. Verify the result while respecting protected management channels.

Staff notes

ACCESS: Server Owner / AEGIS Admin

1. Open Staff Notes in the owner/admin moderation panel.
2. Select a member.
3. Add, view or clear relevant notes.
4. Keep notes factual and restrict their distribution.

Automatic warning escalation

ACCESS: Server Owner / AEGIS Admin

1. Open Moderation settings.
2. Review configured warning thresholds and outcomes.
3. Enable or disable escalation and save.
4. Test with a controlled account in Test Mode before live use.
5. Default guidance: 3 warnings = 10-minute timeout; 5 = 60-minute; 7 = 1 day; 10 = ban, unless reconfigured.

16 STAFF CONTROL PANEL and staff security

The private staff panel exposes scoped workflows for moderators. The server owner and AEGIS Admin configure staff tiers, protections and panel repair.

Use the staff panel

ACCESS: Bot Moderator / Bot Senior Moderator

1. Open STAFF CONTROL PANEL with the appropriate staff role.
2. Select Warn, Timeout, Kick, Ban, Reports, Open Tickets, Unban or Purge as authorized.
3. Choose members or records through dropdowns.
4. Provide reasons and confirmations.
5. Allow the completed temporary interaction to close while the permanent dashboard remains.

Assign staff roles

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > Security & System > Staff Security > Assign Staff Roles.
2. Select the Discord member.
3. Choose Bot Moderator or Bot Senior Moderator.
4. Apply Selected Tier and verify the member's roles.
5. Use Remove Selected Tier to revoke their AEGIS staff tier.

Protected members and roles

ACCESS: Server Owner / AEGIS Admin

1. Open Staff Security > Protection Lists.
2. Add or remove protected members and roles.
3. Review protection coverage before testing high-risk moderation.
4. Use Reset Optional Protections only if you understand the effect; the server owner remains protected.

Repair staff panel

ACCESS: Server Owner / AEGIS Admin

1. Open Staff Security > Repair Staff Panel.
2. Run repair when the channel or permanent dashboard is missing.
3. Verify staff-only permissions and the panel message.
4. Test access with a normal member and authorized moderator.

17 Support Center, reports and tickets

Members can report other members or open private tickets. Staff can claim, resolve, dismiss and close these records, with optional retained transcripts.

Report a member

ACCESS: All members

1. Open Support Center > Report Player or run /report.
2. Select the subject member.
3. Describe the issue and provide evidence links only when appropriate.
4. Submit and retain the confirmation/reference.
5. Do not post sensitive evidence in general channels.

Open a ticket

ACCESS: All members

1. Open Support Center > Open Ticket or run /ticket.
2. Enter subject, ticket type and details.
3. Submit; AEGIS creates or opens a private support workflow.
4. Use the ticket channel to communicate with authorized staff.
5. Avoid creating duplicate tickets for the same issue.

Claim and resolve a report

ACCESS: Authorized staff

1. Open STAFF CONTROL PANEL > Reports.
2. Select the report.
3. Choose Assign to Me and review its details.
4. Resolve or Dismiss as justified.
5. Check whether reporter notification is enabled.

Claim and close a ticket

ACCESS: Authorized staff

1. Open STAFF CONTROL PANEL > Open Tickets.
2. Select the ticket and click Assign to Me if appropriate.
3. Assist the member inside the private ticket.
4. Close Ticket when complete.
5. Verify transcript retention or channel cleanup according to BOT SETTINGS.

Configure ticket limits

ACCESS: Server Owner / AEGIS Admin

1. Open BOT SETTINGS > Reports / Tickets.
2. Set maximum open tickets per member and staff options.
3. Configure reporter notification and closed-channel deletion.
4. Save and verify with a test ticket.

18 Moderation logs and audit containment

AEGIS logs selected moderation and management activities. v24.55 prevents ordinary private alliance message edit/delete contents from entering general moderation logs.

Enable log categories

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > Moderation Logs.
2. Select categories such as Deleted Messages, Edited Messages, Warnings, Timeouts, Kicks, Bans, Roles, Nicknames, Alliances and Panel Actions.
3. Use All Categories ON or OFF if appropriate.
4. Save and verify the private log destination.

Repair log channel

ACCESS: Server Owner / AEGIS Admin

1. Choose Repair Log Channel.
2. Verify AEGIS can view and send to the managed log channel.
3. Check that regular members cannot read it.
4. Repeat a benign moderation event to confirm delivery.

Audit private alliance information

ACCESS: Server Owner

1. Do not assume old moderation logs are purged by the v24.55 upgrade.
2. Review legacy logs for historical private message contents.
3. Limit log-channel access to authorized administrators.
4. Do not copy private message content into public support or announcement channels.

19 Security center, anti-raid and lockdown

AEGIS provides configurable flood, mass-mention, raid and new-account thresholds, trusted roles, approved domains and lockdown/recovery actions.

Review security thresholds

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > Security & System > Security.
2. Review flood, mass-mention, join/raid and new-account thresholds.
3. Adjust each value to suit expected community activity.
4. Save and use Test Mode where supported.
5. Review logs for false positives after changes.

Trusted roles and approved domains

ACCESS: Server Owner / AEGIS Admin

1. Open the Security settings.
2. Configure trusted role IDs and approved domains using the offered selectors or text inputs.
3. Review the scope of each exception.
4. Save and retest normal moderation behavior.

Manual and automatic lockdown

ACCESS: Server Owner / AEGIS Admin

1. Monitor security alerts and inspect evidence.
2. Use the manual lockdown option during an incident or allow configured automation to act.

3. Keep administrator and recovery access available.
4. Use End Lockdown after the incident.
5. Verify restored permissions and check health/readiness.

20 Rules, acceptance and verification gate

The rules gate can require members to acknowledge server rules before normal use. Repair and notification tools support onboarding enforcement.

Edit server rules

ACCESS: Server Owner / AEGIS Admin

1. Open Security & System > Rules & Verification Gate.
2. Choose Edit Rules.
3. Write the updated rule text.
4. Choose whether existing members must reaccept, if offered.
5. Save and review the published rules message.

Enable or disable the gate

ACCESS: Server Owner / AEGIS Admin

1. Choose Toggle Gate.
2. Confirm the intended enabled or disabled state.
3. Test the behavior with an unverified member.
4. Review Test Mode simulation behavior when enabled.

Repair rules prompt and notify pending

ACCESS: Server Owner / AEGIS Admin

1. Choose Repair Rules when #rules or Accept Rules controls are missing.
2. Check the persistent acceptance button.
3. Select Notify Pending to remind members who have not accepted.
4. Review Acceptance Stats to confirm progress.

Accept rules as a member

ACCESS: Players

1. Open the server's #rules channel.
2. Read the rules completely.
3. Press Accept Rules.
4. Confirm the system records your acceptance and unlocks any permitted onboarding actions.

21 Backups, database and restoring state

The production Oracle deployment separates application code from persistent state. Backups protect AEGIS configuration, but a Discord channel deletion may not be reconstructable from database state alone.

Create a manual backup

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > Security & System > Backup & Database.
2. Select Backup Now or Manual Backup.
3. Wait for completion and record the result.
4. Use List Backups to confirm the new snapshot exists.

Configure automatic backups

ACCESS: Server Owner / AEGIS Admin

1. Choose Backup Settings.
2. Enable daily backups and set retention count.
3. Verify that the data directory and any configured mirror are writable.
4. Save and validate via /aegis readiness.

List backups and database health

ACCESS: Server Owner / AEGIS Admin

1. Choose List Backups to inspect snapshot filenames and sizes.
2. Open Database Status to run or review SQLite integrity checks.
3. Investigate errors before further deployment changes.
4. Keep an independent application archive and persistent-data backup.

Restore a backup

ACCESS: Server Owner / AEGIS Admin

1. Review which backup should be restored and what data will be overwritten.
2. Take a fresh safety backup of the current state.
3. Choose Restore Latest or the supported recovery workflow.
4. Complete owner/admin confirmation and allow restoration to finish.
5. Run health and readiness and inspect server configuration.

NOTE: Restore is high impact; do not test against production without a recovery plan.

22 Health checks, drift and emergency recovery

AEGIS can detect missing managed infrastructure, repair permission drift and report environment readiness. Automatic repair may create bursts of API traffic on very large servers.

Run /aegis info

ACCESS: All members

1. Type /aegis info in an authorized channel.
2. Review the bot version, runtime mode, uptime and other reported health details.
3. Capture the version when filing a support issue.

Run /aegis readiness

ACCESS: Server Owner / AEGIS Admin

1. Type /aegis readiness as an owner or authorized administrator.
2. Review the database, backup, heartbeat, cloud storage and server configuration checks.
3. Resolve failed items before marking a rollout complete.
4. Rerun after maintenance or role-permission changes.

Run Health Check or Pre-Launch Check

ACCESS: Server Owner / AEGIS Admin

1. Open Security & System > Health & Repair.
2. Choose Run Health Check or Pre-Launch Check.
3. Read every failed or warning item.
4. Use targeted repair first.
5. Rerun the same check to confirm recovery.

Drift / Recovery Check

ACCESS: Server Owner / AEGIS Admin

1. Choose Drift / Recovery Check.
2. Review changed permissions and missing resources.
3. Use Repair Detected Drift when warranted, or acknowledge a known state where supported.
4. Test private alliance visibility again after permission recovery.

Repair Everything

ACCESS: Server Owner / AEGIS Admin

1. Create a safety backup.
2. Select Repair Everything only when smaller repairs are insufficient.
3. Avoid repeated clicks while the operation is running.

4. Review the log output and /aegis readiness result.

Emergency /aegis recovery

ACCESS: Server Owner

1. Sign in as the actual Discord server owner.
2. Run /aegis recovery.
3. Review the emergency backup and recovery effects.
4. Allow persistent views, command syncing and drift recovery to complete.
5. Verify permissions and dashboards after the operation.

NOTE: Do not expose this path to ordinary administrators.

23 BOT SETTINGS reference

BOT SETTINGS centralizes feature toggles, defaults, operational mode, timezone, retention, exports and module resets. Names in the Quick Feature Selector may differ slightly from detailed controls.

General and feature toggles

ACCESS: Server Owner / AEGIS Admin

1. Open SERVER CONTROL PANEL > BOT SETTINGS.
2. Choose General to configure welcome text, channel and reminders.
3. Choose Feature Toggles for onboarding, alliance requests, polls, announcements, advanced events, player dashboard, verification, tickets and related functions.
4. Change settings and Save.
5. Verify at least one member-facing use case for each enabled feature.

Alliance, event, poll and announcement defaults

ACCESS: Server Owner / AEGIS Admin

1. Choose Alliance Defaults to set recruitment and member limits.
2. Choose Event Defaults for capacity, reminders and recurrence.
3. Choose Poll Defaults for duration and anonymity.
4. Choose Announcement Defaults for repeat intervals and mention rules.
5. Save each module separately.

Notification and moderation defaults

ACCESS: Server Owner / AEGIS Admin

1. Open Notification Defaults to configure initial player preferences.
2. Apply defaults to existing profiles only if intentionally requested.

3. Open Moderation to review escalation thresholds.
4. Save and test the changed behavior.

Export configuration or reset a module

ACCESS: Server Owner / AEGIS Admin

1. Choose Export Config to generate a review/backup copy.
2. Store the export securely.
3. Use Reset Module only after checking the affected subsystem and creating a backup.
4. Complete explicit confirmation and rerun readiness.

24 Timezone, Test Mode, Maintenance Mode and retention

The normal production state is Test Mode OFF and Maintenance Mode OFF. Scheduling uses the configured server timezone, and retention applies to supported stored record categories.

Set the server timezone

ACCESS: Server Owner / AEGIS Admin

1. Open BOT SETTINGS > Operational / Timezone.
2. Choose the region and timezone from the paged selectors.
3. Confirm the selection.
4. Verify an upcoming scheduled announcement uses the intended local clock time.

Switch Test Mode

ACCESS: Server Owner / AEGIS Admin

1. Open Operational Settings.
2. Set Test Mode ON before deliberately testing destructive workflows.
3. Save Operational Settings.
4. When testing is complete, set Test Mode OFF and save.
5. Verify /aegis info or settings reflect the new mode.

Maintenance Mode and cooldown

ACCESS: Server Owner / AEGIS Admin

1. Choose Operational Settings.
2. Turn Maintenance Mode ON only during planned maintenance.
3. Set the permitted command cooldown where offered.
4. Save, then later restore normal mode and verify user-facing features.

Configure retention

ACCESS: Server Owner / AEGIS Admin

1. Open BOT SETTINGS > Data Retention.
2. Set retention periods for tickets, reports, events, polls, announcements, profiles and moderation logs.
3. Read whether zero means indefinite retention for that field.
4. Save and optionally run Cleanup Now when appropriate.
5. Verify important audit records are retained as intended.

25 Developer feedback, support and service communication

All members can report bugs or suggest features through the public feedback flow. Reports are queued when direct delivery is temporarily unavailable.

Send developer feedback

ACCESS: All members

1. Run /aegis feedback, or use Send Feedback from the panel.
2. Choose Bug Report, Suggestion or Other Feedback.
3. Enter a short subject and clear reproduction steps.
4. Submit and retain any feedback reference.
5. Exclude Discord bot tokens, private SSH keys and unnecessary personal data.

Use the support server

ACCESS: All users

1. Open the official AEGIS PRIME support server through the configured app information.
2. Read known issues or support guidance.
3. Include AEGIS version, affected feature and error time when reporting a bug.
4. Avoid uploading private alliance transcripts to a public channel.

26 Slash command quick reference

Discord slash commands are typed beginning with /. Available commands and access depend on the installed bot version, feature toggles and member permissions.

/aegis commands

ACCESS: Various; see each command's in-app permissions

1. /aegis info: version, health and configuration summary.
2. /aegis install: get the official installation link.

3. /aegis readiness: production-readiness diagnostics for owner/admin.
4. /aegis setup: launch guided setup.
5. /aegis recovery: owner-only emergency repair.
6. /aegis privacy: read privacy information.
7. /aegis mydata: export your own guild-scoped data.
8. /aegis feedback: send developer feedback.

/alliance commands

ACCESS: Various; alliance authorization applies

1. /alliance setup: configure an alliance as an authorized administrator.
2. /alliance add: add a player when authorized.
3. /alliance remove: remove a player's alliance assignment when authorized.
4. /alliance rank: change a player's rank.
5. /alliance roster and /alliance list: inspect membership and alliances.
6. /alliance apply and /alliance transfer: submit alliance requests.
7. /alliance r4request: request R4 promotion.

/alliancepoll and support commands

ACCESS: Eligible users

1. /alliancepoll create, list, results and close: operate alliance polls within allowed authority.
2. /report: privately report another member.
3. /ticket: open a private support ticket.
4. Check Discord's slash-command hints for required arguments.

27 Privacy, personal data and records

AEGIS maintains per-server user and operation data such as player profiles, alliance ranks, warnings, reports, tickets and configurable retention. Member data export is scoped to the caller.

View privacy information

ACCESS: All members

1. Run /aegis privacy.
2. Read the stored data categories and configured policies.
3. Contact authorized server management for clarification.

Export your data

ACCESS: All members

1. Run /aegis mydata.
2. Follow the private export instructions.
3. Download only your own data.
4. Store or delete the export securely after use.

Handle sensitive records

ACCESS: Server Owner / AEGIS Admin

1. Keep reports, support transcripts and staff notes in restricted channels.
2. Avoid copying alliance private content into broad log channels.
3. Review retention before deleting records.
4. Understand native Discord Administrator access cannot be hidden by a bot.

28 Oracle Cloud operations and troubleshooting

This chapter is for the central AEGIS operator, not ordinary server owners. The application runs under systemd with data in a separate persistent path.

Inspect the service

ACCESS: Cloud operator

1. Connect to the Oracle Ubuntu host through authorized SSH.
2. Run sudo systemctl status aegis-prime --no-pager.
3. Run sudo journalctl -u aegis-prime -n 80 --no-pager to inspect errors.
4. Avoid sharing environment secrets or private key contents in support messages.

Controlled upgrade

ACCESS: Cloud operator

1. Create a new Discord database backup and application rollback archive.
2. Upload and verify the release ZIP, then compile the staged Python files.
3. Stop the systemd service and install application files while preserving the virtual environment, secrets and persistent data.
4. Install required dependencies, check version and restart.
5. Run /aegis readiness and the release's live acceptance tests.

Resolve Discord HTTP 429 warnings

ACCESS: Cloud operator

1. Identify whether warnings are limited to the startup burst or continue later.

2. Use journalctl time filters to find repeated PATCH, PUT, GET or DELETE actions.
3. Do not repeatedly press the same repair or dashboard button while requests are pending.
4. Investigate duplicate background tasks if the same resource is edited continuously.
5. Retest after stabilizing; do not mask errors by disabling audit and safety checks blindly.

Common repair checklist

ACCESS: Owner / Cloud operator

1. Role operation fails: check bot role hierarchy and Manage Roles.
2. Channel repair fails: verify Manage Channels and target permissions.
3. User Manual button broken: check public PDF URL and AEGIS_USER_MANUAL_URL.
4. Persistent dashboard missing: run targeted repair or owner recovery.
5. Scheduled job missing: check timezone, permissions and one-instance runtime.
6. Cloud bot offline: check service, token configuration, data mount and logs.

29 Known limitations and planned improvements

The manual documents the current v24.55 build, not every feature that has been discussed or proposed. Do not treat planned fixes as already deployed.

Owner-only AEGIS Admin manager

ACCESS: Server Owner

1. AEGIS protects the AEGIS Admin role from ordinary Role Management.
2. In v24.55, the advertised Owner: AEGIS Admins control may not be reachable from the normal panel.
3. The actual server owner can assign the zero-native-permissions AEGIS Admin role using Discord Server Settings > Roles > Manage Members.
4. A proper owner-only member selector is a planned enhancement.

Alliance removal inside Assign / Move Player

ACCESS: Server Owner / AEGIS Admin

1. v24.55 provides separate Remove Alliance Role or Remove Player actions.
2. A Remove Member from Alliance choice directly inside Assign / Move Player has been requested for the next release.
3. Until that update is deployed, use the existing separate removal workflow.

Document and operational safety

ACCESS: All users

1. This guide assumes v24.55 CLOUD READY; use /aegis info to check the running version.

2. Discord changes interfaces and displays; the corresponding named tool may appear through a Quick Feature Selector.
3. Only live role/privacy testing confirms access control, not syntax compilation.
4. Public App Directory discovery remains a separate publishing decision.