SIf4jReporter

该类同样是继承自 AbstractReporter 抽象类, 实现了 Scheduled 接口。

在该类中有一个属性:

```
//初始大小大致符合 150 个带有默认 scope 设置的指标
private int previousSize = 16384;
```

在 report 方法中有一个 tryReport 方法用来发送数据。

```
private void tryReport() {
   // initialize with previous size to avoid repeated resizing of
backing array
   // pad the size to allow deviations in the final string, for
example due to different double value representations
   StringBuilder builder = new StringBuilder((int) (previousSize *
1.1));
   builder
       .append(lineSeparator)
       .append("=========== Starting metrics
report ======
       .append(lineSeparator);
   builder
       .append(lineSeparator)
       .append("-- Counters --
        ----")
       .append(lineSeparator);
    for (Map.Entry<Counter, String> metric : counters.entrySet()) {
       builder
           .append(metric.getValue()).append(":
").append(metric.getKey().getCount())
           .append(lineSeparator);
   }
   builder
       .append(lineSeparator)
       .append("-- Gauges ----
       .append(lineSeparator);
```

```
for (Map.Entry<Gauge<?>, String> metric : gauges.entrySet()) {
           .append(metric.getValue()).append(":
").append(metric.getKey().getValue())
           .append(lineSeparator);
   }
   builder
       .append(lineSeparator)
       .append("-- Meters ---
          ----")
       .append(lineSeparator);
   for (Map.Entry<Meter, String> metric : meters.entrySet()) {
       builder
           .append(metric.getValue()).append(":
").append(metric.getKey().getRate())
           .append(lineSeparator);
   }
   builder
       .append(lineSeparator)
       .append("-- Histograms
                 ----")
       .append(lineSeparator);
   for (Map.Entry<Histogram, String> metric :
histograms.entrySet()) {
       HistogramStatistics stats =
metric.getKey().getStatistics();
       builder
           .append(metric.getValue()).append(":
count=").append(stats.size())
           .append(", min=").append(stats.getMin())
           .append(", max=").append(stats.getMax())
           .append(", mean=").append(stats.getMean())
           .append(", stddev=").append(stats.getStdDev())
           .append(", p50=").append(stats.getQuantile(0.50))
           .append(", p75=").append(stats.getQuantile(0.75))
           .append(", p95=").append(stats.getQuantile(0.95))
           .append(", p98=").append(stats.getQuantile(0.98))
           .append(", p99=").append(stats.getQuantile(0.99))
           .append(", p999=").append(stats.getQuantile(0.999))
           .append(lineSeparator);
   }
   builder
       .append(lineSeparator)
       .append("============ Finished metrics
```

```
.append(lineSeparator);
LOG.info(builder.toString());

previousSize = builder.length();
}
```

要使用此 reporter, 你必须复制 /opt/flink-metrics-slf4j-1.9.0.jar 到 /lib 文件夹中。

配置示例:

```
metrics.reporter.slf4j.class:
org.apache.flink.metrics.slf4j.Slf4jReporter
metrics.reporter.slf4j.interval: 60 SECONDS
```

https://ci.apache.org/projects/flink/flink-docs-stable/monitoring/metrics.html#slf4j-orgapacheflinkmetricsslf4jslf4jreporter