

Computer Organization

Lab4 MIPS(3)

Directive, Memory, Machine Code



Topics

Directives

- > .data, .text
- > .macro, .endmacro (optional)
- > .align (0,1,2)
- > .globl vs .extern , .globl main
 - practice 1-1,1-2 (page 9)

Memory


- > Static Storage vs Dynamic Storage(stack vs heap)
- practice 1-3 (page10)

Practice 2

Machine Code and Addressing



Directives in Mars





Directive: .macro, .endmacro

Macros:

A **pattern-matching** and **replacement** facility that provide a simple mechanism to name a frequently used sequence of instructions.

- Programmer invokes the macro.
- > Assembler replaces the macro call with the corresponding sequence of instructions.

Macros vs Subroutines:

- > Same: permit a programmer to create and name a new abstraction for a common operation.
- > **Difference:** Unlike subroutines, macros do not cause a subroutine call and return when the program runs since a macro call is replaced by the macro's body when the program is assembled.



Demo #1

.text print_string: addi \$sp,\$sp,-4 sw \$v0,(\$sp)

> li \$v0,4 syscall

lw \$v0,(\$sp) addi \$sp,\$sp,4

jr \$ra

Assembler replaces the macro call with the corresponding sequence of instructions.

Q1: What's the **difference** between macro and procedue?

Q2: While save the macro's defination(on the right hand in this slides) in an asm file, and assamble it, what's the assembly result?

Is the macro's defination file runable?

Q3: While save the procedure's defination(on the left hand in this slides) in an asm file, and assemble it, what's the assembly result?

Is the procedure defination file runable?

```
.macro print string(%str)
.data
    pstr: .asciiz %str
.text
    addi $sp,$sp,-8
    sw $a0,4($sp)
    sw $v0,($sp)
    la $a0,pstr
    li $v0,4
    syscall
    lw $v0,($sp)
    lw $a0,4($sp)
    addi $sp,$sp,8
end macro.
```



Directive: .align(Demo #2-1)

.data #A

str1: .ascii "Welcome"

str2: .ascii "to"

str3: .asciiz "MIPS32World"

.text

la \$t0, **str2**

lb \$t1,(\$t0)

addi \$t1,\$t1,-32

sw \$t1,(<mark>\$t0</mark>)

la \$a0,str1

li \$v0,4

syscall

li \$v0,10 syscall .data #B

str1: .ascii "Welcome"

str2: .ascii "to"

str3: .asciiz "MIPS32World"

.text

la \$t0, **str2**

lw \$t1,(\$t0)

addi \$t1,\$t1,-32

sb \$t1,(<mark>\$t0</mark>)

la \$a0,str1

li \$v0,4

syscall

li \$v0,10

syscall

Which demo(s) would invoke an exception "fetch address not aligned on word boundary 0x10010007"?

Which instruction would invoke the exception? Ib, sw, lw, sb?

Tips:

While transfering data, the address of data in memory is required to be aligned according to the bit width of data.



Directive: .align(Demo #2-2)

.align : align next data item on specified byte boundary(0=byte, 1=half, 2=word, 3=double)

Which demo(s) would run without exception?
Which demo(s) would get the output "WelcomeToMIPS32World" ?

.data #A

str1: .ascii "Welcome"

str2: .ascii "to"

str3: .asciiz "MIPS32World"

.text

la \$t0, **str2**

Ih \$t1,(\$t0)

addi \$t1,\$t1,-32

sh \$t1,(\$t0)

la \$a0,str1

li \$v0,4

syscall

li \$v0,10

syscall

.data #B

str1: .ascii "Welcome"

.align 2

str2: .ascii "to"

str3: .asciiz "MIPS32World"

.text

la \$t0, **str2**

I<mark>w</mark> \$t1,(\$t0)

addi \$t1,\$t1,-32

sw \$t1,(\$t0)

la \$a0,str1

li \$v0,4

syscall

li \$v0,10

syscall

.data #C

align 2

str1: .ascii "Welcome"

str2: .ascii "to"

str3: .asciiz "MIPS32World"

.text

la \$t0, **str2**

Iw \$t1,(\$t0)

addi \$t1,\$t1,-32

s<mark>w</mark> \$t1,(\$t0)

la \$a0,str1

li \$v0,4

syscall

li \$v0,10

syscall

.data #D

str1: .ascii "Welcome"

str2: .ascii "to"

str3: .asciiz "MIPS32World"

.text

la \$t0, **str2**

lb \$t1,(\$t0)

addi \$t1,\$t1,-32

s<mark>b</mark> \$t1,(\$t0)

la \$a0,str1

li \$v0,4

syscall

li \$v0,10

syscall



Directive: .globl vs .extern

- >.include: insert the contents of the specified file, put filename in quotes
- **>.globl**: declare the listed **label**(s) as global to enable referencing from other files
- **>.extern:** declare the listed **label** and byte length to be a global **data** field

> Local label

➤ A label referring to an object that can be used ONLY within the FILE in which it is defined.

> External label

 A label referring to an object that can be referenced from
 FILE other than the one in which it is defined.

Find the usage of ".extern" and ".globl" on Demo 3-1 and 3-2 What's the relationship between globl main and the entrance of program? What will happen if an external data have the same name with a local data?



Demo #3-1

it's in print callee.it's the default_str it's in print caller.it's the default_str

- Q1. Is the running result same as the sample snap?
- Q2. How many "default str" are defined in "print callee.asm"?
- Q3. While executing the instruction "la \$a0,default_str" in these two files, which "default_str" is used?

```
## "print caller.asm" ##
.include "print callee.asm"
.data
  str caller:
               .asciiz "it's in print caller."
.text
.globl main
main:
     jal print callee
     addi $v0,$zero,4
     la $a0,str caller
     syscall
     la $a0, default str ###which one?
     syscall
     li $v0,10
     syscall
```

```
## "print callee.asm" ##
.extern default str 20
.data
     default str:
                     .asciiz "it's the default str\n"
     str callee:
                     .asciiz "it's in print callee."
.text
                addi $sp,$sp,-4
print callee:
                sw $v0,($sp)
                addi $v0,$zero,4
                la $a0,str callee
                syscall
                la $a0, default str ###which one?
                syscall
                lw $v0,($sp)
                addi $sp,$sp,4
                jr $ra
```



Demo #3-2

In Mars, set "Assemble all files in directory", put the following files in the same directory, then run it. Practice 1-1: answer the questions on last page again.

Practice 1-2: Find the value of globl lable "main", "print callee" and the initial value of \$PC

```
.data
.data
                                                                                            defaulte str 20
   str caller:
                    .asciiz
                                  "it's in print caller."
                                                                             .extern
                                                                             str callee:
                                                                                                  .asciiz
                                                                                                               "it's in print callee."
.text
.globl main
                                                                             defaulte str:
                                                                                                  .asciiz
                                                                                                               "ABC\n"
main:
                                                                      .text
      jal print_callee
                                                                      .globl print callee
                                                                      print callee:
                                                                                          addi $sp,$sp,-4
      addi $v0,$0,0x0a636261
                                                                                           sw $v0,($sp)
      sw $v0, defaulte str
                                             Settings Tools Help
                                                                                           addi $v0,$zero,4
                                             Show Labels Window (symbol table)
      addi $v0,$zero,4
                                                                                           la $a0,str callee
                                             Program arguments provided to MIPS program
      la $a0,str_caller
                                                                                           syscall
                                             Popup dialog for input syscalls (5,6,7,8,12)
                                                                                           la $a0, defaulte str
      syscall
                                             Addresses displayed in hexadecimal
      la $a0, defaulte str
                                                                                           syscall

☑ Values displayed in hexadecimal

      syscall

☑ Assemble file upon opening

                                                                                           lw $v0,($sp)
                                             Assemble all files in directory
      li $v0,10
                                                                                           addi $sp,$sp,4
                                             Assembler warnings are considered errors


☑ Initialize Program Counter to global 'main' if defined


                                                                                           jr $ra
      syscall
```



Memory: Stack vs Heap

- > Stack: used to store the local variable, usually used in calle.
- > Heap: The heap is reserved for sbrk and break system calls, and it not always present.





Pracitce 1-3: Using Mars to find the value of ".text base address", ".data base address", ".extern base address", "heap base address" and "stack base address".



Demo #4-1

The following demo(composed of 4 pieces on this page and the next) is supposed to get and store the data from input device, get the minimal value among the data, the number of input data is determined by user.

```
#piece 1/4
.include "macro print str.asm"
.data
     min value: .word 0
.text
     print string("please input the number:")
     li $v0,5
                     #read an integer
     syscall
     move $s0,$v0
                    #s0 is the number of integers
     sll $a0,$s0,2
                     #new a heap with 4*$s0
     li $v0.9
     syscall
     move $s1,$v0 #$s1 is the start of the heap
                    #$s2 is the point
     move $s2,$v0
```

```
print_string("please input the array\n") #piece 2/4

add $t0,$0,$0

loop_read:

li $v0,5  #read the array
    syscall
    sw $v0,($s2)

addi $s2,$s2,4
    addi $t0,$t0,1
    bne $t0,$s0,loop_read
```

While the 1st input number is 0 or 1, what will happen? why? Modify this demo to make it better



Demo #4-2

```
#piece 3/4
                    #initialize the min value
     lw $t0,($s1)
     sw $t0,min value
     li $t0,1
     addi $s2,$s1,4 #$s1 is the start of the heap
loop find min:
     lw $a0,min value
     lw $a1,($s2)
     jal find min
     sw $v0,min value
     addi $s2,$s2,4
                                 #$s2 is the point
     addi $t0,$t0,1
     bne $t0,$s0 loop find min #s0 is the number of integers
     print string("the min value : ")
     li $v0,1
     lw $a0,min value
     syscall
               #end is defined in the file is macro print str.asm
     end
```

```
#piece 4/4
find_min:

move $v0,$a0
blt $a0,$a1,not_update
move $v0,$a1

not_update:


jr $ra
```

```
please input the number:3
please input the array
-1
0
1
the min value : -1
-- program is finished running --
```




Practice2

- Assember the MIPS code of "Demo4" on page 12 and 13, answer the following question:
 - > P2-1: Find three instructions in Demo4, which belong to R, I and J in the code of Demo 4,
 - what are the opcode of them?
 - what' s the index of register in the R type instruction?
 - what' s the immediate in the I type instruction?
 - what' s the address of J type instruction?
 - P2-2: Find the relationship between the binary part of the branch and jump instruction code and the address of the jumping destination
 - > step1: The value of two lables: loop_find_min, find_min
 - > step2: What' s the "address" in the machine code of instruction "jal find_min" and "bne \$t0,\$s0 loop_find_min"
 - Calculate the jumping destination based on the "address" got from step2, are the jumping destinations same with the value got from step1?



PC-relative addressing

- Target address = PC + constant × 4
- PC already incremented by 4 by this time
- Jump (j and jal) targets could be anywhere in text segment
 - Encode full address in instruction



- (Pseudo)Direct jump addressing
 - Target address = PC31...28 : (address × 4)



Tips: Machine Code of MIPS(1)

Name			Fle	Comments					
Field size	6 bits	5 bits	5 bits	5 bits	5 bits	6 bits	All MIPS instructions are 32 bits long		
R-format	ор	rs	rt	rd	shamt	funct	Arithmetic instruction format		
I-format	ор	rs	rt	address/immediate			Transfer, branch, imm. format		
J-format	ор		target address				Jump instruction format		

				pp(31:26)				
28–26	0(000)	1(001)	2(010)	3(011)	4(100)	5(101)	6(110)	7(111)
31-29								
0(000)	R-format	Bltz/gez	jump	jump & link	branch eq	branch ne	blez	bgtz
1(001)	add immediate	addiu	set less than imm.	set less than imm. unsigned	andi	ori	xori	load upper immediate
2(010)	TLB	F1Pt						
3(011)								
4(100)	load byte	load half	lwl	load word	load byte unsigned	load half unsigned	lwr	
5(101)	store byte	store half	swl	store word			swr	
6(110)	load linked word	1wc1						
7(111)	store cond. word	swc1						



Tips: Machine Code of MIPS(2)

Name			Fie	Comments				
Field size 6 bits	5 bits	5 bits	5 bits	5 bits	6 bits	All MIPS instructions are 32 bits lon		
R-format	ор	rs	rt	rd	shamt	funct	Arithmetic instruction format	
I-format	ор	rs	rt	address/immediate			Transfer, branch, i mm. format	
J-format	ор		target address			Jump instruction format		

		- Op	(31:26)=00000	o (K-Tormat)	, rance(5.0)			
2-0	0(000)	1(001)	2(010)	3(011)	4(100)	5(101)	6(110)	7(111)
5-3								
0(000)	shift left logical		shift right logical	sra	sllv		srlv	srav
1(001)	jump register	jalr			syscall	break		
2(010)	mfhi	mthi	mflo	mtlo				
3(011)	mult	multu	div	divu				1
4(100)	add	addu	subtract	subu	and	or	xor	not or (nor)
5(101)			set1.t.	set l.t. unsigned				
6(110)	6				11,			
7(111)								





Tips on Mars

To make the instruction labled by 'global main' as the 1st instruction to run, do the following settings.

In Mars 'manual:

Settings - Initialize Program Counter to global 'main' if defined







Tips: macro_print_str.asm

```
.macro print_string(%str)
   .data
   pstr: .asciiz %str
   .text
   la $a0,pstr
   li $v0,4
   syscall
.end macro
.macro end
   li $v0,10
   syscall
.end macro
```

Define and use macro, get help form help page of Mars