Samba:File Share:
```
Ports: 139, 445
Packages: samba samba-common samba-client
Service: smb nmb
Config: /etc/samba/smb.conf
```

On Server machine:
```
# dnf install samba samba-common samba-client -y
# mkdir /admin
# touch /admin/file{1..10}.txt
# chmod -R 755 /admin
# chown -R nobody:nobody /admin
```

```
# vim /etc/samba/smb.conf

[global]
workgroup = WORKGROUP

Go to end of the file & add :

[admin]
path =  /admin
browsable = yes
writable = yes
guest ok = yes
read only = no
:wq

To check:
```
```
# testparm
# systemctl start smb nmb
```

```
# systemctl enable smb nmb

# systemctl status smb nmb

[+] Enable SAMBA in firewalld.

[+] setenforce 0

On Client:
```````````
dnf install samba-client -y [RedHat/CentOS]
apt install samba-client -y [Debian]

Access:
````````
# smbclient '\\192.168.206.100\admin'
OR
# smbclient '\\master.het.com\admin'

Enter WORKGROUP\root's password: [just hit enter]
Anonymous login successful
smb: \> ls
smb: \> exit
```

```
_____________
Secure Samba Share Directory:
```````````````````````````````


groupadd smb_group
useradd -G smb_group smbuser
smbpasswd -a smbuser
chmod -R 770 /admin
chown -R root:smb_group /admin

Add these lines to define to secure samba share in smb.conf.

[admin]
path = /admin
valid users = @smb_group
```
```

```
guest ok = no
writable = no
browsable = yes

# systemctl restart smb nmb


_________________
Client:
`````````
dnf install samba-client -y [RedHat/CentOS]
apt install samba-client -y [Debian]
smbclient '\\192.168.206.140\admin' -U smbuser

smb: \> get filename.txt
smb: \> put local_file.txt
smb: \> recurse ON
smb: \> prompt OFF
smb: \> mput *.pdf

Permanent Mount:
````````````````
Step 1: Install Required Packages
(Common Internet File System - cifs)
# dnf install cifs-utils -y

Step 2: Create a Mount Point
# mkdir -p /mnt/smbshare

Step 4: Mount Automatically at Boot (Permanent)
# vim /etc/fstab

//192.168.1.101/sharename /mnt/smbshare cifs defaults,username=user,password=pass 0 0

:wq

# systemctl daemon-reload
# mount -a



Windows:
`````````
1) Open RUN

win + r

2) \\server'sIP\admin

username: user
password: ******
```
```