```
 Postfix Mail Server   -- SMTP  -- 25 -- MTA
 Dovecot: an IMAP and POP3 server
``````````````````````````````````
SMTP   - 25 - postfix
POP3   - 110 - dovecot
IMAP   - 143 - dovecot

dnf install dovecot -y

vim /etc/dovecot/dovecot.conf

Line 24 - uncomment
protocols = imap pop3 lmtp

line 30: uncomment and change (if not use IPv6)
listen = *, ::

vim /etc/dovecot/conf.d/10-master.conf

Postfix smtp-auth
unix_listener auth-userdb {
    mode = 0666
    user = postfix
    group = postfix

vim /etc/dovecot/conf.d/10-auth.conf

line 10: uncomment and change (allow plain text auth)
disable_plaintext_auth = no

line 100: add
auth_mechanisms = plain login

vim /etc/dovecot/conf.d/10-ssl.conf

line 8: change (not require SSL)
ssl = no

vim /etc/dovecot/conf.d/10-mail.conf
mail_location = maildir:~/Maildir # Line 24 - uncomment
mail_location = mbox:~/mail:INBOX=/var/spool/mail/%u # Line 25 - uncomment

:wq

chmod 666 /var/spool/mail/*

systemctl enable dovecot
systemctl start dovecot
lsof -i:110
lsof -i:143
lsof -i:25

firewall-cmd --zone=public --add-service={smtp,imap,pop3} --permanent
firewall-cmd --reload
```

---
```