

11.9.9 Starting a remote copy Consistency Group

When a remote copy consistency group is created, the remote copy process can be started, for all the relationships that are part of the consistency groups.

To start a consistency group, open the **Copy Services** → **Remote Copy** panel, right-click the consistency group to be started, and select **Start**, as shown in Figure 11-140.




Figure 11-140 Starting a remote copy Consistency Group

11.9.10 Switching a relationship copy direction

When a remote copy relationship is in the Consistent synchronized state, the copy direction for the relationship can be changed. Only relationships that are not a member of a Consistency Group, or the only relationship in a Consistency Group, can be switched. In any other case, consider switching the Consistency Group instead.

Important: When the copy direction is switched, it is crucial that no outstanding I/O exists to the volume that changes from primary to secondary because all of the I/O is inhibited to that volume when it becomes the secondary. Therefore, careful planning is required before you switch the copy direction for a relationship.

To switch the direction of a remote copy relationship, complete the following steps:

1. Open the **Copy Services** → **Remote Copy** panel.
2. Right-click the relationship to be switched and select **Switch**, as shown in Figure 11-141.




Figure 11-141 Switching remote copy relationship direction