

Tiger VNC with Mate Desktop

TigerVNC is an open-source implementation of VNC (Virtual Network Computing) that allows you to remotely access and control another computer's desktop GUI.

Installation Steps:

Step-1: Install the tigervnc

```
# sudo dnf install tigervnc-server -y (RHEL/centos/rocky)
```

```
[siddharrth@master ~]$ sudo dnf install tigervnc-server -y
[sudo] password for siddharrth:
Last metadata expiration check: 0:07:33 ago on Tue 07 Apr 2026 08:04:12 AM EDT.
Dependencies resolved.
=====
Package                                Architecture      Version           Repository        Size
=====
Installing:
tigervnc-server                        x86_64            1.15.0-8.el8_10.rocky.0.1  appstream         316 k
Installing dependencies:
tigervnc-selinux                       noarch            1.15.0-8.el8_10.rocky.0.1  appstream         54 k
Transaction Summary
=====
Install 2 Packages

Total download size: 370 k
Installed size: 707 k
Downloading Packages:
(1/2): tigervnc-selinux-1.15.0-8.el8_10.rocky.0.1.noarch.rpm      81 kB/s | 54 kB      00:00
(2/2): tigervnc-server-1.15.0-8.el8_10.rocky.0.1.x86_64.rpm     425 kB/s | 316 kB     00:00
-----
Total                                                                271 kB/s | 370 kB     00:01
Running transaction check
Transaction check succeeded.
Running transaction test
Transaction test succeeded.
Running transaction
  Preparing                : 1/1
  Running scriptlet: tigervnc-selinux-1.15.0-8.el8_10.rocky.0.1.noarch 1/2
  Installing           : tigervnc-selinux-1.15.0-8.el8_10.rocky.0.1.noarch 1/2
  Running scriptlet: tigervnc-selinux-1.15.0-8.el8_10.rocky.0.1.noarch 1/2
  Installing           : tigervnc-server-1.15.0-8.el8_10.rocky.0.1.x86_64 2/2
  Running scriptlet: tigervnc-server-1.15.0-8.el8_10.rocky.0.1.x86_64 2/2
  Verifying            : tigervnc-selinux-1.15.0-8.el8_10.rocky.0.1.noarch 1/2
  Verifying            : tigervnc-server-1.15.0-8.el8_10.rocky.0.1.x86_64 2/2

Installed:
  tigervnc-selinux-1.15.0-8.el8_10.rocky.0.1.noarch
  tigervnc-server-1.15.0-8.el8_10.rocky.0.1.x86_64
Complete!
```

Ubuntu

```
# sudo apt install tigervnc-viewer
```

```
# sudo apt install tigervnc-standalone-server tigervnc-common
```

```
To install mate desktop full version ----- # sudo apt install ubuntu-mate-desktop -y
```

Step-2: Create a VNC Password

```
# vncpasswd
```

```
[siddharrth@master ~]$ vncpasswd
Password:
Verify:
Would you like to enter a view-only password (y/n)? n
A view-only password is not used
```

Step-3: Start the VNC server

```
# vncserver
```

```
[siddharrth@master ~]$ vncserver
WARNING: vncserver has been replaced by a systemd unit and is now considered deprecated and removed in upstream.
Please read /usr/share/doc/tigervnc/HOWTO.md for more information.
New 'master.localdomain:1 (siddharrth)' desktop is master.localdomain:1
Starting applications specified in /home/siddharrth/.vnc/xstartup
Log file is /home/siddharrth/.vnc/master.localdomain:1.log
```

Step-3: Configure VNC Desktop

```
# vi ~/.vnc/xstartup
```

```
[siddharrth@master ~]$ vi ~/.vnc/xstartup
4L, 85C written
```

Replace the content

```
#!/bin/bash
unset SESSION_MANAGER
unset DBUS_SESSION_BUS_ADDRESS
exec mate-session &
```

```
#!/bin/bash
unset SESSION_MANAGER
unset DBUS_SESSION_BUS_ADDRESS
exec mate-session &
```

Make executable:

```
chmod +x ~/.vnc/xstartup
```

```
[siddharrth@master .vnc]$ chmod +x ~/.vnc/xstartup
```

Step-4: Verify Running Session

```
# vncserver -list
```

```
[siddharrth@master ~]$ vncserver -list
WARNING: vncserver has been replaced by a systemd unit and is now considered deprecated and removed in upstream.
Please read /usr/share/doc/tigervnc/HOWTO.md for more information.
TigerVNC server sessions:
X DISPLAY #      PROCESS ID
:1          29362
```

Step-5: Add to firewall (if firewall is setup)

```
# sudo firewall-cmd --add-port=5901/tcp --permanent
```

```
# sudo firewall-cmd --reload
```

```
[siddharrth@master ~]$ sudo firewall-cmd --add-port=5901/tcp --permanent
success
[siddharrth@master ~]$ sudo firewall-cmd --reload
success
```

To check port is added

```
# ss -tulnp | grep 5901
```

```
[siddharrth@master ~]$ ss -tulnp | grep 5901
tcp  LISTEN  0      5            0.0.0.0:5901      0.0.0.0:*    users:((("Xvnc",pid=29362,fd=6))
tcp  LISTEN  0      5            [::]:5901        [::]:*      users:((("Xvnc",pid=29362,fd=7))
[siddharrth@master ~]$ sudo firewall-cmd --list-ports
22/tcp 300/tcp 5901/tcp 8649/udp
```

Step-6: Check SELinux

getenforce

It should be Permissive



If not,


setenforce 0

```
[siddharrth@master ~]$ getenforce
Enforcing
[siddharrth@master ~]$ sudo setenforce 0
[siddharrth@master ~]$ getenforce
Permissive
```

Step-7: Connect in tigervnc

VNC server: 10.10.40.88:1





Step-8: To stop VNC server

```
# vncserver -kill :1
```

```
[siddharth@master ~]$ vncserver -kill :1
WARNING: vncserver has been replaced by a systemd unit and is now considered deprecated and removed in upstream.
Please read /usr/share/doc/tigervnc/HOWTO.md for more information.
Killing Xvnc process ID 29362
```

Troubleshoots

- If connection is refused, check firewall and port list.
- Check selinux. It should be Permissive.
- If still, can't connect follow these steps:
 - Check `# ss -tulnp | grep 5901`
 - If the output is like this `127.0.0.1:5901`, means it can connect only with ubuntu, not with windows.
 - `# vncserver -kill :1` ----- kill the process
 - `# vncserver :1 -localhost no` ----- start the process, not inside the localhost
 - Check `# ss -tulnp | grep 5901`

- It should show like this '0.0.0.0:5901' instead of this '127.0.0.1:5901'

○