

Thinlinc in linux machine with mate desktop

ThinLinc - ThinLinc is a remote desktop server that allows multiple people to log into a Linux server simultaneously. It is based on VNC and SSH

MATE - MATE is a Desktop Environment (DE). It is the graphical interface you see: the taskbar, the start menu, the desktop icons, and the file manager.

Steps to be followed for this

Step-1: First install the mate desktop to linux machine

```
# sudo yum update -y  
  
# sudo dnf install mate-desktop
```

Step-2: Download and install Thinlinc

```
# wget https://www.cendio.com/downloads/server/tl-4.20.0-server.zip
```

Unzip the zip file

```
# unzip tl-4.20.0-server.zip
```

Install the thinlinc

```
# ./install-server
```

Follow and accept the t&c

```
Externally reachable address to use [ip/hostname/manual]? ip  
  
Administrator contact  
=====
```

ThinLinc will send administrative messages, for example license warnings, to this email address. You can add multiple email addresses separated by spaces.

```
Administrator email []?
```

```
A supported firewall frontend has been detected. Do you want to  
configure it to allow ThinLinc services to be reachable from other  
machines?  
  
* OpenSSH service: Allow users access via the native ThinLinc client  
* ThinLinc Web Access service: Allow users access via a web browser  
* ThinLinc Web Administration service: Allow remote administration of  
ThinLinc  
* ThinLinc master service: Allow this machine to control other ThinLinc  
agent machines  
* ThinLinc agent service: Allow this machine to be controlled by a  
ThinLinc master machine  
  
Configure the firewall for OpenSSH service? [Yes/no]? yes  
Configure the firewall for ThinLinc Web Access service? [Yes/no]? yes  
Configure the firewall for ThinLinc Web Administration service? [Yes/no]? yes  
Configure the firewall for ThinLinc master service? [Yes/no]? yes  
Configure the firewall for ThinLinc agent service? [Yes/no]? yes  
  
Configuring and enabling ThinLinc firewall services... done.  
  
The local firewall has been configured to allow the chosen ThinLinc  
services to be accessed.  
  
Press Enter to continue...
```

Step-3: configure firewall (If firewall is setup)

```
# sudo firewall-cmd --permanent --add-service=ssh  
# sudo firewall-cmd --permanent --add-port=300/tcp  
# sudo firewall-cmd --reload
```

Step-4: Start the services

```
# sudo systemctl start vsmserver vsmagent tlwebaccess  
# sudo systemctl status vsmserver  
# sudo systemctl status vsmagent  
# sudo systemctl status tlwebaccess
```

Vsmserver - The core ThinLinc service that manages all remote desktop sessions and user connections.

Vsmagent - Lightweight agent running on each server that works with vsmserver to manage actual desktop sessions.


tlwebaccess - Web interface/server that lets users connect via web browser instead of downloading a client.

Step-5: Access ThinLinc through web

<https://10.10.40.88:300>

Note: If you get any error or issue with login reboot the machine

Enter the credentials



The image shows the ThinLinc login web interface. At the top is the ThinLinc logo, consisting of a blue square icon with a white stylized 'f' and the text 'ThinLinc' in blue. Below the logo are two input fields: 'Username' with the text 'siddharth' and 'Password' with masked characters '.....'. To the right of the password field is an eye icon for toggling visibility. Below the input fields is a blue 'Log in' button. At the bottom, there is a horizontal line, followed by the text 'Version 4.20.0' and 'Copyright © 2025 Cendio AB'.

Select the desktop service

--> Here mate desktop is selected

