shimmerstuff

Manual. Free and open source by Studio 87. Support: ko-fi.com/studio87

Intro

shimmerstuff is a shimmer reverb and a shimmer delay in one plugin, with input and wet effects and a routing view. Shimmer means the tail is pitch shifted (for example up an octave) and fed back, so it climbs as it fades.

It is free and open source, made by Studio 87. It collects nothing and works fully offline.

Quick start

- Put shimmerstuff on a pad, a vocal or a synth. Pick a main preset at the top right.
- Reverb tab: choose a type, then drag the yellow dot in the decay view (sideways for Decay, up and down for Size).
- Delay tab: set Time and Feedback; Shift sets how far each repeat climbs or falls in pitch.
- FX and Routing tab: drag the boxes to run reverb and delay in series or side by side.
- Hover any control for one second to read what it does.

Tabs are views

Shimmer Reverb, Shimmer Delay and FX and Routing are three views of the same plugin, made to fine tune each part. The routing and the on or off switches you chose stay active whichever tab is open. The ON button on the Reverb and Delay tabs is the same switch as the power icon on the box in the routing view (and the same host parameter).

Reverb

Five types: plate, hall, shimmer plate, shimmer hall and velvet. Decay is the tail length, Damping darkens it, Pre-delay delays its start, Size is the room size, Modulation adds movement. Shimmer pitch and Shimmer set how much pitch shifted tail is fed back (a second voice is available). Wet HP and Wet LP shape the tail only. The decay view shows the energy decay of the real reverb, measured live.

Delay

Time, Feedback, Shift (semitones per repeat), Shimmer (how much of the repeat is shifted), Damping and Mix. Drag the first bar in the echo view for the time, any bar up or down for the feedback.

FX and routing

Input FX (high-pass, low-pass and antialiased saturation) sit before the effects. Wet FX act on the effect signal only: saturation, a three band squash (quiet up, loud down), stereo width, a duck and a boost. The duck can follow the source, run free in Hz, or lock to the host tempo with eight shapes. Its source can be the plugin input or the sidechain input (turn it on in your DAW). The routing view shows Input FX, Reverb, Delay and Wet FX. Drag a box to another column to put it in series, or onto a column to put it in parallel. The power corner switches a box on or off.

Presets

Each tab has its own preset list (factory and your own) for just that part, and the Main preset list at the top right sets the whole plugin: reverb, delay, FX and routing, including which units are on. Save writes your preset on this computer. The graph (routing) is saved with the preset and with your project, but it is not an automatable parameter.

Recommendations

- Pad or vocal: Shimmer Hall, decay 6 s, Wet HP 300 Hz, Mix 30 %.
- Pumping tail: Wet FX duck 1/4 BPM sync, source Plugin input.
- Climbing echoes: Delay only, Shift +12, Feedback 55 %.

Interface tour

The numbered picture below is the plugin window (Shimmer Reverb view). The list names every control.

Support

If it helps your music you can support the project at ko-fi.com/studio87. The plugin never asks and never collects anything.

Interface tour

Numbered pink badges mark every control. The list below gives the name and the full info-bubble text of each. The picture is the plugin window itself.



#	Control	What it does
1	Previous preset	Previous preset for this tab.
2	Preset list	Presets for this tab: factory ones and your own. Moving a control shows Custom.
3	Next preset	Next preset for this tab.
4	Save	Save this tab's settings as your own preset (kept on this computer).
5	More	Delete your presets or open the presets folder.
6	Guide	Quick guide: what each view and control does.
7	Settings	Info bubbles and the presets folder.
8	About & Support	About Studio 87, privacy, and ways to support the project.
9	Shimmer Reverb	The reverb view: plate, hall, shimmer plate, shimmer hall and velvet.
10	Shimmer Delay	The delay view: echoes that climb (or fall) in pitch with every repeat. The routing stays as you set it on every tab.
11	FX and Routing	Route the reverb and delay in series or side by side, and add saturation, squash, duck and width.
12	Main preset	Main presets set the whole plugin: reverb, delay, FX and routing.
13	Save main preset	Save the whole plugin as your own main preset.
14	Decay	The measured decay of the real reverb. Yellow dot: decay (sideways) and size (up or down). Cyan: pre-delay. Blue: damping. Orange: shimmer. Pink: mix.
15	Tone	Live spectrum of the input and output with draggable filter lines.
16	Decay view	Drag the coloured dots; double-click a dot to reset it.
17	Level	Input and output peaks, RMS, RT60, and the clip light.

#	Control	What it does
18	Peak reset	Clears the held peaks and the clip light.
19	ON	Switches the reverb on or off. Same switch as the power icon in the routing diagram.
20	Type	Plate, hall, shimmer plate, shimmer hall or velvet.
21	Decay knob	Tail length.
22	Size	Room size.
23	Pre-delay	Gap before the reverb starts.
24	Modulation	Slow movement inside the tail.
25	Velvet colour	Velvet type only: dark to bright.
26	Shimmer pitch	Pitch of the shimmer voice fed back into the tail.
27	Shimmer amount	How much shifted tail is fed back.
28	Pitch 2	Pitch of the second shimmer voice.
29	Amount 2	Amount of the second shimmer voice.
30	Damping	Darkens the tail.
31	Wet HP	High-pass on the reverb tail only.
32	Wet LP	Low-pass on the reverb tail only.
33	Mix	Reverb dry/wet.