

OpenText™ Identity Console

Installation guide

Version : 25.4

PDF Generated on : January 23, 2026

Table of Contents

1. Installation guide	1
1.1. Planning to install OpenText Identity Console	2
1.1.1. System requirements and prerequisites for docker installation	3
1.1.2. System requirements and prerequisites for standalone installation (non-docker)	5
1.1.3. System requirements and prerequisites for workstation	11
1.1.4. RPM signature verification	15
1.2. Installing OpenText Identity Console	16
1.2.1. Installing standalone OpenText Identity Console (non-docker)	17
1.2.2. Installing OpenText Identity Console workstation on Windows	31
1.2.3. Installing OpenText Identity Console as docker container	36
1.2.4. Installing OpenText Identity Console In Azure Kubernetes Services	53
1.3. Upgrading OpenText Identity Console	64
1.3.1. Upgrading OpenText Identity Console on standalone server	65
1.3.2. Upgrading OpenText Identity Console workstation on Windows	66
1.3.3. Upgrading OpenText Identity Console container	68
1.3.4. Upgrading the OSP container	71
1.4. Uninstalling OpenText Identity Console	73
1.4.1. Uninstallation of OpenText Identity Console docker container	74
1.4.2. Uninstallation of standalone OpenText Identity Console (non-docker)	75
1.4.3. Uninstallation of OpenText Identity Console workstation on Windows	76
1.5. Troubleshooting	77
1.5.1. Error: Login failure. Invalid credentials	78
1.5.2. INFO: Latest OpenText Identity Console version is already installed. Exiting	79
1.5.3. ERROR: Installing OpenText Identity Console with older NICI instance	80
1.5.4. ERROR: Failed dependencies	81
1.5.5. ERROR: Server certificate failed message	82

1. Installation guide

The *Guide* provides information on how to install and manage the product. This book defines terminology and includes implementation scenarios.

This guide is intended for network administrators.

1.1. Planning to install OpenText Identity Console



Note

OpenText Identity Console supports the following products and their respective latest versions.

- OpenText eDirectory 9.2.4 HF2
- OpenText Identity Manager Engine 4.8.3 HF2

You must upgrade your instances before using the OpenText Identity Console.

- [System Requirements and Prerequisites for Docker Installation](#)
- [System Requirements and Prerequisites for Standalone Installation \(Non-Docker\)](#)
- [System Requirements and Prerequisites for Workstation](#)
- [RPM Signature Verification](#)

1.1.1. System requirements and prerequisites for docker installation

System requirements

As OpenText Identity Console can be run as a Docker container, for more information about system requirements and supported platforms for installing OpenText Identity Console, see [Docker Documentation](#).

Prerequisites

- Install Docker 20.10.9-ce or later. For more information on how to install Docker, see [Docker Installation](#).
- (Optional) Using the One SSO Provider (OSP), you can enable the single sign-on authentication for your users to the OpenText Identity Console portal. You must install OSP before installing OpenText Identity Console. To configure OSP for OpenText Identity Console, follow the on-screen prompts and provide the required values for configuration parameters. To register OpenText Identity Console to an existing OSP server, you must manually add the following to the `ism-configuration.properties` file in `/opt/netiq/idm/apps/tomcat/conf/` folder:

```
com.netiq.edirapi.clientID = identityconsole
com.netiq.edirapi.redirect.url = https://<Identity Console
Server IP>:<Identity Console Listener
Port>/eDirAPI/v1/<eDirectory Tree Name>/authcoderedirect
com.netiq.edirapi.logout.url = https://<Identity Console
Server IP>:<Identity Console Listener
Port>/eDirAPI/v1/<eDirectory Tree Name>/logoutredirect
com.netiq.edirapi.logout.return-param-name = logoutURL
com.netiq.edirapi.response-types = code,token
com.netiq.edirapi.clientPass._attr_obscurity = AES    # or
system-supported encryption
com.netiq.edirapi.clientPass =
<securely_generated_random_secret>
```



Note

- With OSP, you can connect to only a single OpenText eDirectory tree as OSP does not support multiple OpenText eDirectory trees.
- Third party OSP is not supported in OpenText Identity Console.
- In a NAM integrated environment, OpenText Identity Console with OSP is currently not supported.

- Ensure that you have a proper DNS entry available for your host machine in `/etc/hosts` with a fully qualified host name.
- If you want to use OpenText Identity Console in Edge browser, you must download the latest version of Microsoft Edge for full functionality.



Note

While using OpenText Identity Console in Mozilla Firefox, the operation might fail with `Origin Mismatch` error message. To troubleshoot, perform the following steps:

1. Update Firefox to the latest version.
2. Specify `about:config` in the Firefox URL box and press Enter.
3. Search for Origin.
4. Double-click on `network.http.SendOriginHeader` and change its value to 1.

1.1.2. System requirements and prerequisites for standalone installation (non-docker)

System requirements

This section explains the system requirements and prerequisites to install standalone OpenText Identity Console.

Category	Minimum Requirement
Processor	1.4 GHz 64-bit
Memory	2GB
Disk Space	200 MB on Linux
Supported Browser	• Latest version of Microsoft Edge • Latest version of Google Chrome • Latest version of Mozilla Firefox  Note While using OpenText Identity Console in Mozilla Firefox, the operation might fail with Origin Mismatch error message. To troubleshoot, perform the following steps: 1. Update Firefox to the latest version. 2. Specify about:config in the Firefox URL box and press Enter. 3. Search for Origin. 4. Double-click on network.http.SendOriginHeader and change its value to 1.

Category	Minimum Requirement
Supported Operating System	• Certified: ◦ SUSE Linux Enterprise Server (SLES) 15 SP5, (SLES) 15 SP6 ◦ Red Hat Enterprise Linux (RHEL) 8.7, 8.8, 8.9, 9.2, 9.3, 9.4, 9.5, and 9.6 • Supported: Supported on later versions of support packs of the above certified Operating Systems.


Category	Minimum Requirement
Certificates	• Obtain a <code>pkcs12</code> server certificate with the private key to encrypt/decrypt data exchange between the client and the OpenText Identity Console server. From OpenText Identity Console 1.7.2 onwards users can generate server certificate during the installation process. This server certificate is used to secure the http connection. You can use server certificates generated by any external CA. For more information, see Creating Server Certificate Objects. The server certificate should contain the Subject Alternative Name with IP address and DNS of the OpenText Identity Console server. Once the server certificate object is created, you must export it in .pfx format. • From OpenText Identity Console 1.9 onwards, you can choose to auto fetch the CA certificate as per your requirement. • From OpenText Identity Console 1.7.2 onwards users can import CA Certificate (<code>SSCert.pem</code>) by providing IP address and port information during installation process. For more information, see Generate CA certificate.

Once you are ready, proceed with installing OpenText Identity Console. For more information, see [Installing Standalone OpenText Identity Console \(Non-Docker\)](#).

(Optional) Prerequisite for OSP configuration

Using the One SSO Provider (OSP), you can enable the single sign-on authentication for your users to the OpenText Identity Console portal. You must install OSP before installing OpenText Identity Console. To configure OSP for OpenText Identity Console, follow the on-screen prompts and provide the required values for configuration parameters. To register OpenText Identity Console to an existing OSP server, you must manually add the following to the `ism-configuration.properties` file in `/opt/netiq/idm/apps/tomcat/conf/` folder:

```
com.netiq.edirapi.clientID = identityconsole
com.netiq.edirapi.redirect.url = https://<Identity Console
Server IP>:<Identity Console Listener
Port>/eDirAPI/v1/<eDirectory Tree Name>/authcoderedirect
com.netiq.edirapi.logout.url = https://<Identity Console Server
IP>:<Identity Console Listener Port>/eDirAPI/v1/<eDirectory Tree
Name>/logoutredirect
com.netiq.edirapi.logout.return-param-name = logoutURL
com.netiq.edirapi.response-types = code,token
  com.netiq.edirapi.clientPass._attr_obscurity = AES    # or
system-supported encryption
  com.netiq.edirapi.clientPass =
<securely_generated_random_secret>
```



Note

- If you are installing OSP for the first time, specify the option 'y' for **Configure OSP with eDirAPI** and follow the on-screen prompts to register OpenText Identity Console with OSP.
- Ensure to specify the OpenText eDirectory tree name in lowercase while configuring OpenText Identity Console. In case, the tree name is not specified in lowercase, the login to the OpenText Identity Console server might fail.
- With OSP, you can connect to only a single OpenText eDirectory tree as OSP does not support multiple OpenText eDirectory trees.
- Third party OSP is not supported in OpenText Identity Console.
- In a NAM integrated environment, OpenText Identity Console with OSP is currently not supported.


1.1.3. System requirements and prerequisites for workstation

System requirements

This section explains the system requirements and prerequisites to run workstation OpenText Identity Console (version 1.5 and later).

Category	Minimum Requirement
Processor	1.5 GHz 64-bit
Memory	2GB
Disk Space	1 GB on Windows
Supported Operating System	• Certified: ◦ Windows Server 2019 ◦ Windows Server 2022 ◦ Windows 10 ◦ Windows 11 ◦ Windows 2025

Category	Minimum Requirement
Certificates	• You must obtain a server certificate in pfx format. This server certificate must always be named keys.pfx. For more information, see Creating Server Certificate Objects. • From OpenText Identity Console 1.7.2 onwards users can generate Server Certificate during the installation process. • From OpenText Identity Console 1.9 onwards, by default, the auto fetching of CA certificate is enabled as true. • To manually fetch the CA certificate, you must obtain a CA certificate for all trees in .pem format to validate the CA signature of the server certificates obtained in the previous step. This root CA certificate also ensures establishing a secured ldap communication between the client and the OpenText Identity Console server. • From OpenText Identity Console 1.7.2 onwards users can import CA Certificate (SSCert.pem) by providing IP address and port information during installation process.



Note

If the Windows server has multiple domain or admin accounts, only one administrator can install and access OpenText Identity Console, provided that OpenText eDirectory is also installed on the same machine.

Once you are ready, proceed with installing OpenText Identity Console. For more information, see [Installing OpenText Identity Console Workstation on Windows](#).

1.1.4. RPM signature verification

Use the following steps to perform the RPM Signature Verification:

1. Navigate to the folder where the build is extracted.

For example: `<untarred location of Identity Console>/IdentityConsole_<version>_Linux/license/MicroFocusGPGPackageSignature.pub` .

2. Run the following command to import the Public Key:

```
rpm --import MicroFocusGPGPackageSign.pub
```

3. (Optional) Run the following command to verify the RPM signature: `rpm --checksig -v <RPM Name>`

For Example:

```
rpm --checksig -v identityconsole-1.8.0.0000.x86_64.rpm
```

```
identityconsole-1.8.0.0000.x86_64.rpm:
```

```
Header V4 RSA/SHA256 Signature, OK, key ID 786ec7c0: OK
```

```
Header SHA1 digest: OK
```

```
Header SHA256 digest: OK
```

```
Payload SHA256 digest: OK
```

```
V4 RSA/SHA256 Signature, key ID 786ec7c0: OK
```

```
MD5 digest: OK
```

1.2. Installing OpenText Identity Console

This chapter covers the installation of the OpenText Identity Console and provides security recommendations. Before installing, review the prerequisites and system requirements in [Planning to Install OpenText Identity Console](#).

- [Installing standalone OpenText Identity Console \(non-docker\)](#)
- [Installing OpenText Identity Console workstation on Windows](#)
- [Installing OpenText Identity Console as docker container](#)
- [Installing OpenText Identity Console In Azure Kubernetes Services](#)

1.2.1. Installing standalone OpenText Identity Console (non-docker)

You can install the OpenText Identity Console in one of the following ways:



Note

To ensure proper functionality, we recommend you install OpenText Identity Console and OpenText eDirectory on the same machine, which must have at least one instance of OpenText eDirectory available.

Performing an interactive installation

This section covers how to install standalone OpenText Identity Console using the interactive installation method.

1. Log in to the [Software License and Download](#) portal and navigate to the Software Downloads page.
2. Select the following:
 - Product: OpenText eDirectory
 - Product Name: OpenText eDirectory per User Sub SW E-LTU
 - Version: 25.4
3. Download and extract the latest build for OpenText Identity Console.
4. Navigate to the directory where you extracted the OpenText Identity Console build > `IdentityConsole_<version>_Linux`.
5. Run the following command while logged in as root or root-equivalent user:

```
./identityconsole_install
```

6. Read the Introduction, and then click **ENTER**.
7. Enter `'y'` to accept the License Agreement. This installs all the required RPMs on your system.
8. Enter the Identity Console server's hostname (FQDN)/IP address. For example, `10.10.33.100`

If you press **Enter** without specifying an IP address, your system's IP address/hostname is used by default.

9. Enter the port number for Identity Console to listen. The default value is `9000`.
10. Specify which `eDirectory-hosts` to connect. You can provide either IP address or domain name. For example: `localhost:636,xx.xx.xx.xx:636` or `edir.domain.com:636`
11. Choose one of the following options based on your requirements:
 - If you do not want to integrate OSP with OpenText Identity Console, choose `'n'` and continue with Step 12.
 - If you want to integrate OSP with OpenText Identity Console, choose `'y'` and provide inputs for the following steps:
 1. Enter the eDirectory/Identity Vault server's Domain name/IP address with LDAPS port number.

For example:
`192.168.1.1:636`
 2. Enter the eDirectory/Identity Vault username.

Example:
`cn=admin,ou=org_unit,o=org`
 3. Enter the eDirectory/Identity Vault password.
 4. Enter the eDirectory/Identity Vault password again to confirm the password.
 5. Enter the OSP server domain name/IP address with SSO server SSL port number.
 6. Enter the OSP client ID and OSP client password.
 7. Enter the eDirectory/Identity Vault tree name.

12. Choose one of the following options based on your requirements:
 - If you want to auto fetch the CA certificates, choose auto fetch as `'y'`.
 - If you do not want to auto fetch the CA certificates, choose auto fetch as `'n'`.

13. Choose one of the following options based on your requirements:

- If you want to import the CA certificate from the server, input 'y' and press **Enter**.

CA certificate gets copied successfully in /config/eDirAPI/cert .

To manually fetch or add the CA certificate, refer [Generate CA Certificate](#)

- If you do not want to import the CA certificate from the server, input 'n' and press **Enter**.
- If you enter 'q' ", the installation is terminated.

14. Choose one of the following options to generate a Server Certificate:

- If you want to generate the Server Certificate, input 'y' and press **Enter**. Provide inputs for the following steps:

1. Enter the eDirectory user name. Example: cn=admin,o=novell .

2. Enter the eDirectory user password.

3. Re-enter the eDirectory user password.

4. Enter the server certificate name.

Example: servercert

5. Enter the server certificate password.

Example: password@123

6. Re-enter the server certificate password.

Example: password@123

- If you already have a Server Certificate that you want to use, input 'n' and press **Enter**. Provide inputs for the following steps:

1. Specify the location of your Server Certificate directory path manually.

For example, /home/cert/keys.pfx

2. Enter the server certificate password.

3. Re-enter the server certificate password.



Note

- You can find the following log files in the `/var/opt/novell/eDirAPI/log` directory:
 - `edirapi.log` - This file logs edirapi events and debugging issues.
 - `edirapi_audit.log` - This file logs edirapi audit events. The logs follow a CEF auditing format.
 - `identityconsole_install.log` - This file logs OpenText Identity Console events.
- You can check the logs for OpenText Identity Console start and stop operations in the `/var/log/messages` file.
- If installation fails, use the following command to reconfigure:

```
/usr/bin/identityconsoleConfigure
```

Utilities to generate certificates

You have the option to obtain CA Certificates and Server Certificates for other trees using the following tools or utilities.



Note

The scripts for CA and Server certificate are available in `/opt/novell/eDirAPI/sbin` path.

Generate CA certificate

1. Download and extract the latest OpenText Identity Console build.
2. Navigate to the directory `/opt/novell/eDirAPI/sbin` to fetch, delete, or view the list of CA certificates.
3. Run the following command while logged in as root or root-equivalent user.

```
./get_cacert fetch <ip address/DNS:ldaps port>
```

For example:

```
./get_cacert fetch 10.10.10.10:636
```

4. To manually add the CA certificate in `cert` folder, navigate to `/etc/opt/novell/eDirAPI/cert` copy and paste the CA certificate.

```
<IP address/DNS_ldaps port.pem>
```

For example:

```
10.10.10.10_636.pem
```

Generate server certificate

1. Download and extract the latest OpenText Identity Console build.
2. Navigate to the directory to fetch, delete or view the list of CA certificates > `/opt/novell/eDirAPI/sbin`
3. Run the following command while logged in as root or root-equivalent user.

```
./get_servercert <eDirectory IP address with LDAPS port number> <eDirectory/Identity Vault username> <userpassword> <server certificate name> <server certificate password>
```

Example:

```
./get_servercert 10.10.10.10:636 cn=admin,ou=org_unit,o=org password keys password
```

Performing a silent installation

Silent installation enables you to install OpenText Identity Console without any interactive input. To use this method, you must define your options for installing OpenText Identity Console in the `silent.properties` file and then run the installation process from the command line. After you modify the properties file, the system uses the information from it to complete the installation silently.

Before starting the silent installation, ensure that you meet all the [prerequisites](#).

Silent Properties File

Parameter	Description
Installation Configuration	
AUTO_FETCH="Yes"	Enables auto-fetching of certificates from specified eDirectory server during login. • Yes - Automatically fetching the certificates. • No - Log in with the given eDirectory IP/FQDN. For multi-tree login, manually copy the certificates.
AUTOGENERATE_CACERT="Yes"	Indicates whether you want to import the CA certificate from the eDirectory server during installation. • Yes - Allow you to fetch CA certificate automatically. • No - Enter the path of CA certificate, <customlocation/SSCert.pem>. For example: /home/SSCert.pem.
CACERT_LOCATION=""	Mention the CA certificate path including the filename. Applicable only when AUTOGENERATE_CACERT= 'No'.

AUTOGENERATE_SERVERCERT="Yes"	Indicates whether you want to generate or import server certificate from the server during installation. • Yes - Allow you to generate server certificate automatically. • No - Enter the path of server certificate <customlocation/keys.pfx>. For example: /home/keys.pfx
SERVERCERT_LOCATION=""	Mention the Server certificate path including the filename. Applicable when AUTOGENERATE_SERVERCERT= 'No'.
EDIR_HOST="10.10.10.10:636"	Enter the eDirectory Server hostname or IP address(<IP/FQDN>:<PORT>). It is mandatory during installation. Example: 10.XX.XX.XX:636 or idm.edir.opentext.com:636 (FQDN:636).
IDC_IP="10.10.10.10"	Enter the the Identity Console server hostname or IP address. It is mandatory during installation. Example: 10.XX.XX.XX or idm.edir.opentext.com (FQDN).
IDC_PORT="9000"	Port number you want the Identity Console to listen. It is mandatory during installation. Example: 9000
SERVERCERT_NAME="cert"	Enter the Server certificate name if you choose to auto generate the certificate.
SERVERCERT_PASSWD="samplevalue"	Enter the Server certificate password.

SERVERCERT_USERNAME="cn=admin,ou=sa,o=system"	Enter the eDirectory or Identity Vault username to which Identity Console will connect during installation. It is mandatory during installation. Example: cn=admin,ou=sa,o=system
SERVERCERT_USER_PASSWD="sample value"	Enter the eDirectory or Identity Vault user password.
Installation configuration with OSP	
EDIR_TREENAME="my_tree"	Enter the eDirectory or Identity Vault tree name. Example: my_tree
OSP_CLIENT_ID="identityconsole"	Enter the OSP client ID.
OSP_CLIENT_PASSWD="samplevalue"	Enter the OSP client password.
OSP_IP=""	Enter the OSP server domain name or IP address with port number.
OSP_MODE="No"	Enter whether you want to integrate OSP with Identity Console.
VAULT_IP=""	Enter the eDirectory or Identity Vault server domain name or IP address with port number. Example: 10.10.XX.XX:636
VAULT_PASSWD="samplevalue"	Enter the eDirectory or Identity Vault user password.
VAULT_USERNAME="cn=admin,o=org"	Enter the eDirectory or Identity Vault username.

To edit the silent properties file:

1. Navigate to the IdentityConsole_<version>_Linux directory in the location where you have extracted the OpenText Identity Console build.

2. Open the silent.properties file and modify the values as per your requirement:

- If auto generation of certificates is set to **Yes**,

1. Enter the following details in the silent.properties file:

```
# Installation configuration

AUTO_FETCH="Yes"
AUTOGENERATE_CACERT="Yes"
CACERT_LOCATION=""
    AUTOGENERATE_SERVERCERT="Yes"

SERVERCERT_LOCATION=""
    EDIR_HOST="10.10.10.10:636"

    IDC_IP="10.10.10.10"

    IDC_PORT="9000"

    SERVERCERT_NAME="cert"

    SERVERCERT_PASSWD="samplevalue"

SERVERCERT_USERNAME="cn=admin,o=org"

SERVERCERT_USER_PASSWD="samplevalue"

# OSP mode configuration

    EDIR_TREENAME="my_tree"
    OSP_CLIENT_ID="identityconsole"
    OSP_CLIENT_PASSWD="samplevalue"

    OSP_IP=""
    OSP_MODE="No"
    VAULT_IP=""
    VAULT_PASSWD="samplevalue"

    VAULT_USERNAME="cn=admin,o=org"
```

- If auto generation of certificates is set to **No**,

1. Enter the following details in silent.properties file:

```
# Installation configuration

    AUTO_FETCH="No"
    AUTOGENERATE_CACERT="No"
    CACERT_LOCATION="/home/SSCert.pem"

    AUTOGENERATE_SERVERCERT="No"
    SERVERCERT_LOCATION="/home/keys.pfx"
    EDIR_HOST="10.10.10.10:636"

    IDC_IP="10.10.10.10"

    IDC_PORT="9000"

    SERVERCERT_NAME="cert"

    SERVERCERT_PASSWD="samplevalue"

SERVERCERT_USERNAME="cn=admin,o=org"

SERVERCERT_USER_PASSWD="samplevalue"

# OSP mode configuration

    EDIR_TREENAME="my_tree"
    OSP_CLIENT_ID="identityconsole"
    OSP_CLIENT_PASSWD="samplevalue"

    OSP_IP=""
    OSP_MODE="No"
    VAULT_IP=""
    VAULT_PASSWD="samplevalue"

    VAULT_USERNAME="cn=admin,o=org"
```

3. Run the following command to run the installer in silent mode:

```
./identityconsole_install -s silent.properties
```

You can find installation-related logs in the `Identity Console installation > identityconsole_install.log` file.

Multi-tree with standalone OpenText Identity Console

To connect OpenText Identity Console with multiple OpenText eDirectory trees when the auto-fetch is disabled, you must copy the CA certificates from all the OpenText eDirectory trees to the `/etc/opt/novell/eDirAPI/cert/` directory.

Copy the CA certificates as follows:

```
cp /home/user/<ip address1_ldap port.pem>
/etc/opt/novell/eDirAPI/cert/<ip address1_ldap port.pem>
```

```
cp /home/user/<ip address2_ldap port.pem>
/etc/opt/novell/eDirAPI/cert/<ip address2_ldap port.pem>
```

To fetch CA certificate using the `get_cacert` utility, refer the section [Generate CA Certificate](#).

Run one of the following command to restart OpenText Identity Console:

```
/usr/bin/identityconsole restart
```

or

```
systemctl restart netiq-identityconsole.service
```

When the auto-fetch is enabled, the CA certificates are automatically copied to the `cert` folder.

Replacing the server certificate in standalone OpenText Identity Console

Perform the following steps to replace server certificate in Standalone OpenText Identity Console:

1. Run decryptor to store the keys:

```
su - nds -c "/opt/novell/eDirAPI/sbin/decryptor
/Expiredcert/noexpire/new-keys.pfx novell
/etc/opt/novell/eDirAPI/conf/ssl/private/cert.pem"
```

2. Restart the OpenText Identity Console:

```
systemctl restart netiq-identityconsole.service
```

Stopping, restarting, and status of standalone OpenText Identity Console

- To stop, run one of the following command:

```
/usr/bin/identityconsole stop
```

or

```
systemctl stop netiq-identityconsole.service
```

- To restart, run one of the following command:

```
/usr/bin/identityconsole restart
```

or

```
systemctl restart netiq-identityconsole.service
```

- To check the status, run one of the following command:

```
/usr/bin/identityconsole status
```

or

```
systemctl status netiq-identityconsole.service
```

- To start, run one of the following command:

```
/usr/bin/identityconsole start
```

or

```
systemctl start netiq-identityconsole.service
```

1.2.2. Installing OpenText Identity Console workstation on Windows

OpenText Identity Console can be launched on Windows as workstation, and requires the REST services running. Therefore, when it is launched, an eDirAPI process runs in the `edirapi.exe` cmd prompt. If you close `edirapi.exe` terminal, OpenText Identity Console will no longer function.

The following procedure describes how to run OpenText Identity Console on Windows.

1. Log in to the [Software License and Download](#) portal and navigate to the Software Downloads page.
2. Select the following:
 - Product: OpenText eDirectory
 - Product Name: OpenText eDirectory per User Sub SW E-LTU
 - Version: 25.4
3. Download and extract the `IdentityConsole_<version>_workstation_win_x86_64.zip`.
4. Navigate to the extracted folder and install `NICL_wx64`.
5. (Optional) Open the `edirapi_win.conf` file and edit the port number for OpenText Identity Console to listen.
6. If you already have the `keys.pfx` and `SSCert.pem` files that you want to use, change the CA certificate filename to `<ipaddress_ldap>.pem(xx.xx.xx.xxx_636.pem)`, and then copy the files manually into `cert` folder located in `C:\IdentityConsole_<version>_workstation_win_x86_64\edirAPI\cert`.

Then proceed to step 9.

7. If you want to generate the CA certificate, navigate to the `eDirAPI` folder, run the `get_cacert.exe fetch <IP address_port.pem>` binary in command prompt, located in `C:\IdentityConsole_version_workstation_win_x86_64\edirAPI\`, and provide the OpenText eDirectory/Identity Vault server Domain name/IP address with LDAPS port number.

For example,

```
get_cacert.exe fetch 10.10.10.125:636
```

10.10.10.125_636.pem file is generated.

8. If you want to generate the Server Certificate, run `get_servercert.exe help` binary through command prompt along with the following details:
 - eDirectory/Identity Vault server Domain name/IP address with LDAPS port number.
 - eDirectory/Identity Vault user name.
 - eDirectory/Identity Vault password.
 - Server certificate name.
 - Server certificate password.

For example,

```
get_servercert.exe 10.10.10.125:636 cn=admin,o=novell  
password keys password
```

A `keys.pfx` file is generated.

9. Navigate to the extracted folder, double-click the `configure.bat` file and enter the server certificate (`keys.pfx`) password in the command prompt.

If the server certificate is changed, then re-run the `configure.bat` file with the password of the new certificate.

10. Navigate to the extracted folder and double-click the `run.bat` file.

The eDirAPI process terminal (`edirapi.exe`) starts running, and the OpenText Identity Console login page appears.




Note

- For subsequent logins to the OpenText Identity Console application, double click the `run.bat` . The login page will appear. If the `eDirAPI` process terminal (`edirapi.exe`) is already running, then run `identityconsole.exe` from the build extracted folder.
- Users can find the following logs in:
`\IdentityConsole_<version>_workstation_win_x86_64\eDirAPI\log`
`edirapi.log` - This is used for logging different events in `edirapi` and debugging issues.
`edirapi_audit.log` - This is used for logging audit events of `edirapi` . The logs follow CEF auditing format.
- OSP based logins are not supported in workstation mode.
- If the port number is already in use, edit the **listen** parameter in the `edirapi_win.conf` file with a new port number and double-click the `run.bat` to successfully log in to the OpenText Identity Console.

Utilities to generate certificates

You have the option to obtain CA Certificates and Server Certificates for other OpenText eDirectory Trees using the following utilities.



Note

The scripts for CA and Server certificate are available in `/opt/novell/eDirAPI/sbin` path.

Generate CA certificate

1. Download and extract the latest OpenText Identity Console build.
2. Navigate to the directory where you extracted the OpenText Identity Console build. Example: `C:\IdentityConsole_<version>_workstation_win_x86_64\eDirAPI`
3. Run the following binary through command prompt.

```
get_cacert.exe fetch <ip address:port>
```

Provide the OpenText eDirectory IP address and LDAPS port number.

Example: `get_cacert.exe fetch 10.10.10.125:636`

`10.10.10.125_636.pem` file is generated and copied to `cert` folder.

Generate server certificate

1. Navigate to the folder where you have extracted the OpenText Identity Console build.

Example: `IdentityConsole_<version>_win`

2. Run `get_servercert.exe help` for more help options through command prompt.
 - eDirectory/Identity Vault server Domain name/IP address with LDAPS port number.
 - eDirectory/Identity Vault user name.
 - eDirectory/Identity Vault password.
 - Server certificate name.
 - Server certificate password.

To generate the Server Certificate, run the following command through command prompt:

Example:

`get_servercert.exe 10.10.10.125:636 cn=admin,o=novell password keys password`

`keys.pfx` file is generated and copied to `cert` folder.

Multi-tree with OpenText Identity Console as workstation

OpenText Identity Console allows user to connect to multiple trees by entering the IP address at the login page.

Closing and re-launching OpenText Identity Console workstation

To close the application and the process:

1. Close the OpenText Identity Console desktop windows application.
2. Stop the eDirAPI process by closing the `eDirAPI` process terminal.

To relaunch OpenText Identity Console Workstation, navigate to the folder where the build is extracted and double click the `run.bat` file (Windows batch file).



Note

If the eDirAPI process terminal is already running, then run `identityconsole.exe` from the build extracted folder to relaunch OpenText Identity Console Workstation.

1.2.3. Installing OpenText Identity Console as docker container

This section includes the following procedures:

Security recommendations

- Docker containers do not have any resource constraints by default. This provides every container with the access to all the CPU and memory resources provided by the host's kernel. You must also ensure that one running container should not consume more resources and starve other running containers by setting limits to the amount of resources that can be used by a container.
 - Docker container should ensure that a Hard Limit is applied for the memory used by the container using the `--memory` flag on Docker run command.
 - Docker container should ensure that a limit is applied to the amount of CPU used by a running container using the `--cpuset-cpus` flag on the Docker run command.
- `--pids-limit` should be set to 300 to restrict the number of kernel threads spawned inside the container at any given time. This is to prevent DoS attacks.
- You must set the on-failure container restart policy to 5 using the `--restart` flag on Docker run command.
- You must only use the container once the health status shows as **Healthy** after the container comes up. To check the container's health status, run the following command:

```
docker ps <container_name/ID>
```

- Docker container will always start as non-root user (`nds`). As an additional security measure, enable user namespace remapping on the daemon to prevent privilege-escalation attacks from within the container. For more information on user namespace remapping, see [Isolate containers with a user namespace](#).



Note

The VIM editor is no longer installed in the container. If necessary, perform the following steps to install it:

1. Login to the container as root-user and run `docker exec -it -u root <containername> /bin/bash` command.
2. If yum is not available, run `microdnf install yum` to install yum.
3. Run `dnf install -y vim` or `yum install -y vim` command to install the vim editor.

Installing OpenText Identity Console As a docker container



Note

- OpenText Identity Console can be configured with or without OSP. If you choose to configure it with OSP, you must first [deploy the OSP container](#), followed by the OpenText Identity Console container. Make sure to modify the `silent.properties` file to include your desired values for deployment.
- If you want direct access to network host on Linux platform , use the `--network` flag.

To install OpenText Identity Console as a Docker container:

The configuration parameters, sample values and examples mentioned in this procedure are for reference purposes only. You must ensure not to use them directly in your production environment.

1. Log in to the [Software License and Download](#) portal and navigate to the Software Downloads page.
2. Select the following:
 - Product: OpenText eDirectory
 - Product Name: OpenText eDirectory per User Sub SW E-LTU
 - Version: 25.4
3. Download the `IdentityConsole_<version>_Container.tar.zip` .

1. The image has to be loaded into the local Docker registry. Extract the `IdentityConsole_<version>_Containers.tar.gz` file using the below command:

```
tar -xvf IdentityConsole_<version>_Containers.tar.gz
```

2. Navigate to the `identityconsole` folder and run the following command to load them:

```
docker load --input identityconsole.tar.gz
```

4. Open the `silent.properties` file and modify the values as per your requirement:

Silent Properties File

Parameter	Description
Installation Configuration	
AUTO_FETCH="Yes"	Enables auto-fetching of certificates from specified eDirectory server during login. ◦ Yes - Automatically fetching the certificates. ◦ No - Logins with the given eDirectory IP/FQDN. For multi-tree login, manually copy the certificates.
AUTOGENERATE_CACERT="Yes"	Indicates whether you want to import the CA certificate from the eDirectory server during installation. ◦ Yes - Allow you to fetch CA certificate automatically ◦ No - The path of the CA certificate is /config/eDirAPI/etc/cert/SSCert.pem
CACERT_LOCATION=""	Mention the CA certificate path including the filename. Applicable only when AUTOGENERATE_CACERT= No

AUTOGENERATE_SERVERCERT="Yes"	Indicates whether you want to generate or import server certificate from the server during installation. ◦ Yes - Allow you to generate server certificate automatically ◦ No - The path of the server certificate is /config/eDirAPI/etc/cert/keys.pfx
SERVERCERT_LOCATION=""	Mention the Server certificate path including the filename. Applicable when AUTOGENERATE_SERVERCERT= No.
EDIR_HOST="10.10.10.10:636"	Enter the eDirectory Server hostname or IP address(<IP/FQDN>: <PORT>). It is mandatory during installation. Example: 10.XX.XX.XX:636 or idm.edir.opentext.com:636 (FQDN:636)
IDC_IP="10.10.10.10"	Enter the the Identity Console server hostname or IP address. It is mandatory during installation. Example: 10.XX.XX.XX or idm.edir.opentext.com (FQDN)
IDC_PORT="9000"	Port number you want the Identity Console to listen. It is mandatory during installation. Example: 9000

SERVERCERT_NAME="cert"	Enter the Server certificate name if you choose to auto generate the certificate.
SERVERCERT_PASSWD="samplevalue"	Enter the Server certificate password.
SERVERCERT_USERNAME="cn=admin,ou=sa,o=system"	Enter the eDirectory or Identity Vault username to which Identity Console will connect during installation. It is mandatory during installation. Example: cn=admin,ou=sa,o=system
SERVERCERT_USER_PASSWD="samplevalue"	Enter the eDirectory or Identity Vault user password.
Installation configuration with OSP	
EDIR_TREENAME="my_tree"	Enter the eDirectory or Identity Vault tree name. Example: my_tree
OSP_CLIENT_ID="identityconsole"	Enter the OSP client ID.
OSP_CLIENT_PASSWD="samplevalue"	Enter the OSP client password.
OSP_IP=""	Enter the OSP server domain name or IP address with port number.

OSP_MODE="No"	Enter whether you want to integrate OSP with Identity Console.
VAULT_IP=""	Enter the eDirectory or Identity Vault server domain name or IP address with port number. Example: 10.10.XX.XX:636
VAULT_PASSWD="samplevalue"	Enter the eDirectory or Identity Vault user password.
VAULT_USERNAME="cn=admin,o=org"	Enter the eDirectory or Identity Vault username.

1. If auto generation of certificates is set to **Yes**,

1. Enter the following details on the silent.properties file:

```
# Installation configuration

    AUTO_FETCH="Yes"
    AUTOGENERATE_CACERT="Yes"
    CACERT_LOCATION=""

    AUTOGENERATE_SERVERCERT="Yes"
    SERVERCERT_LOCATION=""
    EDIR_HOST="10.10.10.10:636"

    IDC_IP="10.10.10.10"

    IDC_PORT="9000"

    SERVERCERT_NAME="cert"

    SERVERCERT_PASSWD="samplevalue"

SERVERCERT_USERNAME="cn=admin,o=org"

SERVERCERT_USER_PASSWD="samplevalue"

# OSP mode configuration

    EDIR_TREENAME="my_tree"
    OSP_CLIENT_ID="identityconsole"
    OSP_CLIENT_PASSWD="samplevalue"

    OSP_IP="10.10.10.10:8543"

    OSP_MODE="No"
    VAULT_IP="10.10.10.10:636"

    VAULT_PASSWD="samplevalue"

    VAULT_USERNAME="cn=admin,o=org"
```

2. Run the following command to install identity console container:

- To customize the FQDN configuration inside the host file (`/etc/host`) of the container, use the `--add-host` flag.

```
docker run -v
./silent.properties:/netiq/identityconsole/silent.properties --name identityconsole_container --volume
identityconsole-volume:/config --add-
host=FQDN:IDC_IP --add-host=FQDN:eDir_IP -p
9000:9000 -d identityconsole:<version>
```

- To configure the container and the host to share the same network, use `--network=host` flag:

```
docker run -v
./silent.properties:/netiq/identityconsole/silent.properties --name identityconsole_container --volume
IDConsole-volume:/config --network=host -d
identityconsole:<version>
```

2. If auto generation of certificates is set to **No**,

1. Manually move the certificates to `identityconsole` folder.
2. Run the following command to manually copy the certificates and install the container:
 - To customize the FQDN configuration inside the host file (`/etc/host`) of the container, use the `--add-host` flag.

```
docker run -v
./keys.pfx:/config/eDirAPI/etc/cert/keys.pfx -v
./SSCert.pem:/config/eDirAPI/etc/cert/SSCert.pem -
v
./silent.properties:/netiq/identityconsole/silent.prop
erties --name identityconsole_container --volume
IDConsole-volume:/config --add-host=FQDN:IDC_IP
--add-host=FQDN:eDir_IP -p 9000:9000 -d
identityconsole:<version>
```

- To configure the container and the host to share the same network, use `--network=host` flag:

```
docker run -v
./keys.pfx:/config/eDirAPI/etc/cert/keys.pfx -v
./SSCert.pem:/config/eDirAPI/etc/cert/SSCert.pem -
v
./silent.properties:/netiq/identityconsole/silent.prop
erties --name identityconsole_container --volume
IDConsole-volume:/config --network=host -d
identityconsole:<version>
```

Multi-tree with OpenText Identity Console as docker

To connect OpenText Identity Console with multiple OpenText eDirectory trees when the auto-fetch is disabled, you must either volume mount it or copy the CA certificates from all the OpenText eDirectory trees to the container's volume cert folder `/config/eDirAPI/cert/`.

For example, if you connect to two OpenText eDirectory trees, then you must either volume mount it into the container's cert folder and restart it:

```
docker run -v ./SSCert1.pem:/config/eDirAPI/etc/cert/SScert1.pem -v
./SSCert2.pem:/config/eDirAPI/cert/SScert2.pem -v
./silent.properties:/netiq/identityconsole/silent.properties --volume IDConsole-
volume:/config -p 9000:9000 -d identityconsole:<version>
```

Run the following commands to restart OpenText Identity Console:

```
docker restart <identityconsole-container-name>
```

Example:

```
docker restart identityconsole-container-1
```

Deploying the OSP container

Perform the following steps to deploy the OSP container:

1. Log in to [Software License and Download](#) portal and navigate to the Software Downloads page.
2. Select the following:
 - Product: OpenText eDirectory
 - Product Name: OpenText eDirectory per User Sub SW E-LTU
 - Version: 9.2
 - OpenText Identity Console Standalone
3. Download and extract the `IdentityConsole_<version>_Containers.tar.zip` file.
4. To install OpenText Identity Console in the OSP container, a keystore (`tomcat.ks`) is required.

Perform the following steps to generate the keystore:

1. Create a folder `certs` in the `/opt/` directory.
2. Run the following command to create a keystore (`tomcat.ks`):

```
keytool -genkey -alias osp -keyalg RSA -storetype
pkcs12 -keystore /opt/certs/tomcat.ks -validity 3650 -
keysize 2048 -dname "CN=blr-osp48-
demo.labs.blr.novell.com" -keypass password -storepass
password
```



Note

Ensure that the IP address of the machine is named as CN name or as fully qualified hostname. For example: CN=xx.xx.xx.xx

3. Run the following command to create a certificate signing request. For example: `cert.csr`.

```
keytool -certreq -v -alias osp -file
/opt/certs/cert.csr -keypass password -keystore
/opt/certs/tomcat.ks -storepass password
```

4. Pass the created `cert.csr` to Identity Console and get the `cert.der` as explained:

1. Launch OpenText Identity Console as Administrator.
2. Click **Certificate Management > Issue Certificate** and select the file.
3. Go to **Key Usage Specifications > Key Type** and select the **Custom** radio button.
4. Click **Key Usage** and select the following check boxes:

- **Data Encipherment**
- **Key Encipherment**
- **Digital Signature**

5. Click **Certificate Parameters > Subject Alternative Names** 
 - > OSP Server IP address or OSP Server DNS Name
 - > **Next** > **OK**.

The message appears as **Certificate has been generated successfully**.

6. Click **OK**.
7. Download the issued certificate `cert.der` and copy it to `/opt/certs/`.

5. Copy the `SSCert.der` from OpenText eDirectory to `/opt/certs`

6. Run the following commands to import the CA certificate (`SSCert.der`) and server certificate (`cert.der`) into the `tomcat.ks` keystore.

```
keytool -import -trustcacerts -alias root -keystore
/opt/certs/tomcat.ks -file /opt/certs/SSCert.der -
storepass password -noprompt
```

```
keytool -import -alias osp -keystore
/opt/certs/tomcat.ks -file /opt/certs/cert.der -
storepass password -noprompt
```

5. Create a new folder as `/data` .
6. Copy the `tomcat.ks` from `/opt/certs` and paste it to the `data` folder.
7. From the extracted OpenText Identity Console container build, copy the `osp-edirapi-silent.properties` files in to the `data` folder.
8. Modify the `osp edirapi silent` properties file as per your requirement. A sample silent properties file has been shown below:

```
# Silent file for osp with edirapi
## Static contents Do not edit - starts
INSTALL_OSP=true
DOCKER_CONTAINER=y
EDIRAPI_PROMPT_NEEDED=y
UA_PROMPT_NEEDED=n
SSPR_PROMPT_NEEDED=n
RPT_PROMPT_NEEDED=n
CUSTOM_OSP_CERTIFICATE=y
## Static contents Do not edit - ends# OSP Details
SSO_SERVER_HOST=osp.example.com (osp configured server IP
address)
SSO_SERVER_SSL_PORT=8543
OSP_COMM_TOMCAT_KEYSTORE_FILE=/config/tomcat.ks
OSP_COMM_TOMCAT_KEYSTORE_PWD=samplevalue
SSO_SERVICE_PWD=samplevalue
OSP_KEYSTORE_PWD=samplevalue
IDM_KEYSTORE_PWD=samplevalue
OSP_CUSTOM_NAME="Identity Console"
USER_CONTAINER="o=novell"
ADMIN_CONTAINER="o=novell"
MASTER_KEYSTORE_PWD=samplevalue
# IDConsole Details
IDCONSOLE_HOST=192.168.1.1 (IdentityConsole configured
server IP address)
IDCONSOLE_PORT=9000
EDIRAPI_TREENAME=ed913 (Tree name should be in lowercase)#If
ENABLE_CUSTOM_CONTAINER_CREATION is set to y
#ie., when you have user and admin container different from
o=data
# and they need to be created in eDir
#then CUSTOM_CONTAINER_LDIF_PATH should be entered as well
ENABLE_CUSTOM_CONTAINER_CREATION=n
#ENABLE_CUSTOM_CONTAINER_CREATION=y
#CUSTOM_CONTAINER_LDIF_PATH=/config/custom-osp.ldif# eDir
Details
ID_VAULT_HOST=192.168.1.1 (eDir/ID_Vault configured server
IP address)
ID_VAULT_LDAPS_PORT=636
```

```
ID_VAULT_ADMIN_LDAP="cn=admin,o=novell"
ID_VAULT_PASSWORD=samplevalue
```



Note

To avoid space constraints while using the silent properties (DOS text) file, you must convert the DOS text file to UNIX format using the `dos2unix` tool. Run the below command to convert text file from DOS line endings to Unix line endings:

```
dos2unix filename
```

For example:

```
dos2unix samplefile
```

9. Run the following command to load the OSP image:

```
docker load --input osp.tar.gz
```

10. Deploy the container using the following command:

```
docker run -d --name OSP_Container --network=host -e
SILENT_INSTALL_FILE=/config/osp-edirapi-silent.properties -v
/data:/config osp:<version>
```

For example:

```
docker run -d --name OSP_Container --network=host -e
SILENT_INSTALL_FILE=/config/osp-edirapi-silent.properties -v
/data:/config osp:<version>
```



Note

After deploying OSP container, install and configure OpenText Identity Console with OSP server details.

Stopping and restarting OpenText Identity Console As docker container

To stop, run the following command:

```
docker stop identityconsole-container-name
```

To restart, run the following command:

```
docker restart identityconsole-container-name
```

To start, run the following command:

```
docker start identityconsole-container-name
```

Replacing the Server Certificate in Docker Container

Perform the following steps to replace the server certificate in Docker Container:

1. Run the following command to copy the new server certificate in any location of your container.

Example:

```
docker cp /path/to/new-keys.pfx
<container_id/name>:/tmp/new-keys.pfx
```

2. Login to the container by using the following command:

```
docker exec -it container_name bash
```

3. Run the decryptor to store the keys as a pseudo-user:

```
LD_LIBRARY_PATH=/opt/novell/eDirAPI/sbin/decryptor
/Expiredcert/noexpire/new-keys.pfx novell
/etc/opt/novell/eDirAPI/conf/ssl/private/cert.pem
```

4. Exit the container console using the command:

```
exit
```

5. Restart the container by entering:

```
docker restart container name
```

1.2.4. Installing OpenText Identity Console In Azure Kubernetes Services

Azure Kubernetes Service (AKS) is a managed Kubernetes service that enables you to install and manage clusters. This section includes the following procedures:

Installing OpenText Identity Console in AKS cluster

This section explains the following procedures to install OpenText Identity Console in AKS Cluster:

Creating an Azure container registry (ACR)

Azure Container Registry (ACR) is an Azure-based, private registry, for Docker container images.

For more detail steps see [Create an Azure container registry using the Azure portal](#) section in the Create container registry - Portal or perform the following steps to create an Azure Container Registry (ACR):

1. Sign in to [Azure Portal](#).
2. Go to **Create a resource > Containers > Container Registry**.
3. In the **Basics** tab, specify values for **Resource group** and **Registry name**. The registry name must be unique within Azure and contain minimum of 5 and maximum of 50 alphanumeric characters.

Accept default values for the remaining settings.
4. Click **Review + create**.
5. Click **Create**.
6. Sign in to Azure CLI, run the following command to log in to Azure Container Registry.

```
az acr login --name registryname
```

Example:

```
az acr login --name < idconsole >
```

- Retrieve the login server of the Azure Container Registry using the command:

```
az acr show --name registryname --query loginServer --output table
```

Example:

```
az acr show --name < idconsole > --query loginServer --output table
```

- Tag the local image of OpenText Identity Console with the name of the ACR login server (registryname.azureacr.io) using the following command:

```
docker tag idconsole-image <login server>/idconsole-image
```

Example:

```
docker tag identityconsole:<version> registryname.azurecr.io/identityconsole:<version>
```

- Push the tagged image to the registry.

```
docker push <login server>/idconsole: <version>
```

Example:

```
docker push registryname.azurecr.io/identityconsole:<version>
```

- Retrieve the list of images in the registry using the command:

```
az acr show --name registryname --query loginServer --output table
```

Setting a Kubernetes cluster

Create a kubernetes service resource using Azure portal or CLI.

For more detail steps to create a Kubernetes service resource in azure with a node, see [Create an AKS Cluster](#) in the [Azure Quickstart](#).



Note

- Ensure to select Azure CNI as network.
- Select the existing virtual network (where the OpenText eDirectory server is installed in the subnet).
- Select the existing container registry where OpenText Identity Console image is available.

Creating a standard SKU public IP address

A Public IP address resource under Kubernetes cluster resource group acts as load Balancer IP for the application.

For detail steps, see the [Create a public IP address using the Azure portal](#) in the Create public IP address – Portal.

Setting up cloud shell and connecting to Kubernetes cluster

Use cloud Shell which is available in azure portal for all operations.

To setup cloud shell in Azure portal see [Start Cloud Shell](#) section in [Bash – Quickstart](#) or perform the following steps to set Up Cloud Shell and connect to Kubernetes Cluster:

1. In the Azure portal, click the button to Open Cloud Shell.



Note

To manage a Kubernetes cluster, use the Kubernetes command-line client, kubectl. kubectl is already installed if you use Azure Cloud Shell.

2. Configure kubectl to connect to your Kubernetes cluster using the following command:

```
az aks get-credentials --resource-group "resource group name" --name "Kubernetes cluster name"
```

Example:

```
az aks get-credentials --resource-group myResourceGroup --
name myAKSCluster
```

3. Verify the list of the cluster nodes using the command:

```
kubectl get nodes
```

Deploying the application

To install OpenText Identity Console, you can use `idc-services.yaml` , `idc-statefulset.yaml` , `idc-storageclass.yaml` and `idc-pvc.yaml` sample files.

You can also create your own yaml files as per the requirement.

1. Create a storage class resource using below command:

```
kubectl apply -f <location of the YAML file>
```

Example:

```
kubectl apply -f idc-storageclass.yaml
```

(Optional) For more information on how to dynamically create and use persistence volume with azure files share, see [Dynamically create and use a persistent volume with Azure Files in Azure Kubernetes Service \(AKS\)](#)

A sample storage class resource file has been shown below:

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: azurefilesc
provisioner: kubernetes.io/azure-file
mountOptions:
  - dir_mode=0777
  - file_mode=0777
  - uid=0
  - gid=0
  - mfsymlinks
  - cache=strict
  - actimeo=30
parameters:
  skuName: Standard_LRS
  shareName: fileshare
~
```

A storage class resource enables dynamic storage provisioning. It is used to define how an Azure file share is created.

2. View the details of storageclass using below command:

```
kubectl get sc
```

3. Create a pvc resource using `idc-pvc.yaml` file:

```
kubectl apply -f <location of the YAML file>
```

Example:

```
kubectl apply -f idc.pvc.yaml
```

A sample pvc resource file has been shown below:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvcforsec
spec:
  accessModes:
    - ReadWriteMany
  storageClassName: azurefilesec
resources:
  requests:
    storage: 5Gi
```

A persistence volume claim resource creates the file share. A persistent volume claim (PVC) uses the storage class object to dynamically provision an Azure file share.

4. Upload the edirapi.conf, CA cert, and the server certificate to the cloud shell.

Click the **Upload/Download files** button on cloud shell and upload `edirapi.conf`, `SSCert.pem` and `keys.pfx` files.



Note

`edirapi.conf` has a parameter "origin". Here we need to provide IP address with which we will access OpenText Identity Console application. (use the IP address which is created in the [Creating a standard SKU public IP address](#) section.)

OpenText Identity Console installation requires server certificate(`keys.pfx`).

While creating server certificate make sure to provide valid DNS name in subject Alternative Name.

Steps to build a valid DNS name:

A typical pod deployed using StatefulSet has DNS name like below -
{statefulsetname}-{ordinal}.{servicename}.

{namespace}.svc.cluster.local

- If StatefulSet name in `idconsole-statefulset.yaml` file is `idconsole-app` then `statefulsetname` = `idconsole-app`
- If it is 1st pod, then `ordinal` = 0
- If you define `serviceName` in `idconsole -statefulset.yaml` file as `idconsole` then `serviceName` = `idconsole`
- If it is by default namespace, then `namespace`=`default`

Output: `idconsole-app-0.idcosole.default.svc.cluster.local`

5. Create a configmap resource in Kubernetes cluster which stores the configuration files along with the certificates.

Before running the command make sure that files

(`edirapi.conf` , `SSCert.pem` and `keys.pfx`) are present in the directory.

```
kubectl create configmap <configmapName> --from-file= "path
where the files are present"
```

Example:

```
kubectl create configmap config-data --from-file=/data
```

6. View the details of the configmap object, using `kubectl describe` command:

```
kubectl describe configmap <configmapName>
```

Example:

```
kubectl describe configmap config-data
```

7. Create StatefulSet resource to deploy container.

Run the below command to deploy the container:

```
kubectl apply -f <location of the YAML file>
```

Example:

```
kubectl apply -f idc-statefulset.yaml
```

A sample StatefulSet resource file has been shown below:

```

apiVersion: apps/v1
kind: StatefulSet
metadata:
  name: idconsole-app
spec:
  serviceName: idconsole
  selector:
    matchLabels:
      app: idconsole
  replicas: 1
  template:
    metadata:
      labels:
        app: idconsole
    spec:
      containers:
        - name: idconsole-container
          image: registryname.azurecr.io/identityconsole:
<version>
          env:
            - name: ACCEPT_EULA
              value: "Y"
          ports:
            - containerPort: 9000
          volumeMounts:
            - name: configfiles
              mountPath: /config/data
            - name: datapersistenceandlog
              mountPath: /config
              subPath: log
      volumes:
        - name: configfiles
          configMap:
            name: config-data
        - name: datapersistenceandlog
          persistentVolumeClaim:
            claimName: pvcforsc

```

8. Run the following command to verify the status of the deployed pod:

```
kubectl get pods -o wide
```

9. Create Service resource of type loadBalancer.

The type of service specified in yaml file is of loadBalancer.

Create a service resource using the below command:

```
kubectl apply -f <location of the YAML file>
```

Example:

```
kubectl apply -f ids-service.yaml
```

A sample service resource file has been shown below:

```
apiVersion: v1
kind: Service
metadata:
  name: idconsole-service
  labels:
    run: idconsole-service
spec:
  type: LoadBalancer
  loadBalancerIP: xx.xx.xx.xx
  selector:
    app: idconsole
  ports:
    - port: 9000
      targetPort: 9000
      protocol: TCP
```

Check the EXTERNAL-IP address (or the loadBalancerIP) using the below command:

```
kubectl get svc -o wide
```

10. Launch url using EXTERNAL-IP (or the loadBalancerIP address).

Example:

`https://<EXTERNAL-IP>:9000/identityconsole`

1.3. Upgrading OpenText Identity Console

This chapter describes the process for upgrading OpenText Identity Console to its latest versions. To prepare for the upgrade, review the prerequisites and system requirements provided in [Planning to Install OpenText Identity Console](#).

This section includes the following procedures:

- [Upgrading OpenText Identity Console on standalone server](#)
- [Upgrading OpenText Identity Console workstation on Windows](#)
- [Upgrading OpenText Identity Console container](#)
- [Upgrading the OSP container](#)

1.3.1. Upgrading OpenText Identity Console on standalone server

This section explains the procedure to upgrade standalone OpenText Identity Console:

1. Log in to the [Software License and Download](#) portal and navigate to Software Download SLD page.
2. Navigate by selecting the Product: **OpenText eDirectory** > Product Name: **OpenText eDirectory per User Sub SW E-LTU** > Version: **25.4**
3. Download the latest `IdentityConsole_<version>_Linux.tar.gz` build.
4. Extract the downloaded build by using the following command:

```
tar -zxvf IdentityConsole_<version>_Linux.tar.gz
```

5. Navigate to the folder where you extracted the OpenText Identity Console build.
6. Run the following command:

```
./identityconsole_install
```

7. Follow the instructions as per your OpenText identity Console version.
 1. **[OpenText Identity Console 1.9 and later]** Perform one of the following action as per your requirement:
 - If you want to auto fetch the CA certificates, choose auto fetch as `'y'`.
 - If you do not want to auto fetch the CA certificates, choose auto fetch as `'n'`.
 2. **[For Identity Console 1.8 and earlier]** Specify the previously configured `eDirectory-hosts` to connect. You can provide either an IP address or a domain name .

Example: `localhost:636,xx.xx.xx.xx:636` or `edir.domain.com:636`

OpenText Identity Console gets upgraded successfully.

1.3.2. Upgrading OpenText Identity Console workstation on Windows



Note

- Upgrade OpenText Identity Console to the latest version to support OpenText eDirectory 9.3.
- Reinstall the NCI instance to support the upgraded version of OpenText Identity Console (version 1.9 and later).

The following procedure describes how to upgrade OpenText Identity Console (version 1.5 and later) workstation on Windows.

1. Before upgrading to the new version, ensure to uninstall the previous version as explained: [Uninstallation of OpenText Identity Console Workstation on Windows](#).



Note

To retain the system preference settings, we recommend you to take backup of `CustomConfig.json` file from `C:\IdentityConsole_version_workstation_win_x86_64\eDirAPI`.

2. Log in to the [Software License and Download](#) portal and navigate to the Software Downloads page.
3. Select the following:
 - Product: OpenText eDirectory
 - Product Name: OpenText eDirectory per User Sub SW E-LTU
 - Version: 25.4
4. Download the latest version:
`IdentityConsole_<version>_workstation_win_x86_64.zip`.
5. Extract the downloaded
`IdentityConsole_<version>_workstation_win_x86_64.zip`.
6. Navigate to the extracted folder:
`IdentityConsole_<version>_workstation_win_x86_64\eDirAPI\cert`,

IdentityConsole_<version>_workstation_win_x86_64\edirAPI , and copy the keys.pfx and the customConfig.json file respectively that was taken as backup during [Uninstallation of OpenText Identity Console Workstation on Windows](#).

To get the certificates, refer to the section: [System Requirements and Prerequisites for Workstation](#).

If the user need to connect to multiple OpenText eDirectory trees, refer to the section: [Multi-tree with OpenText Identity Console as Workstation](#).



Note

The server certificate name must always be as keys.pfx .

7. (Optional) Navigate to the folder where the build is extracted and install NICI_wx64 depending on the system configuration. If your system has eDirectory, proceed directly to step 8.
8. Double-click on the file configure.bat > enter the server certificate (keys.pfx) password in the command prompt.
9. Double-click on the file run.bat (Windows batch file).

The edirAPI process terminal (edirapi.exe) starts running, and the OpenText Identity Console login page appears.



Note


- If the edirAPI process terminal (edirapi.exe) is already running, then run identityconsole.exe from the build extracted folder.
- Users can find the following logs in:
 \IdentityConsole_<version>_workstation_win_x86_64\edirAPI\log
 edirapi.log - This is used for logging different events in edirapi and debugging issues.
 edirapi_audit.log - This is used for logging audit events of edirapi .
 The logs follow CEF auditing format.
- OSP based login is not supported in workstation mode.
- OpenText Identity Console Workstation is listening on 9000 port. Do not modify the edirapi_win.conf file.

1.3.3. Upgrading OpenText Identity Console container

When a new version of OpenText Identity Console image is available, the administrator can perform a upgrade procedure to deploy container with the latest version of OpenText Identity Console. Ensure to store all necessary application related data persistently in Docker volumes before performing an upgrade .

Perform the following steps to upgrade OpenText Identity Console using Docker Container:

1. Download and load the latest version of the Docker image from the [Software License and Download](#) and perform the steps to install the latest version OpenText Identity Console as mentioned in [Installing OpenText Identity Console](#).



Note

Before upgrading from version 25.2 to 25.4, run the following command to copy the NICI folder:

```
docker exec <idc_container_name> sh -c 'mv
/var/opt/novell/nici /config/eDirAPI/ && ln -sf
/config/eDirAPI/nici /var/opt/novell/nici'
```

Before upgrading from version 24.4 and below to version 25.4, as part of security fix, ensure to add the `idconsolemode = true` , `check-origin = "true"` and `origin = "<IP_address>:<port>"` attributes in the `edirapi.conf` file present in the volume.

For example:

```
listen = ":9000"
idconsolemode = true;
osp-mode = false;
auto-fetch = true;
check-origin = "true";
origin = "https://10.xx.xx.xx:636"
bcert = "etc/opt/novell/edirAPI/cert"
```

2. Once the latest Docker image is loaded, stop your current Docker Container using the following command:

```
docker stop <identityconsole-container-name>
```

For example:

```
docker stop identityconsole-container-1
```

3. Delete the existing container by running the following command:

```
docker rm <identityconsole-container-name>
```

For example,

```
docker rm identityconsole-container-1
```

4. Delete the obsolete OpenText Identity Console Docker image by running the following command, if necessary:

```
docker rmi <identityconsole-image>
```

For example:

```
docker rmi identityconsole:<version>
```

5. The image has to be loaded into the local Docker registry. Extract and load the IdentityConsole_<version>_Containers.tar.gz file using the below commands:

```
tar -xvf IdentityConsole_<version>_Containers.tar.gz
```

```
docker load --input identityconsole.tar.gz
```

6. Run the following command to upgrade Identity Console Container based on your requirement:

- To customize the FQDN configuration inside the host file (`/etc/host`) of the container, use the `--add-host` flag.

```
docker run --name identityconsole_container --volume IDConsole-  
volume:/config --add-host=FQDN:IDC_IP --add-host=FQDN:eDir_IP -p  
9000:9000 -d identityconsole:<version>
```

- To configure the container and the host to share the same network, use `--network=host` flag:

```
docker run --name identityconsole_container --volume IDConsole-  
volume:/config --network=host -d identityconsole:<version>
```

7. To check status of the running container, run the following command:

```
docker ps -a
```

1.3.4. Upgrading the OSP container

Perform the following steps to upgrade the OSP container:

1. Download and load the latest version of the OSP image from the [Software License and Download](#).

For example,

```
docker load --input osp.tar.gz
```

2. Once the latest OSP image is loaded, stop your current OSP container using the following command:

```
docker stop OSP container name
```

3. (Optional) Take the backup of the shared volume.
4. Delete the existing OSP container by running the following command:

```
docker rm OSP container name
```

For example,

```
docker rm OSP_Container
```

5. Go to the directory that contains keystore (tomcat.ks) and silent properties file, delete the existing keystore (tomcat.ks) and retain the existing OSP folder. Generate a new keystore (tomcat.ks) with key size as 2048. For more information, see step 4 in the [Deploying the OSP Container](#).
6. Deploy the container using the following command:

```
docker run -d --name <OSP_Container> --network=host -e SILENT_INSTALL_FILE=/config/osp-edirapi-silent.properties -v /data:/config osp:version
```

For example,

```
docker run -d --name OSP_Container --network=host -e
SILENT_INSTALL_FILE=/config/osp-edirapi-silent.properties -v
/data:/config osp:<version>
```

1.4. Uninstalling OpenText Identity Console

This chapter describes the process for uninstalling OpenText Identity Console:

- [Uninstallation of OpenText Identity Console Docker Container](#)
- [Uninstallation of Standalone OpenText Identity Console \(Non-Docker\)](#)
- [Uninstallation of OpenText Identity Console Workstation on Windows](#)

1.4.1. Uninstallation of OpenText Identity Console docker container

To uninstall OpenText Identity Console Docker container, perform the following steps:

1. Stop the OpenText Identity Console container:

```
docker stop <container-name>
```

2. Run the following command to remove the OpenText Identity Console Docker Container:

```
docker rm -f <container_name>
```

3. Run the following command to remove the Docker image:

```
docker rmi -f <docker_image_id>
```

4. Remove the Docker volume:

```
docker volume rm <docker-volume>
```



Note

If you remove the volume, the data will also be removed from your server.

1.4.2. Uninstallation of standalone OpenText Identity Console (non-docker)

To uninstall standalone OpenText Identity Console, perform the following steps:

1. Navigate to the `/usr/bin` directory on the machine where OpenText Identity Console is installed.
2. Run the following command:

```
./identityconsoleUninstall
```

OpenText Identity Console is successfully uninstalled.



Note

When the OpenText eDirectory or other OpenText OpenText product is installed in the machine, the user must manually uninstall *nici* and *openssl*.

1.4.3. Uninstallation of OpenText Identity Console workstation on Windows

1. Close all the OpenText Identity Console applications.
2. Close the eDirAPI terminal.
3. Navigate to the folder `IdentityConsole_<version>_workstation_win_x86_64` where the build is extracted, navigate to `eDirAPI` folder, and take a backup of `cert` folder.
4. Delete the Workstation folder `IdentityConsole_<version>_workstation_win_x86_64`.
5. Uninstall `NICI_wx64`, only if eDirectory is not installed in the server.

The OpenText Identity Console Workstation on Windows is uninstalled.

1.5. Troubleshooting

This section includes some tips and best practices while using OpenText Identity Console. If you find something that works well for you, please share it at [Cool Solutions](#).

- [ERROR: Login Failure. Invalid Credentials](#)
- [INFO: Latest OpenText Identity Console version is already installed. Exiting](#)
- [ERROR: Installing OpenText Identity Console with Older NCI Instance](#)
- [ERROR: Failed Dependencies](#)
- [ERROR: Server Certificate Failed Message](#)

For the OpenText Identity Console to perform at its best, use latest supported browser, and clear the browser cache and cookies at regular intervals.

1.5.1. Error: Login failure. Invalid credentials

If you see a "Login Error. Invalid Credentials" (applies only for Container and Linux installed IDC) error message when you log into the OpenText Identity Console, you should check the OpenText Identity Console network call to find if "Entered Hostname invalid" error appears. If you receive an error message, it is because the OpenText eDirectory IP address associated with the OpenText Identity Console may not be present in the `edirapi.conf` file. In this situation, edit the `edirapi.conf` file and add the `edirectory ip` address to the file under the `edir-hosts` parameter.

A sample configuration file is shown below:

```
listen = ":9000"
pfxpassword = "DUMMY-FE98DC76BA54"
bcert = "/etc/opt/novell/eDirAPI/cert/"
ospmode=false
edir-hosts = "<ip_address-1>:636,<ip_address-2>:636"
```

1.5.2. INFO: Latest OpenText Identity Console version is already installed. Exiting

If OpenText Identity Console installation fails or gets interrupted, and the installer exits, on re-install of OpenText Identity Console, the error message is displayed as "Latest identity console version is already installed. Exiting".

In this situation uninstallation of the OpenText Identity Console is not required, user can run the following command to configure:

```
/usr/bin/identityconsoleConfigure
```

1.5.3. ERROR: Installing OpenText Identity Console with older NCI instance

If an unsupported version of NCI is installed or if the NCI is not updated, OpenText Identity Console (version 1.8 and later) displays the following error message.

```
Server not configured with configure.bat file.
```

You have to uninstall or update the NCI instance to support the current version of OpenText Identity Console.

1.5.4. ERROR: Failed dependencies

If you see the failed dependency error message for `libldap_r-2.4.so.2` while installing the OpenText Identity console (version 1.7.2 and later) on later version of RHEL 9.X, install the `openldap-compact rpm` running the below command.

```
yum install openldap-compat.x86_64
```

1.5.5. ERROR: Server certificate failed message

While installing the OpenText Identity console (version 1.7.2 and later) on FIPS-enabled RHEL (version 9.X), you may see an auto-fetching server certificate failed error message.

This issue can be overcome by manually providing the certificates.



© Copyright 2026 Open Text

For more info, visit <https://docs.microfocus.com>
