

OpenText™ Identity Manager

Jobs Guide

Version : 25.4

PDF Generated on : April 21, 2026

Table of Contents

1. Jobs Guide	1
1.1. Overview	2
1.2. Adding a Predefined Job	4
1.2.1. Adding Other Predefined Jobs	5
1.3. Configuring the Properties of Predefined Jobs	7
1.3.1. Understanding the Different States of a Job	8
1.3.2. Configuring the Random Password Generator Job	10
1.3.3. Configuring the Schedule Driver Job	13
1.3.4. Configuring the Subscriber Channel Trigger Job	16
1.3.5. Configuring the Driver Health Job	20
1.3.6. Configuring the Password Expiration Notification Job	25
1.3.7. Modifying the Association Statistics Job Configuration	29
1.4. Creating a Custom Job	33
1.4.1. Job Components	34
1.4.2. Creating the Job Definition and Job Implementation	35
1.4.3. Adding the Job	36
1.5. Starting a Job	37
1.6. Stopping a Job	38
1.7. Disabling a Job	39
1.8. Checking a Job's Status	40
1.9. Deleting a Job	41

1. Jobs Guide

This guide *contains* information about managing OpenText Identity Manager jobs. It is intended for OpenText Identity Manager administrators, partners, and consultants.

1.1. Overview

OpenText Identity Manager provides the ability to launch jobs that perform specific tasks. The jobs can be run more than once, either manually or at scheduled times.

It provides six predefined jobs:

- **Random Password Generator:** Generates a random password for each object defined in the job's scope. The password is generated by NMAS to match a Password Policy object that the job references. The job submits the generated passwords one at a time to a driver's Subscriber channel. The Subscriber channel policies must take action on the passwords.
- **Schedule Driver:** Starts or stops a driver.
- **Subscriber Channel Trigger:** Sends event documents to be processed by a driver's Subscriber channel. For example, a job could generate an event document to trigger policies associated with a user. Submitted event documents can be queued to the driver cache or bypass the cache and processed immediately.
- **Driver Health:** Evaluates the health conditions of a driver, assigns the health state, and carries out any actions associated with the health state. The job is used in conjunction with driver health monitoring. For information about setting up driver health monitoring, including using the Driver Health job, see [Monitoring Driver Health](#) in the [Driver Administration Guide](#).
- **Password Expiration Notification:** Searches for an LDAP directory for objects whose passwords expire in a specified number of days. When an object that meets the criteria is discovered, the job sends an email to the address contained in the object's mail LDAP attribute.
- **Association Statistics:** Calculates the association statistics per server.

Information about using the predefined jobs is provided in [Adding a Predefined Job](#) and [Configuring the Properties of Predefined Jobs](#).

You can also develop custom jobs to perform tasks. A custom job requires you to create a Job Definition and a Job Implementation. The Job Definition is XML code that defines the parameters for the job. The Job Implementation is a JAR file that contains the Java classes that perform the task. The job can perform any task that you can implement through Java classes. Because the job is initiated through the engine, the

job also has access to the Identity Vault data. For more information, see [Creating a Custom Job](#).

1.2. Adding a Predefined Job

OpenText Identity Manager includes the following predefined jobs:

- **Driver Health:** Evaluates the health conditions of the driver, assigns the health state, and carries out any actions associated with the health state.
- **Password Expiration Notification:** Sends email notifications to users whose passwords are about to expire.
- **Random Password Generator:** Generates a random password for identified objects.
- **Schedule Driver:** Starts or stops the driver.
- **Subscriber Channel Trigger:** Submits XML documents to the Subscriber channel to trigger events.
- **Association Statistics:** Calculates the association statistics per server.

Two jobs (Driver Health and Password Expiration Notification) also operate at the driver set level; they automatically apply to all drivers in the driver set unless you change the job scope to exclude some drivers.

The last three jobs (Random Password Generator, Schedule Driver, and Subscriber Channel Trigger) operate at the driver level. You can add them to individual drivers.

1.2.1. Adding Other Predefined Jobs

The following steps provide instructions for using OpenText Identity Console to add all predefined jobs (Driver Health, Password Expiration Notification, Random Password Generator, Schedule Driver, and Subscriber Channel Trigger). For information about using Designer to add jobs, see [Scheduling Jobs](#) in the [Designer Administration Guide](#).

1. Click the **IDM Administration** tab from the home screen.
2. (Conditional) If you want to add the job to a driverset:
 1. Click the **Action menu** icon on the appropriate driver set and select **Driver Set Properties**.
 2. Click **Advanced > Jobs**.
 3. Click the **+ Create a new job** icon.
3. (Conditional) If you are adding the job to a driver:
 1. Click the driver to display the driver properties page.
 2. Click **Advanced > Jobs**.
 3. Click the **+ Create a new job** icon.
4. In the **Job Name** field, specify a descriptive name for the job.
5. Under **Job Type**, make sure that **Installed** is selected, then choose one of the following job types:
 - **Driver Health (Driver Set):** Evaluates the health conditions for a driver, assigns the health state, and carries out any actions associated with the health state.
 - **Password Expiration Notification (Driver Set):** Sends e-mail notifications to users whose passwords are about to expire.
 - **Random Password Generator (Driver Only):** Generates a random password for each object in the job's scope. The password is generated by NMAS to match the Password Policy object that the job references. These Password Policy objects are not usually the same as those used for OpenText eDirectory user password policies.

The job submits the generated passwords one at a time to the driver's Subscriber channel. The Subscriber channel policies must take action on the passwords.

- **Schedule Driver (Driver Only):** Starts or stops the associated driver. You can also toggle a driver to start the driver if it is stopped or to stop the driver if it is running.
- **Subscriber Channel Trigger (Driver Only):** Submits zero or more trigger documents to the Subscriber channel. The submission can either be a document per object if a scope is defined, or it can be a single trigger event if no scope is defined.

Trigger event documents identify the job and the scope object. A trigger event can bypass the cache and be processed immediately if desired. Trigger jobs allow you to use driver policies that you can customize for your personal requirements.

6. In the **Server(s) to run this job** field, select the servers where you want to run the job.

7. Click **Create**.

8. Under **Advanced > Jobs**, select the newly created job name to display its configuration properties.

9. To configure the job's properties, continue with the instructions in the appropriate section:

- [Configuring the Random Password Generator Job](#)
- [Configuring the Schedule Driver Job](#)
- [Configuring the Subscriber Channel Trigger Job](#)
- [Configuring the Driver Health Job](#)
- [Configuring the Password Expiration Notification Job](#)

1.3. Configuring the Properties of Predefined Jobs

The following sections provide instructions for using OpenText Identity Console to configure the properties for five predefined jobs:

- Random Password Generator
- Schedule Driver
- Subscriber Channel Trigger
- Driver Health
- Password Expiration Notification

Each job generates intermediate results and a final result, where the intermediate results affect the final result. For more information, see [Understanding the Different States of a Job](#).

For each job, you can schedule the runtimes, define the scope of objects that the job applies to, set the job-specific parameters, and determine the methods used for results notification. For information about using Designer to configure a job, see [Scheduling Jobs](#) in the [Designer Administration Guide](#).

The steps assume the job is already added to a driver or driver set. For more information about adding predefined jobs, see [Adding a Predefined Job](#).

- [Understanding the Different States of a Job](#)
- [Configuring the Random Password Generator Job](#)
- [Configuring the Schedule Driver Job](#)
- [Configuring the Subscriber Channel Trigger Job](#)
- [Configuring the Driver Health Job](#)
- [Configuring the Password Expiration Notification Job](#)
- [Modifying the Association Statistics Job Configuration](#)

1.3.1. Understanding the Different States of a Job

When a job runs, it generates intermediate results and a final result. The possible results are Success, Warning, Error, and Aborted. The intermediate results affect the final result. The final result is generated when the job is finished.

For each result, you can specify the action you want performed when it occurs. You can instruct the job to generate an event for Novell Audit or Novell Sentinel and also generate an email notification. Alternatively, you might want no action to occur for an intermediate success result and an email notification to be sent for an intermediate error result.

Success

Returned when a job has successfully executed without any errors or warnings.

Warning

Returned when a job cannot complete its execution because of unfulfilled prerequisites required for a successful run of the job. For example, a driver is not configured with a health check before a health check job is run on the driver. The job returns a warning as a final result.

A warning is also displayed when a job partly succeeds in executing its defined task. For example, when a Password Expiration Notification job does not find an object's `passwordExpirationTime` attribute value, the job generates a warning message for that object as an intermediate result. If you instructed the job to send an e-mail to the address contained in the object's mail LDAP attribute, the job does not send the specified e-mail. When the job finishes its scheduled run, OpenText Identity Manager displays a warning with an appropriate message.

A Password Generator job generates an intermediate success message when it successfully generates a password for a user. If the job fails to generate a password for a user object for some reason, OpenText Identity Manager displays a warning as a final result.

Error

Returned when a job has insufficient rights on the object on which it is scheduled to run. An error is also reported when a job is executing and an exception occurs. For example, running a Schedule Driver job to run an already running driver or schedule the job to stop an already stopped driver.

Abort

Stops a job before the job completes its scheduled run. For example, terminating a job using `dxcmd`. Or, when the engine is stopped, all running jobs are automatically aborted.

1.3.2. Configuring the Random Password Generator Job

The Random Password Generator job creates a random password for each object defined in the job's scope. The password is generated by NMAS to match a Password Policy object that the job references. Generally, each driver requires a password policy designed specifically for the connected system. If you don't have a password policy to use, you need to create one before continuing with the job configuration. The job submits the generated passwords one at a time to the driver's Subscriber channel. The Subscriber channel policies must take action on the passwords.

1. Make sure you've already added the job to the driver. See [Adding a Predefined Job](#).
2. On the **General** tab in OpenText Identity Console (under **Advanced > Jobs**), configure the following options:

Enable job: Leave this option selected unless you don't want the job to run.

Delete the job after the first run: Select this option if you want the job to run once only and then be deleted.

Select the server(s) this job should run on: Select the servers where you want the job to run. Multiple servers are available only if the driver is running on multiple servers.

Email server: To monitor the job, you (or others) can receive email notifications whenever certain results occur for the job. You configure email notification on the **Results** tab. However, to enable this email notification to work, you must first specify the email server that will be used to send the notifications. Click the search button to locate and select the `Default Notification Collection` object or any other `notifTemplateCollection` object that defines an SMTP mail server. To send notifications, the job reads the target mail server and authentication credentials (except the password, which is specified in the **Email server password** field) from the selected `Default Notification Collection` object.

Email server password: Set the password for your email server account.



Note

If you do not specify a password, one of the following conditions will apply, depending on the authentication method used by the mail server:

- For basic authentication, the job reads the email server password from **named passwords** using the `dirxml.engine.smtp` key, which is stored at the active driverset level.
- For modern authentication, the client secret is used instead of the email server password. In this case, the job reads the client secret from **named passwords** using the `dirxml.engine.smtp.clientsecret` key, which is also stored at the active driverset level.

Display name: Displays the name assigned to the job.

Description: Displays the description assigned to the job.

3. On the **Schedule** tab, you can select one of the following options:

Toggle to schedule job: Runs the job on a daily, weekly, monthly, or yearly schedule. You can also specify a custom schedule; use the crontab standard when specifying a custom schedule.

Toggle to run job manually: Runs the job only when you initiate it through the **Start the selected job** option (see [Starting a Job](#)).

4. On the **Scope** tab, click the **+ Add an object to the job scope** icon to add the objects for which you want to generate passwords.

5. On the **Parameters** tab, fill in the following fields:

Password Policy object used for password generation: Select the Password Policy object you want to use to generate the passwords. NMAS uses the password policy to generate the passwords. Generally, each driver requires a password policy designed specifically for the connected system. If you don't have a password policy, click the **Save** icon to save the job's current configuration, then create a password policy.

Generate a password for objects without a driver association: This is set to `false` by default. If you added objects to the **Scope** tab that are not associated

with objects in the driver's connected system, and you want to generate passwords for these objects, select **true**.

6. On the **Results** tab, define the actions you want performed based on the results for the job.

Each time the job runs, it generates intermediate results and the final result. For each result, you can specify the action you want performed when it occurs. For more information, see [Understanding the Different States of a Job](#).

1. Click the **No action** link next to the result to display the Result Notification dialog box.
2. Select **Audit result** if you want to generate an event for Novell Audit or Novell Sentinel.

or

Select **Send email**, then fill in the recipient and e-mail template information.

3. Click **OK** to save your changes.

7. When you have finished configuring the job, click the **Save** icon to save your changes.

8. Select the job in the list (by selecting the check box next to the job name), then click the **Get Status** icon.

The Job Status dialog box displays any configuration errors. Because the job requires rights to the driver object and those rights have not yet been granted, you see an **Insufficient rights to driver object** error.

9. Click **Grant rights**, then click **OK** to confirm the action.

10. If other errors are displayed, resolve the errors. Otherwise, click **OK** to close the Job Status dialog box.

1.3.3. Configuring the Schedule Driver Job

The Schedule Driver job starts or stops the driver based on an established schedule.

1. Make sure you've already added the job to the driver. See [Adding a Predefined Job](#).
2. On the **General** tab in OpenText Identity Console (under **Advanced > Jobs**), configure the following options:

Enable job: Leave this option selected unless you don't want the job to run.

Delete the job after the first run: Select this option if you want the job to run once only and then be deleted.

Select the server(s) this job should run on: Select the servers where you want the job to run. Multiple servers are available only if the driver is running on multiple servers.

Email server: To monitor the job, you (or others) can receive email notifications whenever certain results occur for the job. You configure e-mail notification on the **Results** tab. However, to enable this email notification, you must first specify the email server. Click the **search** button to locate and select the **Default Notification Collection** object or any other **notfTemplateCollection** object that defines an SMTP mail server. To send notifications, the job reads the target mail server and authentication credentials (except the password, which is specified in the **Email server password** field) from the selected **Default Notification Collection** object.

Email server password: Set the password for your email server account.



Note

If you do not specify a password, one of the following conditions will apply, depending on the authentication method used by the mail server:

- For basic authentication, the job reads the email server password from **named passwords** using the `dirxml.engine.smtp` key, which is stored at the active driverset level.
- For modern authentication, the client secret is used instead of email server password. In this case, the job reads the client secret from **named passwords** using the `dirxml.engine.smtp.clientsecret` key, which is also stored in the active driverset level.

Display name: Displays the name assigned to the job.

Description: Displays the description assigned to the job.

3. On the **Schedule** tab, select one of the following options:

Toggle to schedule job: Runs the job on a daily, weekly, monthly, or yearly schedule. You can also specify a custom schedule; use the crontab standard when specifying a custom schedule.

Toggle to run job manually: Runs the job only when you initiate it through the **Run Now** option (see [Starting a Job](#)).

4. Ignore the **Scope** tab; it does not apply to the Schedule Driver job.

5. On the **Parameters** tab, select the type of action you want the job to perform:

Start the driver: Starts or restarts the driver.

Stop the driver: Stops the driver.

Toggle the driver: Starts the driver if it is stopped. Stops the driver if it is running.

6. On the **Results** tab, define the actions you want performed based on the results for the job.

Each time the job runs, it generates intermediate results and a final result. For each result, you can specify the action you want performed when it occurs. For

more information, see [Understanding the Different States of a Job](#).

1. Click the **No action** link next to the result to display the Result Notification dialog box.

2. Select **Audit result** if you want to generate an event for Novell Audit or Novell Sentinel.

or

Select **Send email**, then fill in the recipient and e-mail template information.

3. Click **OK** to save your changes.

7. When you have finished configuring the job, click the **Save** icon to save your changes.

8. Select the job in the list (by selecting the check box next to the job name), then click the **Get Status** icon.

The Job Status dialog box displays any configuration errors. Because the job requires rights to the driver object and those rights have not yet been granted, you see an **Insufficient rights to driver object** error.

9. Click **Grant rights**, then click **OK** to confirm the action.

10. If other errors are displayed, resolve the errors. Otherwise, click **OK** to close the Job Status dialog box.

1.3.4. Configuring the Subscriber Channel Trigger Job

The Subscriber Channel Trigger job sends event documents to be processed by the driver's Subscriber channel. For example, a job could generate an event document to trigger policies associated with a user.

You configure the job to generate zero, one, or more event documents by defining a scope for the job. The scope identifies objects for which you want the job to trigger events. If you do not include a scope (no objects), the job creates one event document. If you identify one or more objects, the job creates event documents for each object.

Submitted event documents can be queued to the driver cache, or they can bypass the cache and be processed immediately.

1. Make sure you've already added the job to the driver. If you haven't, see [Adding a Predefined Job](#).
2. On the **General** tab in OpenText Identity Console (under **Advanced > Jobs**), configure the following options:

Enable job: Leave this option selected unless you don't want the job to run.

Delete the job after the first run: Select this option if you want the job to run one time only and then be deleted.

Select the server(s) this job should run on: Select the servers where you want the job to run. Multiple servers are available only if the driver is running on multiple servers.

Email server: To monitor the job, you (or others) can receive e-mail notifications whenever certain results occur for the job. You configure e-mail notification on the Results page. However, to enable this e-mail notification to work, you must first specify the e-mail server that will be used to send the notifications. Click the search button to locate and select the `Default Notification Collection` object or any other `notfTemplateCollection` object that defines an SMTP mail server. To send notifications, the job reads the target mail server and authentication credentials (except the password, which is specified in the **Email server password** field) from the selected `Default Notification Collection` object.

Email server password: Set the password for your email server account.



Note

If you do not specify a password, one of the following conditions will apply depending on the authentication method used by the mail server:

- For basic authentication, the job reads the email server password from **named passwords** using the `dirxml.engine.smtp` key, which is stored at the active driverset level.
- For modern authentication, the client secret is used instead of email server password. In this case, the job reads the client secret from **named passwords** using the `dirxml.engine.smtp.clientsecret` key, which is also stored in the active driverset level.

Display name: Displays the name assigned to the job.

Description: Displays the description assigned to the job.

3. On the **Schedule** tab, select one of the following options:

Toggle to schedule job: Runs the job on a daily, weekly, monthly, or yearly schedule. You can also specify a custom schedule; use the crontab standard when specifying a custom schedule.

Toggle to run job manually: Runs the job only when you initiate it through the **Run Now** option (see [Starting a Job](#)).

4. On the **Scope** tab, click **+ Add an object to the job scope** icon to add the objects for which you want the job to trigger events. For each identified object, the job creates an event document. If no object is scoped, the job trigger creates one event document.

5. On the **Parameters** tab, set the parameters for which you want the job to submit trigger documents.

1. If you want to submit a trigger document for scoped objects that do not have a driver association, select `true`. Otherwise, keep the default of `false`.

2. If you want to use the job's Common Name (CN) as a document identifier trigger, keep the default of `true`. Otherwise, select `false`.

3. (Optional) If you select **false** , enter the string that the job can use as the value for the trigger element's Source attribute.
4. Select a method for submitting the trigger documents. If you want to queue the job the trigger is from, keep the default of **Queue (use cache)** . Otherwise, select **Direct (bypass cache)** .
5. (Optional) If you select **Direct (bypass cache)** , you are presented with the **Start driver if not running** option. If you want to start the driver if it is not running, keep the default of **true** . Otherwise, select **false** .
6. (Optional) If you select **true** on the **Start driver if not running** option, you are presented with the **Stop driver when finished processing triggers** option with the default of **true** . Use the default to stop the driver after it finishes processing the trigger job, or select false to keep the driver running.

A customized job definition has its own parameter set.

6. On the **Results** tab, define the actions you want performed based on the results for the job.

Each time the job runs, it generates intermediate results and a final result. For each result, you can specify the action you want performed when it occurs. For more information, see [Understanding the Different States of a Job](#).

1. Click the **No action** link next to the result to display the Result Notification dialog box.
2. Select **Audit result** if you want to generate an event for Novell Audit or Novell Sentinel.

or

Select **Send email**, then fill in the recipient and e-mail template information.

3. Click **OK** to save your changes.
7. When you have finished configuring the job, click the **Save** icon to save your changes.
8. Select the job in the list (by selecting the check box next to the job name), then click the **Get Status** icon.

The Job Status dialog box displays any configuration errors.

9. Click **Grant rights**, then click **OK** to confirm the action.

10. If other errors are displayed, resolve the errors. Otherwise, click **OK** to close the Job Status dialog box.

1.3.5. Configuring the Driver Health Job

The Driver Health job evaluates the conditions for a driver's health states, assigns the driver with the appropriate state, executes any actions associated with the assigned state, and stores the driver's transaction data. The default polling interval is one minute. For more information about setting up health monitoring for a driver, see [Monitoring Driver Health](#) in the [Driver Administration Guide](#).

1. Make sure you've already added the job to the driver set. See [Adding a Predefined Job](#).
2. On the **General** tab in OpenText Identity Console (under **Advanced > Jobs**), configure the following options:

Enable job: Leave this option selected unless you don't want the job to run.

Delete the job after the first run: Select this option if you want the job to run only once and then be deleted.

Select the server(s) this job should run on: Select the servers where you want the job to run. Multiple servers are available only if the driver is running on multiple servers.

Email server: To monitor the job, you (or others) can receive email notifications whenever certain results occur for the job. You can configure email notification on the Results page. However, to enable this email notification, you must first specify the email server. Click the search button to locate and select the **Default Notification Collection** object or any other **notfTemplateCollection** object that defines an SMTP mail server. To send notifications, the job reads the target mail server and authentication credentials (except the password, which is specified in the **Email server password** field) from the selected **Default Notification Collection** object.

Email server password: Set the password for your email server account.



Note

If you do not specify a password, one of the following conditions will apply depending on the authentication method used by the mail server:

- For basic authentication, the job reads the email server password from **named passwords** using the `direxml.engine.smtp` key, which is stored at the active driverset level.
- For modern authentication, the client secret is used instead of email server password. In this case, the job reads the client secret from **named passwords** using the `dirxml.engine.smtp.clientsecret` key, which is also stored in the active driverset level.

Display name: Displays the name assigned to the job.

Description: Displays the description assigned to the job.

3. On the **Schedule** tab, specify when you want the job to run:

The Driver Health job is a continuously running job, meaning that it does not stop unless a health state action shuts it down or it is shut down manually. The job must run continuously to be able to support transaction data collection for use in Transactions History conditions.

If the job does stop, it is restarted based on the schedule.

Toggle to schedule job: Runs the job on a daily, weekly, monthly, or yearly schedule. You can also specify a custom schedule; use the crontab standard when specifying a custom schedule. The default schedule checks every minute to see if the job is running. If the job is not running, it is started.

Toggle to run job manually: Runs the job only when you initiate it through the **Run Now** option (see [Starting a Job](#)).

4. On the **Scope** tab, click **+ Add an object to the job scope** icon to add the driver sets or individual drivers you want the job applied to.

By default, the job applies to all drivers in the driver set. You can, however, modify the list so that the job applies only to specific drivers in the driver set. You can also add other driver sets or drivers from other driver sets.

5. On the **Parameters** tab, select the type of action you want the job to perform:

Login ID: This defaults to the login ID that was used when creating the driver job. You should change this only if you want the driver to authenticate by using different credentials.


You need the following rights to run the health job:

- Read permission with inheritance to the **DirXML-AccessConfigure** attribute of the Driver Set object
- Read permission with inheritance to the **DirXML-AccessRun** attribute of the Driver Set object
- Write permission with inheritance to the **DirXML-AccessSubmitCommand** attribute of the Driver Set object

Login password: This is the password required for the login ID that you supplied in the **Login ID** field.

Subscriber Heartbeat: Controls whether the Driver Health job does a heartbeat query on a driver's Subscriber channel before performing a healthcheck on the driver.

Polling interval: Calculates the driver's transaction data that the health job will store. The default polling interval is one minute.



Note

This parameter was earlier used to perform the following actions:

- Determined how often the job evaluated the conditions for the health states.
- Assigned the driver the appropriate state.
- Executed any actions associated with the assigned state.
- Stored the driver's transaction data.

Polling interval units: Specifies the time unit (minutes, hours, days, weeks) for the number specified in the Polling interval setting.

Duration sampling data is kept: Specifies how long a driver's transaction data is kept. The default, two weeks, causes a transaction to be retained for two weeks before being deleted. A longer duration provides a greater period that can be

used in Transactions History conditions, but requires more memory. For example, to use a Transactions History condition that evaluates the number of publisher-reported events for the last 10 days, you need to keep transaction data for at least 10 days.

Duration units: Specifies the time unit (minutes, hours, days, weeks) for the number specified in the **Duration sampling data is kept** setting.

The combination of **Polling interval**, **Polling interval units**, **Duration sampling data is kept**, and **Duration units** define how much sampling data is maintained by the Driver Health Job, which indicates how much memory the Driver Health Job will require to run.

To store transaction data for one driver every minute (**Polling interval**) for two weeks (**Duration sampling data is kept**) requires approximately 15 MB of memory.

For more information about setting up health monitoring for a driver, see [Memory Requirements for Driver Health](#) in the [Driver Administration Guide](#).

6. On the **Results** tab, define the actions you want performed based on the results of the job.

Each time the job runs, it generates intermediate results and a final result. For each result, you can specify the action you want performed when it occurs. For more information, see [Understanding the Different States of a Job](#).

1. Click the **No action** link next to the result to display the Result Notification dialog box.
2. Select **Audit result** to generate an event for Novell Audit or Novell Sentinel.
or
Select **Send email**, then fill in the recipient and email template information.
3. Click **OK** to save your changes.

7. When finished configuring the job, click the **Save** icon to save your changes.
8. Select the job in the list (by selecting the check box next to the job name), then click the **Get status** icon.

The Job Status dialog box displays any configuration errors. Because the job requires rights to the driver object and those rights have not yet been granted, you see an **Insufficient rights to driver object** error.

9. Click **Grant rights**, then click **OK** to confirm the action.
10. If other errors are displayed, resolve the errors. Otherwise, click **OK** to close the Job Status dialog box.

1.3.6. Configuring the Password Expiration Notification Job

The Password Expiration Notification job searches an LDAP directory for objects whose passwords expire in a specified number of days. When an object that meets the criteria is discovered, the job sends an email to the address contained in the object's mail LDAP attribute.

1. Make sure you've already added the job to the driver set. See [Adding a Predefined Job](#).
2. On the **General** tab in OpenText Identity Console (under **Advanced > Jobs**), configure the following options:

Enable job: Leave this option selected unless you don't want the job to run.

Delete the job after the first run: Select this option if you want the job to run only once and then be deleted.

Select the server(s) this job should run on: Select the servers where you want the job to run. Multiple servers are available only if the driver is running on multiple servers.

Email server: To monitor the job, you (or others) can receive email notifications whenever certain results occur for the job. You configure email notification on the Results page. To enable this email notification, you must first specify the email server. Click the search button to locate and select the **Default Notification Collection** object or any other **notfTemplateCollection** object that defines an SMTP mail server. To send notifications, the job reads the target mail server and authentication credentials (except the password, which is specified in the **Email server password** field) from the selected **Default Notification Collection** object.

Email server password: Set the password for your email server account.



Note

If you do not specify a password, one of the following conditions will apply depending on the authentication method used by the mail server:

- For basic authentication, the job reads the email server password from **named passwords** using the `direxml.engine.smtp` key, which is stored at the active driverset level.
- For modern authentication, the client secret is used instead of email server password. In this case, the job reads the client secret from **named passwords** using the `dirxml.engine.smtp.clientsecret` key, which is also stored in the active driverset level.

Display name: Displays the name assigned to the job.

Description: Displays the description assigned to the job.

3. On the **Schedule** tab, specify when you want the job to run:

Toggle to schedule job: Runs the job on a daily, weekly, monthly, or yearly schedule. You can also specify a custom schedule; use the crontab standard when specifying a custom schedule. The default schedule checks every minute to see if the job is running. If the job is not running, it is started.

Toggle to run job manually: Runs the job only when you initiate it through the **Run Now** option (see [Starting a Job](#)).

4. Ignore the **Scope** tab, it does not apply to this job.

5. On the **Parameters** tab, fill in the following fields:

LDAP Connection: Specify the following details to connect to the LDAP directory:

- **LDAP Host:** Specify the IP address or DNS name of the LDAP server.
- **Use SSL/TLS:** Select **True** if the LDAP connection is secured with SSL/TLS, then set the following options:
 - **LDAP Port:** Specify the port number that LDAP uses to make a connection. If **Use SSL/TLS** is set to False, the default value is 389. If

Use SSL/TLS is set to True, the default value is 636.

- **SSL/TLS Provider:** Specify whether the SSL/TLS provider is Novell Secure Transport Layer (NTLS) or Java Secure Socket Extension (JSSE). If you select NTLS, you must provide the name of a KMO object to create the secure connection. If you select JSSE, you must provide a keystore pair of certificates to create the secure connection.
- **LDAP Authentication Type:** Select whether the LDAP connection is an anonymous connection or an authenticated connection. If you select **Authenticated**, you must provide the username and password of the object that authenticates to the Identity Vault.

LDAP Search: Use the following fields to specify the information used when sending the expiration notification email to users:

- **Days Until Password expires:** Specify the days before the password expires, when the job sends an email to users informing them that their password is expiring. By default, the job sends an email to the users 30 days, 15 days, 5 days, and 1 day before their passwords expire.
- **Search Base:** Specify the DN of the container where the job search occurs. The default value for the Resource Kit is ou=users,o=company,dc=data.
- **Object Class:** Specify the LDAP object class to search. The default is inetOrgPerson.

Notification Email: Use the following fields to specify the information used to create the expiration notification email, the recipients of the email, and other email settings.

- **Notification Email Template:** Specify the name of the template used to create the expiration notification email. The default is the Password Expiration Notification template in the Default Notification Collection object.
- **User Name Attribute:** Specify the LDAP attribute used to add the username to the notification template.
- **From:** Specify the email address used to populate the email's From field.
- **Show Advanced Options:** Select True to display the advanced options, or select False to hide the advanced options. The advanced options are:
 - **Reply to:** Specify the email address that appears in the Reply to field.

- Admin BCC: Specify an administrator to blind copy on the notification email.
- Character encoding: Specify the desired character encoding.
- Custom SMTP headers: Specify a custom SMTP header if desired.

6. On the **Results** tab, define the actions you want performed based on the results for the job.

Each time the job runs, it generates intermediate results and a final result. For each result, you can specify the action you want performed when it occurs. For more information, see [Understanding the Different States of a Job](#).

1. Click the **No action** link next to the result to display the Result Notification dialog box.
2. Select **Audit result** to generate an event for Novell Audit or Novell Sentinel.
or
Select **Send email**, then fill in the recipient and email template information.
3. Click **OK** to save your changes.

7. Click **Save**.

8. Select the job in the list (by selecting the check box next to the job name), then click the **Get status** icon.

The Job Status dialog box displays any configuration errors. Because the job requires rights to the driver object and those rights have not yet been granted, you see an **Insufficient rights to driver object** error.

9. Click **Grant rights**, then click **OK** to confirm the action.
10. If other errors are displayed, resolve the errors. Otherwise, click **OK** to close the Job Status dialog box.

1.3.7. Modifying the Association Statistics Job Configuration

The Association Statistics job runs on a daily, weekly, monthly, or yearly basis.

1. On the **General** page in OpenText Identity Console (under **Advanced > Jobs**), configure the following options:

Enable job: Leave this option selected unless you do not want the job to run.

Delete the job after the first run: Select this option if you want the job to run one time only and then be deleted.

Select the server(s) this job should run on: Select the servers where you want the job to run. Multiple servers are available only if the driver is running on multiple servers.

Email server: To monitor the job, you (or others) can receive email notifications whenever certain results occur for the job. You configure email notification on the **Results** page. However, to enable the email notification, you must specify the email server that will be used to send the notifications. Click the search button to locate and select the `Default Notification Collection` object or any other `notfTemplateCollection` object that defines an SMTP mail server. To send notifications, the job reads the target mail server and authentication credentials (except the password, which is specified in the **Email server password** field) from the selected `Default Notification Collection` object.

Email server password: Set the password for your email server account.



Note

If you do not specify a password, one of the following conditions will apply, depending on the authentication method used by the mail server:

- For basic authentication, the job reads the email server password from **named passwords** using the `direxml.engine.smtp` key, which is stored at the active driverset level.
- For modern authentication, the client secret is used instead of email server password. In this case, the job reads the client secret from **named passwords** using the `dirxml.engine.smtp.clientsecret` key, which is also stored in the active driverset level.

Display name: Displays the name assigned to the job.

Description: Displays the description assigned to the job.

2. On the **Schedule** tab, specify when you want the job to run:

Toggle to schedule job: Runs the job on a daily, weekly, monthly, or yearly schedule. You can also specify a custom schedule; use the crontab standard when specifying a custom schedule. By default, the job is checked every week to see if it is running. If the job is not running, it is started.

Toggle to run job manually: Runs the job only when you initiate it through the **Run Now** option (see [Starting a Job](#)).

3. Ignore the **Scope** tab, it does not apply to this job.

4. On the **Parameters** tab, perform the following actions:

Count no-reference associations: To calculate the no-reference associations, select `true`. By default, the value is set to `false`, which allows the association statistics job to calculate only reference-based associations.



Important

To obtain the no-reference associations, add the **StatisticsJob** object (created under the driverset) as a trustee of the data container (where the associated objects reside). You need to have default set of rights. For example, *All Attribute* rights should have *Compare and Read* rights and *Entry* rights should have *Browse* rights.

Persist Result DN's: To export and view the identities, select **true**. If you select **false**, the identities are not exported and a message is displayed stating that Results discarded due to configuration settings. Enable "Persist Result DN's" in StatisticsJob parameters and recompute to view DN's.

Specify System Objects: This list contains objects which are considered for system class.

5. On the **Results** tab, define the actions you want to be performed based on the results for the job.

Each time the job runs, it generates intermediate results and a final result. For each result, you can specify the action you want performed when it occurs. For more information, see [Understanding the Different States of a Job](#).

1. Click **No action** next to the result to display **Result Notification**.
2. Select **Audit result** if you want to generate an event for Novell Audit or Novell Sentinel.
or
Select **Send email**, then fill in the recipient and email template information.
3. Click **OK** to save your changes.

6. When you have finished configuring the job, click the **Save** icon to save your changes.
7. Select the job in the list (by selecting the check box next to the job name), then click the **Get status** icon.

The Job Status dialog box displays any configuration errors.

8. Click **Grant rights**, then click **OK** to confirm the action.

9. If other errors are displayed, resolve the errors. Otherwise, click **OK** to close the **Job Status** dialog box.


1.4. Creating a Custom Job

You can create a custom job to perform a task one or more times. The following sections provide the concepts and instructions required to create a custom job:

- [Job Components](#)
- [Creating the Job Definition and Job Implementation](#)
- [Adding the Job](#)

1.4.1. Job Components

The following diagram identifies the principal components required to process a job:



High-level view of Job Scheduler process

Job Manager: The Job Manager is responsible for launching scheduled jobs. It runs in the background on each OpenText Identity Manager server and checks every minute to see if a job is scheduled to run. When it encounters a scheduled job, it runs the appropriate Job Implementation.

Job Object: The Job object contains all the information necessary to invoke the job. It includes the name, description, schedule, server list, and XML job definition. The Job object is created in the Identity Vault when you use OpenText Identity Manager or Designer to add the job to a driver set or driver.

Job Definition: The Job Definition is an XML description of all the parameters necessary to perform a specific job, including the Job Implementation used to actually run the job. The Job Definition is an XML attribute associated with the Job object.

Job Implementation: The Job Implementation file is typically a JAR file that contains the Java classes that perform the job. Each OpenText Identity Manager server where you want a job to run must have a copy of the Job Implementation file. The Job Manager runs the Job Implementation at the times scheduled in the Job Definition.

1.4.2. Creating the Job Definition and Job Implementation

The Job Definition is an XML that defines the parameters required to perform a job. This includes the schedule, scope, notification parameters, and the path to the Job Implementation file. To create the XML, see Jobs DTD in the [DTD documentation](#) page.

The Job Implementation is a JAR file that contains Java classes required to perform a job. Instructions for creating the Job Implementation are not provided. The only requirement is that the Java classes run in the OpenText Identity Manager server's Java Runtime Environment. For more information, see [Javadocs for the job interface](#).

1.4.3. Adding the Job

The following steps provide instructions for using OpenText Identity Console to add a custom job. For information about using Designer to add a job, see [Scheduling Jobs](#) in the [Designer Administration Guide](#).

1. Click the **IDM Administration** tab from the home screen.
2. (Conditional) If you want to add the job to a driverset:
 1. Click the **Action menu** icon on the appropriate driver set and select **Driver Set Properties**.
 2. Click **Advanced > Jobs**.
 3. Click the **Create a new job** icon.
3. (Conditional) If you are adding the job to a driver:
 1. Click the driver to display the driver properties page.
 2. Click **Advanced > Jobs**.
 3. Click the **Create a new job** icon.
4. In **Job Name**, specify a descriptive name for the job.
5. Under **Job Type**, select **Custom**, then specify the copied Job Definition's XML.
6. In **Server(s) to run this job**, select the servers where you want to run the job.
7. Click **Create**.
8. Under **Advanced > Jobs**, select the newly created job name to display its configuration properties.
9. Provide the General, Schedule, Scope, Parameters, and Results information required for the Job Definition.
10. Click **Save**.
11. Select the job in the list and click **Get Status**.
12. If errors are displayed, resolve the errors. Otherwise, click **OK**.

1.5. Starting a Job

You can start a job by establishing a run schedule or manually starting the job. The following steps explain how to use OpenText Identity Console to manually start a job.

For information about creating a schedule to run a job, see [Adding a Predefined Job](#).

For information about using Designer to start a job, see [Scheduling Jobs](#) in the [Designer Administration Guide](#).

1. Click the **IDM Administration** tab from the home screen.
2. (Conditional) If you want to start the job for a driverset:
 1. Click the **Action menu** icon on the appropriate driver set and select **Driver Set Properties**.
 2. Click **Advanced > Jobs**.
3. (Conditional) To start a job for a driver:
 1. Click the driver to display the driver properties page.
 2. Click **Advanced > Jobs**.
4. Select the job you want to start and click **Start the selected job**.

1.6. Stopping a Job

You can stop a running job. The job stops immediately without completing its task.

The following steps provide instructions for stopping a job using OpenText Identity Console. For information about stopping a job using Designer, see [Scheduling Jobs](#) in the [Designer Administration Guide](#).

1. Click **the IDM Administration** tab from the home screen.
2. (Conditional) If you want to stop the job for a driverset:
 1. Click the **Action menu** icon on the appropriate driver set and select **Driver Set Properties**.
 2. Click **Advanced > Jobs**.
3. (Conditional) If you want to stop the job for a driver:
 1. Click the driver to display the driver properties page.
 2. Click **Advanced > Jobs**.
4. Select the job you want to stop and click **Stop the selected job**.
5. Click **OK**.

1.7. Disabling a Job

You can disable a job so that it does not run until it is enabled again.

The following steps provide instructions for using OpenText Identity Console to disable a job. For information about disabling a job using Designer, see [Scheduling Jobs](#) in the [Designer Administration Guide](#)

1. Click the **IDM Administration** tab from the home screen.
2. (Conditional) If you want to disable the job for a driverset:
 1. Click **Action menu** on the appropriate driver set and select **Driver Set Properties**.
 2. Click **Advanced > Jobs**.
3. (Conditional) If you want to disable the job for a driver:
 1. Click the driver to display the driver properties page.
 2. Click **Advanced > Jobs**.
4. Select the job you want to disable and click **Disable the selected job**.

1.8. Checking a Job's Status

You can ensure that a job is configured correctly by checking its status. If it is not configured correctly, the status provides error messages instructing you on what needs to be done for the job to run properly.

The following steps provide instructions for using OpenText Identity Console to check a job's status. For information about checking the status of a job using Designer, see [Scheduling Jobs](#) in the [Designer Administration Guide](#).

1. Click the **IDM Administration** tab from the home screen.
2. (Conditional) If you want to check the job status for a driverset:
 1. Click **Action menu** on the appropriate driver set and select **Driver Set Properties**.
 2. Click **Advanced > Jobs**.
3. (Conditional) If you want to check the job status for a driver:
 1. Click the driver to display the driver properties page.
 2. Click **Advanced > Jobs**.
4. Select the job you want to check and click **Get status**.
5. Click **OK** when you have finished reviewing any errors.

1.9. Deleting a Job

You can configure a job to run once and then be deleted, or delete it manually. The following steps provide instructions for manually deleting a job in OpenText Identity Console.

For information about configuring a job to run once and then be deleted, see [Configuring the Properties of Predefined Jobs](#).

For information about deleting a job in Designer, see [Scheduling Jobs](#) in the [Designer Administration Guide](#).

1. Click the **IDM Administration** tab from the home screen.
2. (Conditional) If you want to delete the job for a driverset:
 1. Click **Action menu** on the appropriate driver set and select **Driver Set Properties**.
 2. Click **Advanced > Jobs**.
3. (Conditional) If you want to delete the job for a driver:
 1. Click the driver to display the driver properties page.
 2. Click **Advanced > Jobs**.
4. Select the job you want to delete and click **Delete the selected job**.
5. Select the job you want to delete and click **Delete**.
6. Click **OK** to confirm the deletion.

Sometimes a deleted job continues to run if it is not stopped before being deleted.

To delete an already running job:

1. Stop the job.
2. Delete the job.

If you don't stop the job before deleting it, it continues to run.



© Copyright 2026 Open Text

For more info, visit <https://docs.microfocus.com>
