man7.org > Linux > man-pages

NAME | SYNOPSIS | DESCRIPTION | RETURN VALUE | ERRORS | CONFORMING TO | NOTES | EXAMPLE | SEE ALSO | COLOPHON

Search online pages

CONNECT(2)

Linux Programmer's Manual

CONNECT(2)

NAME

top

connect - initiate a connection on a socket

SYNOPSIS

```
top
```

```
#include <sys/types.h> /* See NOTES */
#include <sys/socket.h>
```

DESCRIPTION

top

The **connect**() system call connects the socket referred to by the file descriptor *sockfd* to the address specified by *addr*. The *addrlen* argument specifies the size of *addr*. The format of the address in *addr* is determined by the address space of the socket *sockfd*; see socket(2) for further details.

If the socket *sockfd* is of type **SOCK_DGRAM**, then *addr* is the address to which datagrams are sent by default, and the only address from which datagrams are received. If the socket is of type **SOCK_STREAM** or **SOCK_SEQPACKET**, this call attempts to make a connection to the socket that is bound to the address specified by *addr*.

Generally, connection-based protocol sockets may successfully connect() only once; connectionless protocol sockets may use connect() multiple times to change their association. Connectionless sockets may dissolve the association by connecting to an address with the sa_family member of sockaddr set to AF_UNSPEC (supported on Linux since kernel 2.2).

RETURN VALUE top

If the connection or binding succeeds, zero is returned. On error, -1 is returned, and *errno* is set appropriately.

ERRORS top

The following are general socket errors only. There may be other domain-specific error codes.

EACCES For UNIX domain sockets, which are identified by pathname:

Write permission is denied on the socket file, or search permission is denied for one of the directories in the path prefix. (See also path resolution(7).)

EACCES, EPERM

The user tried to connect to a broadcast address without having the socket broadcast flag enabled or the connection request failed because of a local firewall rule.

EADDRINUSE

Local address is already in use.

EADDRNOTAVAIL

(Internet domain sockets) The socket referred to by <code>sockfd</code> had not previously been bound to an address and, upon attempting to bind it to an ephemeral port, it was determined that all port numbers in the ephemeral port range are currently in use. See the discussion of <code>/proc/sys/net/ipv4/ip_local_port_range</code> in <code>ip(7)</code>.

EAFNOSUPPORT

The passed address didn't have the correct address family in its sa family field.

EAGAIN For nonblocking UNIX domain sockets, the socket is nonblocking, and the connection cannot be completed immediately. For other socket families, there are insufficient entries in the routing cache.

EALREADY

The socket is nonblocking and a previous connection attempt has not yet been completed.

EBADF sockfd is not a valid open file descriptor.

ECONNREFUSED

A **connect**() on a stream socket found no one listening on the remote address.

EFAULT The socket structure address is outside the user's address space.

EINPROGRESS

The socket is nonblocking and the connection cannot be completed immediately. (UNIX domain sockets failed with EAGAIN instead.) It is possible to select(2) or poll(2) for completion by selecting the socket for writing. After select(2) indicates writability, use getsockopt(2) to read the SO_ERROR option at level SOL_SOCKET to determine whether connect() completed successfully (SO_ERROR is zero) or unsuccessfully (SO_ERROR is one of the usual error codes listed here, explaining the reason for the failure).

EINTR The system call was interrupted by a signal that was caught; see signal(7).

EISCONN

The socket is already connected.

ENETUNREACH

Network is unreachable.

ENOTSOCK

The file descriptor sockfd does not refer to a socket.

EPROTOTYPE

The socket type does not support the requested communications protocol. This error can occur, for example, on an attempt to connect a UNIX domain datagram socket to a stream socket.

ETIMEDOUT

Timeout while attempting connection. The server may be too busy to accept new connections. Note that for IP sockets the timeout may be very long when syncookies are enabled on the server.

CONFORMING TO

top

POSIX.1-2001, POSIX.1-2008, SVr4, 4.4BSD, (connect() first appeared in 4.2BSD).

NOTES top

POSIX.1 does not require the inclusion of <sys/types.h>, and this header file is not required on Linux. However, some historical (BSD) implementations required this header file, and portable applications are probably wise to include it.

For background on the *socklen_t* type, see accept(2).

If **connect**() fails, consider the state of the socket as unspecified. Portable applications should close the socket and create a new one for reconnecting.

EXAMPLE top

An example of the use of **connect**() is shown in getaddrinfo(3).

SEE ALSO to

```
accept(2), bind(2), getsockname(2), listen(2), socket(2),
path resolution(7)
```

COLOPHON top

This page is part of release 5.00 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at

Linux 2019-03-06 CONNECT(2)

Pages that refer to this page: pmsocks(1), telnet-probe(1), accept(2), bind(2), getpeername(2), listen(2), recv(2), select(2), select_tut(2), shutdown(2), socket(2), socket(all(2), syscalls(2), write(2), getaddrinfo(3), ldap_get_option(3), rtime(3), slapd-asyncmeta(5), slapd-ldap(5), slapd-meta(5), ddp(7), ip(7), netlink(7), packet(7), sctp(7), signal(7), signal-safety(7), sock_diag(7), socket(7), tcp(7), udp(7), unix(7), vsock(7)

Copyright and license for this manual page

HTML rendering created 2019-03-06 by Michael Kerrisk, author of *The Linux Programming Interface*, maintainer of the Linux *man-pages* project.

For details of in-depth Linux/UNIX system programming training courses that I teach, look here.

Hosting by jambit GmbH.



