

ChillWithSyd

SERVER MANAGER

Instruction Manual

Soulmask Dedicated Server for Windows

Node.js Web Interface — Port 3000

Installation

ChillWithSyd comes with two installers — one for Windows and one for Linux. Both are distributed as a zip file containing the installer alongside the application files. The installer copies everything into your chosen location and sets up shortcuts and autostart.

WARNING: Place all files from the distribution zip in the same folder before running the installer. The installer looks for server.js, index.html, and the manual PDF alongside itself.

What You Need Before Installing

Node.js	Required on both platforms. The installer checks for it and prompts to install if missing. Download from https://nodejs.org/en/download — use the LTS version.
Windows version	Windows 10 or 11, 64-bit. Administrator rights required for installation.
Linux version	Any modern Linux distribution with systemd (Ubuntu 20.04+, Debian 11+, Fedora, Arch). sudo recommended for system install.
Disk space	Approximately 5 MB for the manager files. Your Soulmask server files are separate (~10 GB) and not affected by this installer.

Windows Installation

Run ChillWithSyd-Setup-v1.1-Windows.exe. You may see a Windows SmartScreen warning — click More info then Run anyway. This happens because the installer is not code-signed.

1. Double-click ChillWithSyd-Setup-v1.1-Windows.exe
2. Click Next on the Welcome screen
3. Read and accept the licence
4. Set the manager port — default is 3000. Change this if another application already uses port 3000 on your machine.
5. Choose your install folder — default is C:\Program Files\ChillWithSyd
6. Tick "Start ChillWithSyd automatically when Windows starts" if this PC is a dedicated server host. This ensures the manager restarts automatically after a reboot.
7. Click Install
8. If Node.js is not detected, a prompt appears — click Yes to open the download page, install Node.js LTS, then run start.bat from the install folder
9. Optionally tick "Launch ChillWithSyd now" on the final screen

NOTE: Node.js runs completely invisibly — no CMD window or DOS box will appear. The manager runs silently in the background. You can confirm it is running by opening Task Manager and looking for node.exe in the process list.

What the Windows Installer Creates

Install folder	server.js, index.html, start.bat, stop.bat, manual PDF, config.env, backups\
Desktop shortcut	ChillWithSyd.lnk — double-click to launch
Start Menu	ChillWithSyd folder with launch, stop, manual and uninstall shortcuts

config.env	Contains CWS_PORT=3000 (or your chosen port). Edit this to change the port later.
.pid file	Written by start.bat when Node starts. Contains the process ID. Used by stop.bat to kill the right process cleanly.
Windows autostart	If ticked: registered in Windows Run key so the manager starts on boot with no window.
Add/Remove Programs	Uninstaller registered — use this to remove ChillWithSyd cleanly
NOTE: The uninstaller removes app files only. Your servers.json and backups folder are never deleted. They remain in the install folder after uninstalling.	

Upgrading on Windows

Run the new installer over the existing installation. It detects the previous install automatically via the registry and reads your current port from config.env — the port field in the wizard is pre-filled with your existing value so you do not need to remember it.

Only app files are replaced: server.js, index.html, start.bat, stop.bat, and the manual PDF. servers.json, backups, and config.env are never touched.

WARNING: Stop the manager (run stop.bat) before running the installer. The installer does not stop it automatically.

Linux Installation

Run the bash installer script from a terminal. It guides you through each step interactively with coloured output.

1. Open a terminal in the folder containing the installer files
2. Make the script executable: `chmod +x ChillWithSyd-Setup-v1.1-Linux.sh`
3. Run it: `bash ChillWithSyd-Setup-v1.1-Linux.sh`
4. Choose install location — `/opt/chillwithsyd` (recommended, requires sudo) or `~/chillwithsyd` (no sudo needed)
5. Enter manager port — default 3000
6. If Node.js is missing or too old, the installer attempts to install it via apt, dnf, or pacman automatically
7. The installer sets up a systemd service and asks if you want to start now

What the Linux Installer Creates

Install folder	server.js, index.html, start.sh, stop.sh, manual PDF, config.env, backups/
config.env	Contains CWS_PORT=3000 (or your chosen port)
systemd service	/etc/systemd/system/chillwithsyd.service — starts on boot, restarts on crash
Helper command	/usr/local/bin/chillwithsyd — run chillwithsyd start/stop/status/log from anywhere

Linux systemd Commands

chillwithsyd start	Start the manager
---------------------------	-------------------

chillwithsyd stop	Stop the manager
chillwithsyd status	Show whether the manager is running
chillwithsyd log	Stream live logs from the manager process
sudo systemctl enable chillwithsyd	Enable autostart on boot (done by installer)
sudo systemctl disable chillwithsyd	Disable autostart on boot
journalctl -u chillwithsyd -f	Follow manager logs directly via systemd journal

Upgrading on Linux

Run the new installer over the existing installation. It detects the existing install, warns you, and asks to confirm before proceeding. Only app files are replaced — `servers.json`, `backups`, and `config.env` are untouched. The `systemd` service is reloaded automatically.

Importing an Existing Server

If you already have a Soulmask server installed and want to manage it with ChillWithSyd, use the import feature rather than setting up a new config from scratch.

1. Open ChillWithSyd in your browser
2. Click + Add / Import in the server tab bar at the top
3. Paste the full path to your existing Soulmask Dedicated Server folder
4. Click OK — the manager scans the folder automatically

The import process detects:

- The server executable location
- Which map is installed (Cloud Mist Forest or Shifting Sands) by checking the save folder
- The server name from `StartServer.bat` if present
- Whether `world.db` exists and its size

All detected settings are pre-filled in Configuration. Ports are auto-assigned to avoid conflicts with any existing servers. The import is non-destructive — your server files, saves, and settings are not modified in any way.

NOTE: After importing, check Configuration to verify the server name, password, and any other settings you want to set before starting.

Changing the Manager Port After Install

The manager port is stored in `config.env` in the install folder. To change it:

- Open `config.env` in a text editor
- Change `CWS_PORT=3000` to your preferred port number
- Save the file
- Restart the manager (run `stop.bat` then `start.bat` on Windows, or `sudo systemctl restart chillwithsyd` on Linux)
- Update your browser bookmark to the new port

Accessing the Manager

Once running, open any browser and go to <http://localhost:3000> (or your chosen port). The  Manual button in the top-right of the panel opens this PDF directly in your browser.

NOTE: If you cannot reach the panel, check that `start.bat` ran successfully (Windows) or that the `systemd` service is active (Linux). See the Troubleshooting chapter for common issues.

Overview

ChillWithSyd is a browser-based management panel for your Soulmask dedicated server. It runs locally as a Node.js process and gives you full control over the server without touching the command line.

Open any browser and go to <http://localhost:3000> to access the panel.

Server Executable	WSServer-Win64-Shipping.exe
Default Game Port	8777 (UDP)
Query Port	27015 (UDP)
EchoPort (Telnet)	18888 (TCP)
SteamAppId	2646460
Manager URL	http://localhost:3000
Save Location	WS\Saved\Worlds\Dedicated\DLC_Level01_Main\
Settings File	WS\Saved\GameplaySettings\GameXishu.json

Getting Started

First Launch

Double-click `start.bat` to launch the manager. A browser tab opens automatically at <http://localhost:3000>.

WARNING: The manager must stay running in the background. Do not close the terminal window while the server is active.

Installing the Server

If you have not yet downloaded the Soulmask dedicated server files, open the Installer tab. The manager will download SteamCMD and the server files (approximately 10 GB).

Starting and Stopping

1. Go to the Dashboard tab
2. Click Start to launch the server
3. Wait for the ONLINE status indicator
4. To stop: click Stop & Save and wait for the green confirmation in Server Logs

IMPORTANT: ALWAYS use Stop & Save. Never force-close the server window — this skips the world save.

Dashboard

The Dashboard gives an at-a-glance view of server health, updated every 3 seconds.

Control Buttons

Start	Launch the server. Runs Steam update check first if configured.
Stop & Save	Sends SaveWorld + shutdown — world saves before the process exits.
Restart	Stop & Save followed by Start.
Save World	Sends a save command without stopping.
Start (skip update)	Start immediately, bypassing the Steam update check.

Other Cards

Next Disk Save bar	Progress bar showing time until the next -backup disk write (default every 5 min).
World Save card	Shows world.db size, time since last save, and auto-save count.
Schedules card	Next scheduled backup and/or restart times. Click Configure to set up.
Server Info	Map, port, cluster role, and active mods.

Configuration

Server Settings

Server Install Path	Full path to the Soulmask Dedicated Server folder.
Server Name	Name shown in the Steam server browser.
Map	Cloud Mist Forest (Level01_Main) or Shifting Sands DLC (DLC_Level01_Main).
Game Port (-PORT)	UDP port for player connections. Default 8777.
Save to Memory (-saving)	RAM snapshot interval. Default 600s. Do not go below 300s.
Save to Disk (-backup)	Disk write interval. Default 300s. Use quick-set dropdown to change.
Server ID	Auto-generated from server name. NEVER change after players join.
Check updates on start	Runs a Steam update check before starting. Adds ~10-30s.

Schedules

Scheduled Backups	Full WS\Saved snapshot. Choose interval (1h–24h) and how many to keep.
--------------------------	--

Daily Restart	Automatic save and restart at a set time each day (recommended: 04:00).
Weekly Restart	Automatic save and restart on a chosen day and time.
Warn before restart	How many minutes notice to log before a scheduled restart (1–30).
Auto-save retention	How many auto-save .db files to keep. At 5 min intervals, 20 = ~100 min rollback.

Server Cluster

Role: Standalone	No cluster — single server only.
Role: Main server	Manages player accounts for the cluster. Start this first, stop last.
Role: Client server	Hosts the second map. Connects to main via broadcast port.
Broadcast Port	Internal TCP port the client uses to connect to main (default 20000). Do not expose publicly.
Main Server IP:Port	For client servers — IP and port of the main server (e.g. 127.0.0.1:20000).

WARNING: KaiQiKuaFu must be 1 (ON) in Gameplay Tuning on both servers for cross-server travel to work. Same password on both servers. Start main first, stop main last.

Steam Workshop Mods

Adding a mod	Paste the Workshop URL or numeric ID. The manager extracts the ID automatically. Click + Add then Save Configuration and restart.
Removing a mod	Click X next to the mod, Save Configuration, restart. Players may see a mismatch warning but can still connect.
Launch argument	Mods load via use(-mod="id1,id2,id3") at startup and auto-download.
Safe to change?	Yes — add or remove anytime when server is stopped. See Mods chapter for caveats about content mods.

Gameplay Tuning

The Gameplay Tuning page provides a visual interface for all 206 server multipliers in GameXishu.json. No JSON editing required.

IMPORTANT: Always stop the server before saving tuning changes. The server overwrites the file with its in-memory values on shutdown.

Workflow

1. Stop the server
2. Click "Load from game files" to read current settings
3. Adjust sliders across the tabs
4. Click "Save to file"
5. Start the server

Tab Guide

XP & Progression	Experience rates, level cap, attribute point multipliers.
Resources	Gathering, mining, logging, crafting output and speeds.
Combat	Damage multipliers — animals, marauders, buildings, stamina.
Survival	Food/water consumption, stamina, item decay, repair costs.
Tribe & Animals	Recruitment limits, taming speed, tribesman mood and upkeep.
World	Day/night cycle, fire speed, portals, building limits, events.
PvP / Raid	PvP damage ratios, raid time windows, invasion settings.
Death & Loot	Keep items on death, corpse bag, chest drop rates.
Marauders	NPC damage, quality and attribute scaling.
Invasions	Invasion timing, scale, monster count, warning period.
Raw JSON	Direct text editor for GameXishu.json.
Diagnose	Checks which file is active and current values.

Your Current Server Values (selected)

ExpRatio	2 (double XP from all sources)
ShaGuaiExpRatio	3 (3x XP from kills)
CaiJiDiaoLuoRatio	3 (3x gathering yield)
ShiWuXiaoHaoRatio	0.5 (eat half as often)
DongWuShengZhangRatio	2 (animals grow twice as fast)
RanLiaoXiaoHaoRatio	0.1 (fuel lasts 10x longer)
ZhiZuoTimeRatio	0.5 (crafting takes half the time)

RoleBagCapacity	100 (100 inventory slots)
MaxFuZhongRatio	30 (30x carry weight)
PlayerDeathCantDropItemKaiGuan	ON (keep items on death)
BinSiKaiGuan	OFF (near-death system disabled)
GongJiJianZhuDamageRatio	0 (buildings indestructible)
KaiQiKuaFu	1 (cluster mode ON)
ReDuXiShu	0.6 (invasion fever slower to build)

Backup and Recovery

Save Types

Auto-save (game)	Created by the server every -backup seconds. Named auto_SERVERID_TIMESTAMP.db. Only created when players are active.
Manual backup	Full WS\Saved folder snapshot. Click Manual Backup to create.
Scheduled backup	Full WS\Saved snapshot on your schedule (every 1–24h).
Pre-restore	Automatic safety copy created before any restore operation.

Restoring a Save

1. Stop the server
2. Open Backup & Recovery
3. Find the entry (use filter buttons to narrow down)
4. Click Restore and confirm
5. Start the server

NOTE: A safety backup of your current state is always created before restoring. After a power cut, the most recent auto-save contains everything up to the last -backup write (max 5 minutes lost).

Steam Workshop Mods

Soulmask has official Steam Workshop mod support. Mods are added via Configuration and auto-download when the server starts. Players are prompted to subscribe when they connect.

WARNING: Always create a manual backup before adding or removing any mod.

Adding Mods

1. Stop the server
2. Go to Configuration → Steam Workshop Mods

3. Paste the Workshop URL or mod ID (e.g. 3324057706). The manager extracts the ID from URLs automatically.
4. Add a friendly name, click + Add
5. Click Save Configuration
6. Start the server — mods download automatically on first start

Removing Mods

Stop the server, click X in the mod list, Save Configuration, restart. Players may see a mismatch warning but can still connect.

What Is Safe to Add and Remove

Always safe	Visual mods, UI improvements, balance tweaks, quality-of-life mods. These do not affect saved world data.
Safe with caution	Mods that add new NPCs or enemies. Existing spawns may disappear but the world save stays intact.
Risky to remove	Mods that add craftable items, structures, or building pieces. If players have used those items, removing the mod makes them show as broken in-game. The save file stays intact but affected items become unusable.
NOTE: If removing a content mod players have used, warn them first so they can dispose of affected items. The save file itself will not corrupt.	

Mod Version Mismatches

"Server connection has been lost" when joining usually means the mod version on the server does not match the player's. Restart the server to re-download the latest version, and ask players to update their Workshop subscription.

Server Clustering

A cluster links two servers so players can move characters between Cloud Mist Forest and Shifting Sands. The main server manages all player account data. The client server hosts the second world.

WARNING: If the main server goes offline, the client server will not allow connections. Start main first, stop main last.

Your Cluster Setup

Main server	Shifting Sands (DLC_Level01_Main) — Role: Main server, Broadcast Port 20000
Client server	Cloud Mist Forest (Level01_Main) — Role: Client server, connects to 127.0.0.1:20000
KaiQiKuaFu	Must be ON (1) in Gameplay Tuning on both servers
Passwords	Must match on both servers

Startup and Shutdown Order

Starting	1. Start Shifting Sands (main) first and wait for ONLINE 2. Then start Cloud Mist Forest (client)
Stopping	1. Stop Cloud Mist Forest (client) first 2. Then stop Shifting Sands (main)

Player Transfers

Players transfer via the Mysterious Island portal while controlling a tribesman (not the initial character). Interact with the terminal, select the destination server.

NOTE: The initial character cannot transfer. Take control of a different tribesman first. You can summon your initial character at a bonfire on the other map using Remodel Initial Character.

Gameplay Tuning — Full Reference

Every slider in the Gameplay Tuning page is listed below with its range, what higher/lower values mean in practice, and your current server value where it differs from the default of 1.

WARNING: Stop the server before saving tuning changes. Changes take effect on next start.

XP and Progression

Global XP Rate	0.1–10 Yours: 2 Master XP multiplier for all sources. 2 = double XP across everything.
Growth XP Rate	0.1–10 Yours: 2 Character level-up XP. Stacks with Global XP Rate.
Kill XP Rate	0.1–10 Yours: 3 XP from killing enemies. Higher = combat levels you faster.
Gathering XP Rate	0.1–10 Yours: 3 XP from harvesting resources.
Crafting XP Rate	0.1–10 Yours: 2.8 XP from crafting items.
Proficiency XP Rate	0.1–100 Yours: 3.1 Weapon, tool and skill proficiency XP.
Mask XP Rate	0.1–100 Yours: 3.3 XP for mask upgrades and awareness.
Training XP Rate	0.1–10 Yours: 2.6 XP from training activities.
Other XP Rate	0.1–10 Yours: 2.9 Miscellaneous XP sources.
Kill XP Share	0–1 Yours: 0.5 Fraction of kill XP shared with nearby tribe members. 0.5 = 50% shared.
Max Level	1–100 Default: 60 Maximum character level cap.
Active/Passive/Secondary Attr	0.1–5 Default: 1 Multipliers for attribute points gained on level-up.

Resources and Gathering

Gathering Drop Rate	0.1–20 Yours: 3 Yield from plants, herbs and basic gathering.
Mining Drop Rate	0.1–20 Yours: 3 Ores, stones and minerals from mining.
Logging Drop Rate	1–10 Yours: 3 Wood and materials from chopping trees.
Gathering Tool Damage	0.1–10 Yours: 2 How fast tools deplete resource nodes. Higher = faster harvesting.
Resource Node HP	0.1–5 Yours: 0.5 HP of trees and rocks. Lower = easier to harvest. Your value halves node HP.
Production Building Output	0.1–10 Yours: 3 Output from automated production buildings.
Animal Corpse Drops	0.1–10 Yours: 2 Materials harvested from animal bodies.
Animal Rare Drops	0.1–10 Yours: 3 Rare drops from animal corpses.
Common NPC Drops	0.1–10 Yours: 2 Drops from regular barbarian NPCs.
Elite NPC Drops	0.1–10 Yours: 3 Drops from elite NPCs.

Boss Drops	0.1–10 Yours: 3 Drops from boss-tier NPCs.
Crop Harvest Rate	0.1–10 Yours: 3 Yield when harvesting grown crops.
Crop Growth Speed	0.1–10 Yours: 3 How fast crops mature.
Crop Rot Speed	0.1–5 Yours: 0.2 How fast crops spoil. Your value = crops last 5x longer.
Crop Water/Fertilizer Drain	0.1–5 Default: 1 Consumption rates for crop upkeep.
Fuel Consumption	0.1–5 Yours: 0.1 Fire and furnace fuel burn rate. Your value = fuel lasts 10x longer.
Crafting Time Ratio	0.1–10 Yours: 0.5 Lower = faster crafting. Your value = half the time.
Conversion Speed	0.1–20 Default: 5 Speed of item conversion in workshops.
Vegetation Respawn Speed	0.1–10 Default: 1 How quickly trees and plants regrow after harvest.

Combat

Wild Monster Damage	0–10 Yours: 0.7 Damage wild monsters deal to players. Lower = easier. Yours = 30% less.
Wild Damage Taken	0.1–10 Yours: 0.6 Damage players receive from wild creatures.
Animal Damage	0.1–10 Yours: 0.7 Damage from animals attacking players.
Animal Resistance	0–10 Yours: 0.6 Damage dealt TO animals. Lower = they die easier. Yours = easier hunting.
Marauder Damage	0.1–10 Default: 1 Damage marauder NPCs deal.
Marauder Resistance	0–10 Default: 1 Damage dealt TO marauders. Lower = die easier.
Building Damage	0–10 Yours: 0 Damage to player structures. Your value = buildings are indestructible.
Wild Animals vs Buildings	0–10 Default: 4 (yours: 1.9) Damage wild animals deal to structures.
AI Difficulty	1–3 Default: 1 1 = normal, 2 = medium, 3 = harder AI behaviour.
Dynamic Boss Scaling	Toggle Default: ON Boss stats adjust based on player count and strength.
Dodge I-Frame Duration	0.1–5 Default: 1 Invincibility window during dodge roll.
Feign Death HP Recovery	0–10 Yours: 1.5 HP recovery speed while prone in near-death state.

Survival

Food Consumption	0.1–5 Yours: 0.5 How fast players get hungry. Your value = eat half as often.
Water Consumption	0.1–5 Yours: 0.6 How fast players get thirsty.
Stamina Drain	0.1–5 Yours: 0.8 Stamina used per action. Lower = lasts longer.
HP Regen Rate	0.1–10 Yours: 2 Passive health regeneration speed.

Stamina Regen	0.1–10 Yours: 2 Passive stamina regeneration.
Durability Loss Rate	0.1–5 Yours: 0.6 How fast items lose durability. Lower = gear lasts longer.
Repair Material Cost	0–1 Yours: 0.6 Materials needed to repair. Your value = 40% cheaper.
Repair Durability Penalty	0–1 Yours: 0.5 Max durability lost per repair. Your value = half penalty.
Item Decay Rate	0.1–5 Yours: 0.1 Food and perishable decay. Your value = last 10x longer.
Death Item Despawn Time	0.1–10 Yours: 3.6 How long dropped items persist. Higher = more time to retrieve.
Max Carry Weight	1–100 Yours: 30 Multiplies carry weight. Your value = 30x default.
Backpack Slots	30–256 Yours: 100 Inventory slots. Restart required to apply.
Keep Items on Death	Toggle Yours: ON ON = full inventory kept on death.
Near-Death System	Toggle Yours: OFF OFF = disables the prone near-death state entirely.
Mood Decrease Rate	0.1–5 Yours: 0.5 How fast tribesman morale drops.
Mood Increase Rate	0.1–5 Yours: 1.4 How fast tribesman morale recovers.
Invasion Fever Rate	0.1–100 Yours: 0.6 How fast fever builds towards triggering invasions. Lower = less frequent.

Tribe and Animals

Guild Max Tribesmen	1–200 Yours: 60 Max tribesmen a guild can recruit.
Personal Max Tribesmen	1–50 Yours: 10 (base), 15 (Lv2), 21 (Lv3) Max tribesmen per player at each mask node tier.
Max Players per Tribe	1–50 Default: 20 Max players in one tribe.
Guild/Personal Max Animals	Guild 1–500 Personal 1–100 Max tamed animals owned.
Following Animals	0–20 Default: 3 How many animals can follow one player at once.
Deployed Tribesmen	1–100 Default: 3 Max tribesmen deployable in combat at once.
Taming Speed	0.1–10 Default: 1 Rate tribesman compliance increases during taming. Higher = faster.
Animal Growth Speed	0.1–10 Yours: 2 How fast young animals mature.
Animal Output Rate	0.1–10 Default: 1 Amount produced per cycle from tamed animals.
Animal Production Interval	0.1–10 Default: 1 Time between production cycles. Lower = faster.
Breeding Interval	0.1–10 Default: 1 Time between breeding cycles. Lower = faster.
Animal Food/Water Drain	0.1–5 Default: 1 How fast tamed animals consume food and water.

Animal Quality	0.1–5 Default: 1 Base quality/tier of tamed and bred animals.
Perfect Remodel	Toggle Default: OFF ON = tribesmen keep all XP and stats on revival.
Offline Hibernate Days	0–30 Default: 7 Days offline before tribesmen stop working.
Giant Elephant Limits	Tribe 1–100 Personal 1–100 Default: 1 each Max giant elephants owned.

World Settings

Day/Night Speed	1–100 Yours: 24 24 = roughly real-time day/night cycle.
Daytime Fraction	0.1–0.9 Yours: 0.65 Fraction of cycle that is daytime. 0.65 = 65% day, 35% night.
Fire Burn Speed	0.1–10 Yours: 0.1 Fire and torch fuel consumption. Your value = last 10x longer.
Building Decay	Toggle Yours: OFF OFF = buildings never decay.
Building Repair Cost	0.1–10 Yours: 0.8 Resource cost multiplier for repairing buildings.
Vegetation Respawn Speed	0.1–10 Default: 1 How fast trees, plants and resources regenerate.
Cluster Mode (KaiQiKuaFu)	Toggle Yours: ON Must be ON for cross-server cluster. OFF on standalone servers.
Two-way Portals	Toggle Default: ON Personal portals and world doors interconnect.
NPC Respawn	Toggle Default: ON ON = NPCs respawn at midnight each game day.
Dungeon Respawn	Toggle Default: ON ON = dungeon enemies respawn.
Auto-use Nearby Chests	Toggle Default: ON Crafting automatically pulls from nearby storage.
Ban Glider	Toggle Default: OFF ON = players cannot use gliders.
Building Preview Mode	Toggle Default: ON Ghost preview mode when placing building pieces.
Building Height Limit	Toggle Default: ON Enforce maximum building height.
Portal Limit	1–100 Default: 10 Max teleportation portals on the server.
Personal/Tribe Bonfire Limits	Personal 1–100 Tribe 6–100 Max bonfires per player and tribe.
Max Carry Weight	1–100 Yours: 30 Multiplies max carry weight for all players.
Backpack Slots	30–256 Yours: 100 Inventory slots per player.
Personal/Tribe Raft Slots	Personal 1–20 Tribe 1–50 Raft space slots.
Max Conveyors	1–1000 Default: 1000 Conveyor/ropeway structures per tribe.
Max Power Mines	1–100 Default: 10 Energy/power mine buildings.
Dance Cooldown	0–24h Default: 4h Cooldown between tribesman dance actions.

Tribe/Ruins/Transport Events	Toggles Default: ON Enable expedition, ruins and transport fleet events.
Platform Build Range Limit	Toggle Default: ON. ON = enforce construction range limit on ships and giant elephants.
Platform Build Count Limit	Toggle Default: ON. ON = enforce quantity cap on platform buildings. OFF = unlimited pieces on ships and elephants.
Platform Max Build Multiplier	0.1-1 Default: 0.1 YOUR VALUE: 0.1 = only 10 percent of singleplayer capacity. Set to 1 for full building limits on ships and giant elephants. This is a very commonly missed setting.

PvP and Raids

PvP Enabled	Toggle Yours: OFF Master switch for all player-to-player damage.
PvP Melee/Ranged Damage	0–1 Yours: 0.4 each Damage in PvP. Max is 1 (full damage). Yours = 40% of normal.
Invasion System	Toggle Yours: ON Enables the barbarian raid system.
Random Invasions	Toggle Yours: ON ON = random invasions can trigger unpredictably.
Invasion Scale	0.1–5 Default: 1 Size of invasions — more waves and enemies. Higher = harder.
Invasion Intensity	0.1–5 Default: 1 Enemy stat strength during invasions.
Invasion Monster Level	0.1–5 Default: 1 Level scaling of invasion monsters.
Invasion Start/End Hour	0–24 Default: 0–24 Time window when invasions can occur.
Raid Cooldown	1–14400 min Default: 1440 (24h) Minimum time between invasions.
Min/Max Invasion Monsters	1–256 Default: 8–128 Monster count range per invasion.
Invasion Burn Coefficient	0–1 Default: 0.6 How destructive fire-burning invasions are to structures.
Invasion Massacre Coefficient	0–1 Default: 0.3 How lethal massacre-type invasions are to tribesmen.
Scout Warning Duration	1–120 min Default: 20 Warning time before invasion begins.
Invasion Reward Multiplier	1–10 Default: 3 Rewards multiplier for successfully defending.
Special/Relic/Boss Events	Toggles Default: varies Special boss spawns, relic chest events, boss death events.
Bonfire Building Protection	Toggle Default: OFF Buildings in bonfire range protected from PvP damage.

Death and Loot

Keep Items on Death	Toggle Yours: ON ON = full inventory kept on death.
Near-Death System	Toggle Yours: OFF OFF = no prone near-death state or corpse spawns.

Death Bag on Respawn	Toggle Default: OFF ON = dropped items move to your respawn location.
Tribe-Only Corpse Loot	Toggle Default: ON Only your tribe members can collect your dropped items.
Chest Drop Multiplier	1–10 Default: 1 Quantity and quality of chest loot.
Chest Drop Level	0–5 Default: 0 Minimum quality tier of equipment from chests. 0 = all tiers.
Normal/Elite/Boss Drop Corrections	0–5 Yours: 1 / 1.9 / 1.6 Drop rate corrections by enemy tier.
Normal/Elite/Boss Durability	0–5 Yours: 1.2 / 1.4 / 1.8 Starting durability of dropped equipment by tier.
Perfect Remodel	Toggle Default: OFF ON = tribesmen keep all XP and stats on revival.

Marauders

Marauder Damage	0.1–10 Default: 1 Damage marauder enemies deal to players.
Marauder Resistance	0–10 Default: 1 Damage dealt TO marauders. Lower = die easier.
Marauder Quality	0.1–5 Default: 1 Marauder quality/tier. Higher = stronger enemies.
Marauder Attr Multipliers	0.1–5 Default: 1 (active, passive, secondary) Attribute scaling for marauder NPCs.

Networking and Server Visibility

For players to find and join your server over the internet you need two things: the correct server name set in ChillWithSyd, and ports forwarded on your router. Without port forwarding, the server will only appear in the Steam server list for players on the same local network.

Server Name

The Server Name in Configuration maps directly to the -SteamServerName launch flag. This is the name players see in the Steam server browser.

Where to set it	Configuration page → Server Name field → Save Configuration → Restart server
Flag passed	-SteamServerName="ChillWithSyd"
Where it appears	Steam → View → Game Servers → Internet tab, filtered by Soulmask
Finding your server	In Steam: View → Servers → Internet. Set game filter to Soulmask. Search by name.
Direct connect	Steam → View → Servers → Favourites → Add server → enter your public IP:8777

NOTE: The server name only appears in the Steam browser once port forwarding is set up correctly. Without it, the server is only visible on your local network.

Ports to Forward

Log into your router admin panel (usually <http://192.168.1.1> or <http://192.168.0.1>) and add the following port forwarding rules, pointing to the local IP address of the PC running the server:

Port 8777	UDP
Port 27015	UDP
Port 18888	TCP
Port 20000	TCP

WARNING: Only forward ports 8777 and 27015 for a standard public server. Port 18888 is optional and should be kept private if possible. Port 20000 must never be exposed publicly.

Windows Firewall

Even with router port forwarding set up, Windows Firewall may still block the traffic. You need inbound rules for the game port and query port:

1. Open Windows Defender Firewall with Advanced Security (search in Start menu)
2. Click Inbound Rules → New Rule
3. Select Port → UDP → Specific local ports: 8777, 27015
4. Select Allow the connection → apply to all profiles
5. Name it "Soulmask Server" and click Finish

Alternatively, open PowerShell as Administrator and run:

```
netsh advfirewall firewall add rule name="Soulmask Game" protocol=UDP dir=in  
localport=8777 action=allow
```

```
netsh advfirewall firewall add rule name="Soulmask Query" protocol=UDP dir=in  
localport=27015 action=allow
```

Finding Your Public IP

Players connecting over the internet need your public IP address. You can find it by searching "what is my ip" in a browser. Your public IP may change periodically if you are on a standard home connection — if this becomes a problem, look into a free DDNS service such as No-IP or DuckDNS which give you a fixed hostname that updates automatically.

Public IP	What players type to connect directly. Changes on router restart with most home ISPs.
Local IP	Used for players on the same home network (e.g. 192.168.1.x). Find it with ipconfig in Command Prompt.
DDNS hostname	A free service that gives you a fixed address like myserver.ddns.net even when your IP changes.
Direct connect	Steam → View → Servers → Favourites → Add a Server → enter IP:port (e.g. 203.0.113.1:8777)

Two Servers (Cluster) Port Setup

If running both Shifting Sands and Cloud Mist Forest as a cluster on the same machine, each server needs its own unique set of ports:

Shifting Sands (main)	Game: 8777 UDP — Query: 27015 UDP — Echo: 18888 TCP
Cloud Mist Forest (client)	Game: 8778 UDP — Query: 27016 UDP — Echo: 18889 TCP
Cluster broadcast	20000 TCP — internal only, do NOT forward on router

Forward all four public ports (8777, 8778, 27015, 27016) on your router. Players choose which map to connect to by selecting the appropriate server in the browser, or connecting directly to the correct port.

WARNING: Make sure both servers have unique port numbers in Configuration before starting them simultaneously. Duplicate ports will cause one server to fail to start.

Checking the Server is Visible

After starting the server with ports forwarded and firewall rules in place:

- Open Steam → View → Servers → Internet tab
- Filter by game: Soulmask
- Search for your server name
- If it does not appear, try the Favourites tab → Add a Server → enter your public IP:8777
- The server should respond with your name, player count, and ping

If the server still does not appear, check: port forwarding rules point to the correct local IP of the server PC, Windows Firewall inbound rules exist for UDP 8777 and 27015, and the server shows ONLINE in ChillWithSyd.

IP Address Privacy and Risks

When you run a game server from home and players connect to it, your home public IP address is exposed to every player who joins. This is an unavoidable fact of how TCP/IP networking works — players need your IP to connect. However, there are real risks to be aware of and practical ways to reduce your exposure.

What the Risks Actually Are

DDoS attacks	A player who dislikes your server can flood your IP with traffic, overwhelming your router and cutting off your internet connection. This is the most common real-world threat for home game servers.
Doxxing	Your public IP can be used to identify your approximate geographic location (city-level, rarely street-level). Combined with other information, bad actors have used this to find personal details about server owners.
Port scanning	Once someone knows your IP, they can probe other ports on your home network to find other services. Good firewall rules mitigate this significantly.
ISP terms of service	Some residential ISPs technically prohibit running public servers. Unlikely to be enforced for small game servers, but worth checking.
NOTE: For a small private server with trusted friends, the risk is very low. The risk increases with public-facing servers open to strangers.	

Option 1 — Keep It Private (Easiest, Zero Risk)

The simplest way to eliminate IP exposure is to not expose your server publicly at all. Share your IP only with people you trust by direct message, and set a strong server password in Configuration. Your server

will not appear in the Steam server browser, but trusted players can connect via direct IP.

- Set a server password in Configuration
- Share your IP privately via Discord, WhatsApp or similar
- Do not forward ports to the server browser query port (27015) if you want to stay off the public list

Option 2 — DDNS Hostname (Convenience, Not Privacy)

Services like No-IP (noip.com) and DuckDNS (duckdns.org) give you a free hostname like myserver.ddns.net that automatically updates when your home IP changes. Players connect using the hostname instead of a raw IP. This does not hide your IP — the hostname still resolves to your home address — but it means your IP changing does not break connections, and it looks more professional.

- No-IP: free tier allows 1 hostname, updates automatically
- DuckDNS: completely free, unlimited hostnames, simple setup
- Neither hides your IP — they just give it a stable name

Option 3 — VPN with Port Forwarding (Good Balance)

Some VPN providers offer port forwarding on their exit servers, meaning your server traffic exits through the VPN IP rather than your home IP. Players connect to the VPN provider IP address, never seeing your real one. This is one of the most practical solutions for home server hosts.

AirVPN	Paid (~£5/month). Good port forwarding support. Players connect to AirVPN IP.
Mullvad	Paid (~£5/month). Strong privacy. Port forwarding available on some servers.
PIA (Private Internet Access)	Paid. Well-known, port forwarding supported.
WARNING: Your regular VPN for browsing (NordVPN, ExpressVPN etc) typically does NOT support port forwarding and will not work for this purpose. You need a VPN specifically offering port forwarding.	

Option 4 — Cheap VPS as a Relay (Best Protection)

Rent a very cheap virtual private server (VPS) from a cloud provider (Hetzner, Linode, Vultr — from £3-5/month). Players connect to the VPS IP. The VPS forwards traffic to your home server using a reverse tunnel. Your home IP is never exposed.

1. Rent a VPS in a nearby region for low latency
2. Set up a reverse tunnel using rathole or frp (both free and open source)
3. Point your game port and query port through the tunnel
4. Give players the VPS IP — they never see your home address

This adds a small amount of latency (typically 5-20ms depending on VPS location) but completely hides your home IP. The VPS is also a natural DDoS buffer — attacks hit the VPS, not your home connection.

Option 5 — Cloudflare Spectrum (Paid, Most Robust)

Cloudflare Spectrum is a paid Cloudflare feature that proxies arbitrary TCP/UDP traffic through Cloudflare global network. Players connect to Cloudflare IP, never seeing yours, and get DDoS protection included.

- Requires a domain name (~£10/year) pointed to Cloudflare
- Cloudflare Spectrum is a paid add-on (not the free tier)
- Provides enterprise-grade DDoS protection
- Works for UDP game traffic (unlike free Cloudflare which is HTTP only)

NOTE: The free Cloudflare Tunnel (cloudflared) only works for HTTP/HTTPS services, not UDP game servers. Cloudflare Spectrum for UDP is a paid feature.

Comparison

Method	Cost Hides IP? DDoS Protection Complexity
Private server + password	Free Yes (not listed) No None
DDNS hostname	Free No No Very low
VPN with port forwarding	£5/month Yes Partial Low
VPS relay (rathole/frp)	£3-5/month Yes Yes Medium
Cloudflare Spectrum	£20+/month Yes Yes (enterprise) Medium

Recommended Approach for ChillWithSyd

For most home server owners running a semi-private server for a community:

- Use a strong server password — filters out strangers
- Use DuckDNS for a stable hostname — free and takes 5 minutes to set up
- If you want public visibility with safety, a cheap VPS relay is the best value
- If DDoS is a real concern, Cloudflare Spectrum is the strongest option

IMPORTANT: Whatever you choose, always keep Windows Firewall enabled and only open the specific ports you need. Never disable the firewall entirely.

Useful Links

DuckDNS (free DDNS)	https://www.duckdns.org Free dynamic DNS. Give your server a stable hostname even when your home IP changes. Takes 5 minutes to set up.
No-IP (free DDNS)	https://www.noip.com Alternative free DDNS service. 1 free hostname on the free tier.
rathole (VPS relay tool)	https://github.com/rapiz1/rathole Lightweight reverse proxy written in Rust. Use this on a cheap VPS to relay game traffic to your home server without exposing your home IP. Supports UDP.
frp (Fast Reverse Proxy)	https://github.com/fatedier/frp Popular alternative to rathole. Slightly more resource-heavy but very well documented. Also supports UDP port forwarding.
AirVPN (VPN + port forwarding)	https://airvpn.org Paid VPN with port forwarding support. Players connect to AirVPN IP, not your home IP.
Mullvad VPN	https://mullvad.net Strong privacy-focused VPN. Port forwarding available. No account email required to sign up.
Hetzner (cheap VPS)	https://www.hetzner.com/cloud European cloud VPS from around 3-5 EUR/month. Good location for UK-based servers. Use as a relay with rathole or frp.
Cloudflare Spectrum	https://www.cloudflare.com/products/cloudflare-spectrum Paid Cloudflare feature for proxying UDP/TCP game traffic. Enterprise-grade DDoS protection. Requires a domain name.

Soulmask Steam Workshop	https://steamcommunity.com/app/2646460/workshop Browse and find mods for your server.
Soulmask Fandom Wiki (server guide)	https://soulmask.fandom.com/wiki/Private_Server Official community wiki with server setup and parameter reference.
Sara Serenity server guide	https://saraserenity.net/soulmask The most comprehensive independent Soulmask server guide. Covers GameXishu.json keys, RCON commands and more.
Node.js download	https://nodejs.org/en/download Required to run ChillWithSyd. Download the LTS version.

Troubleshooting

Server will not start	Check the Server Install Path. The folder must contain WS\Binaries\Win64\WSServer-Win64-Shipping.exe. Check Server Logs for errors.
Players cannot connect	Check Windows Firewall allows UDP on ports 8777 and 27015. Confirm Dashboard shows ONLINE.
World not saving	Always use Stop & Save. Check the Server ID has not changed. Auto-saves only appear when players are online.
Tuning not applying	Stop server before saving tuning. Use Diagnose tab to confirm which file is active. Check KaiQiKuaFu is correct for your setup.
Server shuts down by itself	Check Configuration → Schedules. If Daily or Weekly restart is enabled and the manager restarted near that time, it may have fired. A 60-second guard is in place to prevent this — update to latest server.js.
Stop & Save takes long	Port 18888 may be blocked for local connections. Stdin fallback handles shutdown but port 18888 improves speed. Check Windows Firewall.
Mod connection error	Mod version mismatch. Restart server to re-download, ask players to update Workshop subscription.
Items broken after mod removal	Re-add the mod to restore items. The save file is intact — only the visual/functional reference is missing.
Cluster client won't connect	Check broadcast port 20000 is not blocked by firewall. Check IP:port in client config matches main server.

GameXishu.json Key Reference

This appendix lists every key in GameXishu.json alongside its English label from the Gameplay Tuning page. Use this when editing the JSON file manually. The file is at WS\Saved\GameplaySettings\GameXishu.json and contains three identical slots: "0", "1", and "2". Edit all three slots to ensure your changes take effect.

WARNING: The manager writes to all three slots automatically when you save via the Tuning page. When editing manually, copy your changes to all three slots.

XP and Progression

JSON Key	English Label
ExpRatio	Global XP Rate
ChengZhangExpRatio	Growth XP Rate
CaiJiExpRatio	Gathering XP Rate
ShaGuaiExpRatio	Kill XP Rate
ShaGuaiExpShareRatio	Kill XP Share Ratio
ZhiZuoExpRatio	Crafting XP Rate
MJExpRatio	Mask XP Rate
QiTaExpRatio	Other XP Rate
TrainingExpRatio	Training EXP Rate
ShuLianDuExpRatio	Proficiency EXP Rate
ZhuDongYiJiShuXingRatio	Active Skill Attr
BeiDongYiJiShuXingRatio	Passive Skill Attr
ErJiShuXingRatio	Secondary Attribute Ratio
MaxLevel	Max Level

Resources and Gathering

JSON Key	English Label
CaiJiDiaoLuoRatio	Gathering Drop Rate
CaiJiDamageRatio	Gathering Damage Rate
CaiKuangDiaoLuoRatio	Mining Drop Rate
FaMuDiaoLuoRatio	Logging Drop Rate
CaiJiShengChanJianZhuDiaoLuoRatio	Production Building Output
DongWuShiTiDiaoLuoRatio	Animal Body Drop Rate

DongWuShiTZhongYaoDiaoLuoRatio	Animal Rare Drop Rate
PuTongRenDiaoLuoRatio	Common NPC Drop Rate
JingYingRenDiaoLuoRatio	Elite NPC Drop Rate
BossRenDiaoLuoRatio	Boss Drop Rate
ZuoWuDroRatio	Crop Harvest Rate
ZuoWuShengZhangRatio	Crop Growth Speed
ZuoWuXiaoHuiRatio	Crop Rot Speed
ZuoWuShuiXiaoHaoRatio	Crop Water Drain
ZuoWuFeiLiaoXiaoHaoRatio	Fertilizer Use Rate
RanLiaoXiaoHaoRatio	Fuel Consumption
ZhiZuoTimeRatio	Crafting Time Ratio
ZiYuanShengMingRatio	Resource Node HP
ZhiBeiChongShengRatio	Vegetation Respawn Speed

Combat

JSON Key	English Label
DamageYeShengRatio	Wild Monster Damage Out
BeDamageByYeShengRatio	Wild Damage Taken
DongWuDamageRatio	Animal Damage
DongWuJianShangRatio	Animal Resistance (DMG against animals)
YeShengHitJianZhuShangHaiRatio	Wild Animal Building Damage
GongJiJianZhuDamageRatio	Building Damage
WanJiaHitJianZhuShangHaiRatio	Player Hit Building Damage
AlDengJi	AI Difficulty Level
DynamicBossStats	Dynamic Boss Scaling
SuoDingKaiGuan	Auto Lock-On
RollingInvincibleTimeRatio	Dodge I-Frame Duration
JiaSiHuiFuRatio	Feign Death HP Recovery
IsPlayBossAppearanceSequence	Boss Intro Animations
ManRenTiLiDamageRatio	Barbarian Stamina Damage

ManRenTenacityDamageRatio	Barbarian Tenacity Damage
DongWuTiLiDamageRatio	Animal Stamina Damage

Survival

JSON Key	English Label
ShiWuXiaoHaoRatio	Food Consumption
ShuiXiaoHaoRatio	Water Consumption
QiXiXiaoHaoRatio	Stamina Drain
ShengMingHuiFuRatio	HP Regen Rate
TiLiHuiFuRatio	Stamina Recovery Rate
QiXiHuiFuRatio	Stamina Regen
NaiJiuXiShu	Durability Loss Rate
XiuLiXuYaoCaiLiaoRatio	Repair Material Cost
XiuLiJiangNaiJiuShangXianRatio	Repair Durability Cap Reduction
WuPinFuHuaiRatio	Item Decay Rate
WuPinXiaoHuiTime	Item Destroy Time
MaxFuZhongRatio	Max Carry Weight Multiplier
RoleBagCapacity	Backpack Slot Count
PlayerDeathCantDropItemKaiGuan	Keep Items on Death
BinSiKaiGuan	Near-Death System
FuHuoMoveSiWangBaoKaiGuan	Death Bag Moves on Respawn
ReDuXiShu	Invasion Fever Rate
XinQingJianShao	Mood Decrease Rate
XinQingZengZhang	Mood Increase Rate

Tribe and Animals

JSON Key	English Label
GongHuiMaxZhaoMuCount	Guild Max Tribesmen
GeRenMaxZhaoMuCount	Personal Max Tribesmen
GeRenMaxZhaoMuCount_Two	Personal Max Tribesmen Lv2
GeRenMaxZhaoMuCount_Three	Personal Max Tribesmen Lv3

GongHuiMaxMember	Max Players per Tribe
GongHuiMaxDongWuCount	Guild Max Animals
GeRenMaxDongWuCount	Personal Max Animals
AnimalFollowerMaxCount	Max Following Animals
ManRenChuZhanCount	Deployed Tribesmen
GongHuiMaxSpecDongWuCount	Tribe Giant Elephant Limit
GeRenMaxSpecDongWuCount	Personal Giant Elephant Limit
KurmaFuZhongRatio	Platform Animal Load Multiplier
XinXiLuRu	Deceased Tribesman Records
AddRenKeDuRatio	Tribesman Toxicity Rate
ChongsuRatio	Tribesman Remodel Cooldown
ZuRenFuZhi	Copy Tribesman
JingShenNoXiaoHao	Disable Morale Cost
WanMeiChongSu	Perfect Remodel
DongWuShengZhangRatio	Animal Growth Speed
DongWuChanChuRatio	Animal Output Rate
DongWuShengChanJianGeRatio	Animal Production Interval
FanZhiJianGeRatio	Breeding Interval
DongWuXiaoHaoShiWuRatio	Animal Food Drain
DongWuXiaoHaoShuiRatio	Animal Water Drain
DongWuPinZhiRatio	Animal Quality
FuHuaSpeed	Egg Incubation Speed
XiuMianOfflineDays	Offline Hibernate After (days)

World

JSON Key	English Label
GameWorldTimePower	Day/Night Speed
GameWorldDayTimePortion	Daytime Fraction
YingHuoRanShaoSuDuRatio	Fire Burn Speed
JianZhuFuLanKaiGuan	Building Decay On
JianZhuFuLanMul	Building Decay Rate

JianZhuXiuLiMul	Building Repair Cost
KaiQiJianZhuHuiXueBuilding	Building HP Regen
JianZhuGaoDuLimit	Building Height Limit
JianZhuBeDamageLimit	Building Damage Cooldown
JianZhuMirageKaiGuan	Building Preview Mode
JianZhuChuanSongMenPlusKaiGuan	Extended Portal System
TransDoorInterworkKaiGuan	Two-way Portals
MaxChuanSongMenNumber	Portal Limit
MaxGenRenYingHuoNumber	Personal Bonfire Limit
MaxGongHuiYingHuoNumber	Tribe Bonfire Limit
GeRenBiaoJiMaxCount	Personal Map Markers
GongHuiBiaoJiMaxCount	Tribe Map Markers
GongHuiMaxRaftSpaceCount	Tribe Raft Slots
GeRenMaxRaftSpaceCount	Personal Raft Slots
MaxConveyorCount	Max Conveyor Count
MaxDongLiKuangChangCount	Max Power Mine Buildings
MaxDiCiCount	Max Dungeon Instances
MakeUseAroundRongQiKaiGuan	Auto-use Nearby Chests
ShuaXinNPCKaiGuan	NPC Respawn
DungeonReborn	Dungeon Respawn
ZhaoHuanDisRatio	Mount Summon Distance
BanGlider	Ban Glider
PanpaKaiGuan	Enable Climbing
KaiQiKuaFu	Cluster Mode (Cross-server)
TribalExplorationKaiGuan	Tribe Expedition Events
RuinsExplorationKaiGuan	Ruins Expedition Events
TribalTransportSwitch	Tribe Transport Events
SpecialEventConfigSwitch	Custom Event Config
MaskRepairUpgradeSwitch	Mask Repair Upgrade
TiaoWuLengQueTime	Dance Cooldown (s)

MaRenBeiDongYiJiShuXingRatio	Marauder Passive Skill Attr
PingTaiBuildRangeLimit	Platform Build Range Limit (ships and giant elephants)
PingTaiJianZhuNumLimit	Platform Build Count Limit (ships and giant elephants)
MaxPingTaiJianZhuNumMul	Platform Max Build Multiplier — default 0.1 = 10% of singleplayer slots
PingTaiAffectNavigation	Platform Affects Navigation

Death and Loot

JSON Key	English Label
ZhiYouTongZuCaiJiSiWangKaiGuan	Tribe-Only Corpse Loot
BaoXiangDropRatio	Chest Drop Multiplier
BaoXiangDiaoLuoDengJi	Chest Drop Level
NormalEquipDropRatioCorrection	Normal Equip Drop Correction
EliteEquipDropRatioCorrection	Elite Equip Drop Correction
BossEquipDropRatioCorrection	Boss Equip Drop Correction
NormalEquipDurabilityCorrection	Normal Equip Durability
EliteEquipDurabilityCorrection	Elite Equip Durability
BossEquipDurabilityCorrection	Boss Equip Durability
TeShuDaoJuDropXiShuJiaChengKaiGuan	Special Item Drop Bonus
ChestDropEquipmentMaxQualitySwitch	Chest Equipment Quality Cap
PVEOnlyTongGuiShuCanOpenKaiGuan	PvE Guild-Only Access
YunXuOtherDaKaiXiangZi	Anyone Can Open Chests
YunXuOtherDaKaiGongZuoTai	Anyone Can Use Workbenches
HuiFuChuShiBodyData	Restore Initial Body Data

PvP and Raids

JSON Key	English Label
HuXiangShangHaiKaiGuan	PvP Damage On

PVP_GAPVPDamageRatio	Global PvP Damage
PVP_ShangHaiRatio_JinZhan	PvP Melee Damage
PVP_ShangHaiRatio_YuanCheng	PvP Ranged Damage
PVP_ShangHaiRatio_PlayerToPlayer_DiFang	PvP Attacker Damage
PVP_ShangHaiRatio_PlayerToPlayer_YouFang	PvP Defender Damage
PVP_ShangHaiRatio_WithoutP2P_YouFang	PvP Non-P2P Defender Damage
YouFangShangHaiKaiGuan	Defensive Damage On
PlayerYouFangShangHaiKaiGuan	Player Defensive Damage
WarKaiGuan	Battle/War Mode
ProtectJianZhulnYingHuoSwitch	Bonfire Building Protection
PVPTimeAsiaWorkStartTime	PvP Asia Work Start Hour
PVPTimeAsiaWorkEndTime	PvP Asia Work End Hour
PVPTimeAsiaNoWorkStartTime	PvP Asia Non-Work Start Hour
PVPTimeAsiaNoWorkEndTime	PvP Asia Non-Work End Hour
PVPTimeEuropeWorkStartTime	PvP Europe Work Start Hour
PVPTimeEuropeWorkEndTime	PvP Europe Work End Hour
PVPTimeEuropeNoWorkStartTime	PvP Europe Non-Work Start Hour
PVPTimeEuropeNoWorkEndTime	PvP Europe Non-Work End Hour
PVPTimeAmericaWorkStartTime	PvP America Work Start Hour
PVPTimeAmericaWorkEndTime	PvP America Work End Hour
PVPTimeAmericaNoWorkStartTime	PvP America Non-Work Start Hour
PVPTimeAmericaNoWorkEndTime	PvP America Non-Work End Hour

Marauders

JSON Key	English Label
-----------------	---------------

MaRenDamageRatio	Marauder Damage
ManRenJianShangRatio	Marauder Resistance (DMG against marauders)
ManRenPinZhiRatio	Marauder Quality
MaRenZhuDongYiJiShuXingRatio	Marauder Active Skill Attr
MaRenBeiDongYiJiShuXingRatio	Marauder Passive Skill Attr
MaRenErJiShuXingRatio	Marauder Secondary Attr

Invasions

JSON Key	English Label
RuQinKaiGuan	Invasion / Raid On
SuiJiRuQinKaiGuan	Random Invasions
RuQinQiangDuXiShu	Invasion Intensity
RuQinGuiMoXiShu	Invasion Scale
RuQinGuaiLevelXiShu	Invasion Monster Level
RuQinShaoChengXiShu	Invasion Burn Coefficient
RuQinTuShaXiShu	Invasion Massacre Coefficient
RuQinMaxChangCiCount	Max Simultaneous Invasions
RuQinGuaiCountMin	Min Invasion Monsters
RuQinGuaiCountMax	Max Invasion Monsters
RuQinPerBoGuaiMin	Min Monsters per Wave
RuQinPerBoGuaiMax	Max Monsters per Wave
RuQinBeginHour	Raid Start Hour
RuQinEndHour	Raid End Hour
TanChaMinuteLimit	Scout Phase Duration (min)
JinGongMinuteLimit	Max Attack Duration (min)
LengQueMinuteLimit	Raid Cooldown (min)
RuQinSucceedPrizeTimes	Invasion Reward Multiplier
SpecialBossSwitch	Special Event Bosses
RelicChestEventSwitch	Relic Chest Events
BossDeathEventSwitch	Boss Death Events

Quick Reference

File Locations

Server executable	WS\Binaries\Win64\WSServer-Win64-Shipping.exe
World save (live)	WS\Saved\Worlds\Dedicated\DLC_Level01_Main\world.db
Auto-save files	WS\Saved\Worlds\Dedicated\DLC_Level01_Main\auto_*.db
Gameplay settings	WS\Saved\GameplaySettings\GameXishu.json
Manager config	servers.json (same folder as server.js)
Mods (server)	WS\Binaries\Win64\steamapps\workshop\content\2646460\

Port Reference

Game port (-PORT)	8777 UDP — players connect here
Query port	27015 UDP — Steam server browser
Echo port	18888 TCP — Telnet remote console
Cluster broadcast	20000 TCP — cluster internal (do not expose publicly)
Manager UI	3000 TCP — browser panel

Telnet Console Commands (port 18888)

SaveWorld 0	Write world state to in-memory database
BackupDatabaseByHour	Flush to disk (alias: bkh)
shutdown 30	Save and shut down after 30-second countdown
List_OnlinePlayers	Show all connected players

In-Game GM Commands

gm key [password]	Authenticate as admin
gm saveworld	Force save world state
gm exit	Graceful server shutdown