

On This Page &gt;

# Flake-parts

Clan supports integration with [flake-parts](#), a framework for constructing your `flake.nix` using modules. Follow these steps to integrate Clan with flake-parts:

## Step 1: Update Your Flake Inputs

Add `flake-parts` as a dependency in your `flake.nix` file alongside existing dependencies like `clan-core` and `nixpkgs`. Here's an example:

```
1 # flake.nix
2 inputs = {
3   nixpkgs.url = "github:NixOS/nixpkgs?ref=nixos-unstable";
4
5   # Add flake-parts
6   flake-parts.url = "github:hercules-ci/flake-parts";
7   flake-parts.inputs.nixpkgs-lib.follows = "nixpkgs";
8
9   clan-core = {
10     url = "https://git.clan.lol/clan/clan-core/archive/25.11.tar.gz";
11     inputs.nixpkgs.follows = "nixpkgs"; # Avoid this if using nixpkgs stable
12     inputs.flake-parts.follows = "flake-parts"; # New
13   };
14 };
```

## Step 2: Import the Clan flake-parts Module

Next, import the Clan flake-parts module to make the [Clan options](#) available within `mkFlake`:

```

1 {
2   outputs =
3     inputs@{ flake-parts, ... }:
4     flake-parts.lib.mkFlake { inherit inputs; } (
5       {
6         imports = [
7           inputs.clan-core.flakeModules.default
8         ];
9       }
10    );
11 }

```

## Step 3: Configure Clan Settings and Define Machines

Configure Clan-wide settings and define machines. Here's an example `flake.nix`:

```

1 {
2   outputs = inputs@{ flake-parts, clan-core, ... }:
3     flake-parts.lib.mkFlake { inherit inputs; } ({self, pkgs, ...}: {
4       # See: https://flake.parts/getting-started
5       systems = [
6         "x86_64-linux"
7       ];
8
9       # Import the Clan flake-parts module
10      imports = [
11        clan-core.flakeModules.default
12      ];
13
14      # Define your Clan
15      clan = {
16        meta.name = ""; # Required and must be unique
17        meta.domain = ""; # Required and must be unique
18
19        machines = {
20          jon = {
21            imports = [
22              ./modules/firefox.nix
23              # Add more modules as needed
24            ];
25

```

```
26     nixpkgs.hostPlatform = "x86_64-linux";
27
28     # Enable remote Clan commands over SSH
29     clan.core.networking.targetHost = "root@jon";
30
31     # Disk configuration
32     disko.devices.disk.main = {
33         device = "/dev/disk/by-id/nvme-eui.e8238fa6bf530001001b448f";
34     };
35 };
36 };
37 };
38 });
39 }
```

For more details on configuring `flake-parts` and available Clan options, refer to the [Clan module documentation](#).

← Previous

Nixpkgs Flake Input

Next →

Can I still use nixos-rebuild?

Need help? Reach out to [our community](#).