

TB Inverted Phaser

DETAILED ENGLISH USER MANUAL

A subtractive multi-stage phaser with deep notches, adjustable spacing, feedback, five LFO shapes, and random jitter.



Catalog version: 2.2.0

Documentation edition: 2026-08-04

Host-visible endpoints documented: 13

1. Product purpose

A subtractive multi-stage phaser with deep notches, adjustable spacing, feedback, five LFO shapes, and random jitter.

A conventional phaser adds its all-pass path to the dry signal. TB Inverted Phaser subtracts it, producing harder, deeper cancellation notches that remain clearly defined on pads, sustained chords, guitars, and sound-design material.

What result it creates

- Deep moving spectral notches
- Comb-like patterns from one to twelve stages
- Regular or deliberately unstable modulation
- Dry/wet and residual-texture control

Signal flow

Input -> multi-stage all-pass network -> subtractive combination -> feedback -> LFO and jitter modulation -> Mix and Output

2. Complete feature guide

Stages and Spacing

Stages sets notch count; Spacing changes their distribution. Few stages sound broad, while many stages create a denser comb.

Centre and Depth

Centre places the modulation region and Depth sets its travel around that center.

Rate and LFO Shape

Rate controls speed. Sine and Triangle are smooth, Ramp shapes are directional, and Square produces stepped movement.

Jitter

Adds controlled irregularity to otherwise periodic motion. Use small amounts for organic drift and high amounts for broken modulation.

Amount, Feedback, and Mix

Amount controls the subtractive phase contribution, Feedback reinforces the notch pattern, and Mix blends the complete result with the source.

Output and Programs

Output compensates cancellation or resonant gain. Programs cover pads, glassy hollows, metallic rails, square jolts, and ghost cancellation.

3. Quick start

1. Choose the number of Stages and set Spacing.

2. Place Centre near the source's strongest harmonics.
3. Set Depth, Rate, and LFO Shape.
4. Raise Amount until the notches are clear.
5. Add Feedback carefully.
6. Use Jitter only if perfect repetition is unwanted, then level-match Output.

4. Practical workflows

Pad movement

1. Use 6-12 stages.
2. Choose Sine or Triangle.
3. Set slow Rate, broad Depth, and moderate Feedback.

Expected result: The pad develops deep, continuous movement without rhythmic stepping.

Mechanical sweep

1. Choose Ramp or Square.
2. Raise Feedback and Jitter.
3. Use fewer stages for larger, sharper notches.

Expected result: The source gains directional, machine-like spectral motion.

5. Automation, gain staging, and session use

- Automate only controls that serve a clear musical transition. Fast movement of frequency, time, pitch, mode, oversampling, or algorithm selectors may intentionally create artifacts or require a host-safe transition.
- Match perceived loudness before judging quality. A louder setting will often appear better even when the processing decision is not better.
- Use the plug-in bypass endpoint for comparison and preserve an unprocessed source or earlier project version.
- Factory programs are starting points. Loading a program changes multiple parameters; save a new DAW preset after adapting it to the source.
- The parameter appendix is captured from the installed VST3 host contract. It lists every host-visible endpoint, its displayed range/options, default, automation status, and identifier.

6. Limits, cautions, and troubleshooting

- Subtractive phase processing can remove substantial energy at particular notes.
- High Feedback may ring.
- Always check the effect in mono when it is part of a wider stereo chain.
- No audible change: confirm the plug-in and relevant sub-block are enabled, Mix/Amount is not at a neutral value, and the source contains energy in the processed region.
- Unexpected level: return input, output, send, feedback, and parallel-mix controls to conservative values, then rebuild the setting one block at a time.
- Automation does not match the panel: reload the project, confirm the DAW is addressing the current plug-in version, and check whether a factory program or state recall replaced values.

- Clicks or transitions: avoid sample-instant changes to algorithm, time, pitch, mode, or oversampling selectors unless the sound is intentional.

7. Complete host parameter reference

This appendix contains all 13 parameters exposed by the current installed VST3 to a host. Repeated EQ-band endpoints are intentionally listed rather than collapsed. Discrete options are printed in full when the host contract exposes them.

Parameter	Range / options	Default	Host status	Function
Amount VST3 ID 733630552	0.0 to 100.0	65.0	Automatable	Sets how strongly the named process affects the signal.
Bypass VST3 ID 1652125811	Off, On	Off	Automatable; Bypass	Turns the complete plug-in processing path off or on through the host-visible bypass endpoint.
Centre VST3 ID 783470043	120.0 to 4000.0	720.0	Automatable	Sets the principal frequency, note, or spectral center used by this function.
Depth VST3 ID 95472323	0.0 to 100.0	70.0	Automatable	Sets how strongly the named process affects the signal.
Feedback VST3 ID 1955982213	0.0 to 85.0	28.0	Automatable	Returns processed signal to its own input, extending or intensifying the effect.
Jitter VST3 ID 987746540	0.0 to 100.0	0.0	Automatable	Controls granular density, dispersion, or random variation for the named process.
LFO Shape VST3 ID 686216812	Sine, Triangle, Ramp Up, Ramp Down, Square	Sine	Automatable	Selects the operating algorithm, response shape, or tonal character for the named block.
Mix VST3 ID 108124	0.0 to 100.0	100.0	Automatable	Sets the balance between the original signal and the complete processed path.
Output VST3 ID 1141971201	-12.0 to 6.0	0.0	Automatable	Sets or limits the final output level after the plug-in's main processing.
Program VST3 ID 1886548852	Init, Pad Drift, Slow Orbit, Wide Vortex, Fast Warble, Ramp Sweeper, Thin Air, Hollow Glass, Static Teeth, Metal Rail, Square Jolt, Broken Motion, Ghost Cancel	Init	Automatable	Selects a factory program. Loading a program recalls a coordinated set of plug-in parameters.
Rate VST3 ID 3493088	0.020 to 8.000	0.350	Automatable	Sets the speed of modulation, movement, or repeated change.
Spacing VST3 ID 135324739	0.0 to 100.0	35.0	Automatable	Host-automatable control for Spacing. Its full range and default are shown in this table; use it with the related feature section above.
Stages VST3 ID 1254989109	1 to 12	6	Automatable	Host-automatable control for Stages. Its full range and default are shown in this table; use it with the related feature section above.

Documentation basis

Prepared from the current public catalog, current local product brief and implementation notes where available, existing English manuals where available, and a direct scan of the installed VST3 host contract. Internal implementation details that are not user-facing are intentionally excluded; all user-facing features and host-visible controls are documented.