

TB Parallel Reverb

DETAILED ENGLISH USER MANUAL

A three-engine parallel space designer: Glue for room body, Bright for plate/spring color, and Space for hall or impulse-response depth.



Catalog version: 3.0.1

Documentation edition: 2026-08-04

Host-visible endpoints documented: 43

1. Product purpose

A three-engine parallel space designer: Glue for room body, Bright for plate/spring color, and Space for hall or impulse-response depth.

One reverb algorithm usually forces a compromise between proximity, color, and long depth. TB Parallel Reverb runs three independent wet engines in parallel, allowing each spatial role to be tuned and auditioned separately before the final dry/wet blend.

What result it creates

- Short room or chamber glue
- Plate or spring brightness
- Long hall or convolution depth
- Independent sends, filtering, width, pre-delay, color, and solo

Signal flow

Dry input -> parallel Glue, Bright, and Space engines -> per-engine send/return -> wet sum bus -> final Wet/Dry Mix

2. Complete feature guide

Engine enable, mode, and solo

Each engine can be enabled independently. Glue selects Room or Chamber; Bright selects Plate or Spring; Space selects Hall or IR. Reverb Solo auditions one wet return without dry.

Shared controls

Each engine provides Pre-Delay, Wide, Send Gain, Decay or Length, High Pass, Low Pass, Diffusion, and Color-related shaping appropriate to that engine.

Glue engine

Size, Diffusion, Damping, Early/Late Mix, filtering, width, and short decay create proximity, body, and a common room around the source.

Bright engine

Plate/Spring mode, modulation rate/depth, diffusion, distance or spring tension, filtering, width, and color produce shine or mechanical character.

Space engine

Hall/IR mode, Hall Type, Decay/Length, HF Damping, Diffusion, Shimmer, filtering, width, and pre-delay build long depth. IR mode uses the loaded response behavior available in the deployed build.

Send versus Wet/Dry

Per-engine Send Gain controls each wet return. Wet/Dry Mix controls the final global relationship between the original source and the summed wet bus.

Programs

Factory programs cover balanced three-engine spaces, vocal plates and chambers, drum rooms, halls, clouds, and deliberately haunted textures.

3. Quick start

1. Set Wet/Dry to 100 percent on an aux return or to a conservative value on an insert.
2. Build Glue first with a short decay and moderate send.
3. Add Bright for plate or spring color.
4. Add Space at a lower send for depth.
5. Use Solo to tune each return in isolation.
6. Remove unnecessary lows/highs per engine and set width.
7. Exit Solo and balance all sends in context.

4. Practical workflows

Lead vocal space

1. Use Glue Room for proximity.
2. Use Bright Plate for a clear tail.
3. Add Space Hall quietly behind both.
4. High-pass each engine and use pre-delay to protect diction.

Expected result: The vocal remains forward while the reverb field gains body, shine, and depth.

Drum room stack

1. Use Glue Chamber for body.
2. Add Bright Plate or Spring to the snare region.
3. Keep Space short or low in level.
4. Use Solo to remove low-frequency wash.

Expected result: The kit sounds larger without losing transient definition.

5. Automation, gain staging, and session use

- Automate only controls that serve a clear musical transition. Fast movement of frequency, time, pitch, mode, oversampling, or algorithm selectors may intentionally create artifacts or require a host-safe transition.
- Match perceived loudness before judging quality. A louder setting will often appear better even when the processing decision is not better.
- Use the plug-in bypass endpoint for comparison and preserve an unprocessed source or earlier project version.
- Factory programs are starting points. Loading a program changes multiple parameters; save a new DAW preset after adapting it to the source.
- The parameter appendix is captured from the installed VST3 host contract. It lists every host-visible endpoint, its displayed range/options, default, automation status, and identifier.

6. Limits, cautions, and troubleshooting

- Parallel returns add together and can build level quickly.
- Solo is an audition state; disable it before export.
- Long decay, shimmer, and high feedback-like settings can mask the source.
- No audible change: confirm the plug-in and relevant sub-block are enabled, Mix/Amount is not at a neutral value, and the source contains energy in the processed region.
- Unexpected level: return input, output, send, feedback, and parallel-mix controls to conservative values, then rebuild the setting one block at a time.
- Automation does not match the panel: reload the project, confirm the DAW is addressing the current plug-in version, and check whether a factory program or state recall replaced values.
- Clicks or transitions: avoid sample-instant changes to algorithm, time, pitch, mode, or oversampling selectors unless the sound is intentional.

7. Complete host parameter reference

This appendix contains all 43 parameters exposed by the current installed VST3 to a host. Repeated EQ-band endpoints are intentionally listed rather than collapsed. Discrete options are printed in full when the host contract exposes them.

Parameter	Range / options	Default	Host status	Function
Bright Color VST3 ID 726260873	0 to 100	45	Automatable	Selects the operating algorithm, response shape, or tonal character for the named block.
Bright Decay VST3 ID 647391463	1.50 to 2.50	2.00	Automatable	Sets how long the associated detector, envelope, reverb, or resonant process takes to recover or decay.
Bright Diffusion VST3 ID 1529017835	0 to 100	70	Automatable	Shapes spatial density, resonant spread, or diffuse body for the named process.
Bright Enabled VST3 ID 1740343015	Off, On	On	Automatable	Enables or disables the named processing block without bypassing the entire plug-in.
Bright High Pass VST3 ID 1230933485	20 to 1800	450	Automatable	Reduces low-frequency content in the associated audio or detector path.
Bright Low Pass VST3 ID 1558818091	1200 to 20000	13500	Automatable	Reduces high-frequency content or shortens high-frequency decay in the associated path.
Bright Mode VST3 ID 647188413	Plate, Spring	Plate	Automatable	Selects the operating algorithm, response shape, or tonal character for the named block.
Bright Modulation Depth VST3 ID 119127547	0.00 to 20.00	1.50	Automatable	Sets how strongly the named process affects the signal.
Bright Modulation Rate VST3 ID 281350824	0.02 to 5	0.02	Automatable	Sets the speed of modulation, movement, or repeated change.
Bright Plate Distance Spring Tension VST3 ID 1775723855	0 to 100	35	Automatable	Sets the named spatial coordinate or psychoacoustic positioning cue.
Bright Pre-Delay VST3 ID 1596243386	0.0 to 100.0	18.0	Automatable	Host-automatable control for Bright Pre-Delay. Its full range and default are shown in this table; use it with the related feature section above.
Bright Send Gain VST3 ID 647357858	-60.0 to 6.0	-15.0	Automatable	Sets gain for the named input, output, band, or parallel send/return path.
Bright Wide VST3 ID 647480557	0 to 270	210	Automatable	Sets stereo spread or the lateral distribution of the processed signal.
Bypass VST3 ID 1652125811	Off, On	Off	Automatable; Bypass	Turns the complete plug-in processing path off or on through the host-visible bypass endpoint.
Glue Color VST3 ID 1476289070	0 to 100	30	Automatable	Selects the operating algorithm, response shape, or tonal character for the named block.
Glue Damping VST3 ID 1862232333	0 to 100	60	Automatable	Reduces high-frequency content or shortens high-frequency decay in the associated path.
Glue Decay VST3 ID 1779964578	0.50 to 1.00	0.75	Automatable	Sets how long the associated detector, envelope, reverb, or resonant process takes to recover or decay.
Glue Diffusion VST3 ID 1763844368	0 to 100	65	Automatable	Shapes spatial density, resonant spread, or diffuse body for the named process.
Glue Early Late Mix VST3 ID 1133218292	0 to 100	45	Automatable	Sets the balance between the original signal and the complete processed path.
Glue Enabled VST3 ID 962934604	Off, On	On	Automatable	Enables or disables the named processing block without bypassing the entire plug-in.
Glue High Pass VST3 ID 753592872	20 to 1500	200	Automatable	Reduces low-frequency content in the associated audio or detector path.
Glue Low Pass VST3 ID 781409680	1000 to 20000	9000	Automatable	Reduces high-frequency content or shortens high-frequency decay in the associated path.
Glue Mode VST3 ID 1779761528	Room, Chamber	Room	Automatable	Selects the operating algorithm, response shape, or tonal character for the named block.
Glue Pre-Delay VST3 ID 1118902773	0.0 to 60.0	8.0	Automatable	Host-automatable control for Glue Pre-Delay. Its full range and default are shown in this table; use it with the related feature section above.

Parameter	Range / options	Default	Host status	Function
Glue Send Gain VST3 ID 1779930973	-60.0 to 6.0	-12.0	Automatable	Sets gain for the named input, output, band, or parallel send/return path.
Glue Size VST3 ID 1779935190	0 to 100	50	Automatable	Shapes spatial density, resonant spread, or diffuse body for the named process.
Glue Wide VST3 ID 1780053672	0 to 180	150	Automatable	Sets stereo spread or the lateral distribution of the processed signal.
Program VST3 ID 1886548852	Init Parallel, Three Engine Balance, Natural Space, Clean Bus Wash, Dark Bus Glue, Wide Open, Vocal Plate Halo, Intimate Vocal Room, Pop Vocal Sheen, Ballad Bloom, Lead Vocal Forward, Breathly Air, Dark Vocal Chamber, Wide Vocal Double, Tight Rap Slap, Gospel Hall, Whisper Cloud, Retro Vocal Spring, Drum Room Snap, Tight Booth, Ambient Kit, Snare Plate, Gated Burst Room, Big Rock Room, Jazz Brush Room, Lo-Fi Drum Box, Trap Slap, Percussion Shine, Kick Weight Room, Tom Hall, Clean Amp Spring, Surf Splash, Crunch Room, Lead Guitar Hall, Acoustic Air, Shoegaze Wash, Slide Chamber, Funk Tight Room, Metal Rhythm Plate, Dream Swell, Grand Piano Stage, Upright Room, Warm Rhodes, Wurli Spring, Church Organ, Tight Clav, Felt Piano Intimate, Cinematic Piano, Toy Piano Box, Electric Bloom, Wide Pad Bed, Pluck Bounce, Arp Shimmer, Saw Stack Space, Glass Bell, Warm Analog Room, Ethereal Lead, Drone Bed, Retro Synth Chamber, Hyper Wide Stack, Soft Synth Keys, Motion Pad, Subtle Bass Room, Upright Wood, Synth Bass Depth, Bass Amp Chamber, Clean Low Lift, Dub Cavern, Concert Strings, Solo Violin Hall, Warm Cello Room, Full Score Hall, Chamber Quartet, Epic Trailer Space, Harp Air, Brass Stage, Shimmer Cloud, Octave Bloom, Infinite Drift, Glacier, Cathedral Light, Soft Focus, Deep Space, Slow Swell, Frozen Air, Spring Tape Dream, Night Sky, Underwater, Choir Of Ghosts, Endless Hall, Metal Tank, Broken Spring, Warped Tape Space, Tiny Speaker Box, Backwards Feel, Alien Transmission, Bit Cavern, Pitch Riser, Sonar Ping, Haunted Room	Init Parallel	Automatable	Selects a factory program. Loading a program recalls a coordinated set of plug-in parameters.
Reverb Solo VST3 ID 1485249314	Off, Glue, Bright, Space	Off	Automatable	Host-automatable control for Reverb Solo. Its full range and default are shown in this table; use it with the related feature section above.
Space Color VST3 ID 478609917	0 to 100	25	Automatable	Selects the operating algorithm, response shape, or tonal character for the named block.

Parameter	Range / options	Default	Host status	Function
Space Decay / Length VST3 ID 1193592051	0.25 to 10.00	3.20	Automatable	Sets how long the associated detector, envelope, reverb, or resonant process takes to recover or decay.
Space Diffusion VST3 ID 1973961055	0 to 100	72	Automatable	Shapes spatial density, resonant spread, or diffuse body for the named process.
Space Enabled VST3 ID 2118459227	Off, On	On	Automatable	Enables or disables the named processing block without bypassing the entire plug-in.
Space Hall Type VST3 ID 1704521273	Church, Auditorium, Concert Hall, Studio Hall	Church	Automatable	Selects the operating algorithm, response shape, or tonal character for the named block.
Space HF Damping VST3 ID 56797150	0 to 100	45	Automatable	Reduces high-frequency content or shortens high-frequency decay in the associated path.
Space High Pass VST3 ID 67634169	20 to 1500	300	Automatable	Reduces low-frequency content in the associated audio or detector path.
Space Low Pass VST3 ID 1936934303	1000 to 20000	7500	Automatable	Reduces high-frequency content or shortens high-frequency decay in the associated path.
Space Mode VST3 ID 1193389001	Hall, IR	Hall	Automatable	Selects the operating algorithm, response shape, or tonal character for the named block.
Space Pre-Delay VST3 ID 432944070	0.0 to 200.0	60.0	Automatable	Host-automatable control for Space Pre-Delay. Its full range and default are shown in this table; use it with the related feature section above.
Space Send Gain VST3 ID 1193558446	-60.0 to 6.0	-22.0	Automatable	Sets gain for the named input, output, band, or parallel send/return path.
Space Shimmer VST3 ID 1494550811	0 to 100	15	Automatable	Host-automatable control for Space Shimmer. Its full range and default are shown in this table; use it with the related feature section above.
Space Wide VST3 ID 1193681145	0 to 360	240	Automatable	Sets stereo spread or the lateral distribution of the processed signal.
Wet/Dry Mix VST3 ID 1466200326	0 to 100	100	Automatable	Sets the balance between the original signal and the complete processed path.

Documentation basis

Prepared from the current public catalog, current local product brief and implementation notes where available, existing English manuals where available, and a direct scan of the installed VST3 host contract. Internal implementation details that are not user-facing are intentionally excluded; all user-facing features and host-visible controls are documented.