

TB Volume

DETAILED ENGLISH USER MANUAL

A focused stereo-linked level utility with dB and percent display modes plus output peak protection.



Catalog version: 1.2.0

Documentation edition: 2026-08-04

Host-visible endpoints documented: 3

1. Product purpose

A focused stereo-linked level utility with dB and percent display modes plus output peak protection.

A simple gain stage is useful for automation, trim, and level matching, but many utilities surround it with metering and routing that slow down basic work. TB Volume keeps one underlying level value and allows it to be viewed in dB or an equal-loudness-inspired percent scale without changing the sound when modes switch.

What result it creates

- Fast and repeatable level trim
- Mode switching without a gain jump
- Clean automation of one normalized endpoint
- Stereo-linked peak protection in the deployed design

Signal flow

Input -> normalized level mapping displayed as dB or percent -> stereo-linked output protection -> output

2. Complete feature guide

Mode

dB mode displays a conventional gain range; percent mode displays the same underlying normalized level on a 0-300 percent scale. Changing Mode changes presentation, not the current audio level.

Normalized Level

The host-visible level endpoint runs from 0 to 1 and is mapped by the selected display mode. The midpoint is the neutral reference in the current design.

Peak protection

The deployed design includes stereo-linked sample-peak protection with short lookahead near full scale. Treat it as safety, not as a mastering limiter.

Automation

Automate the normalized level for fades and scene changes. Because both display modes address the same value, do not expect separate automation lanes for dB and percent.

3. Quick start

1. Choose dB or percent display.
2. Set the level while monitoring the downstream bus.
3. Use bypass for a true level comparison.
4. Write automation on Normalized Level.
5. Leave headroom; do not rely on peak protection for routine gain staging.

4. Practical workflows

Level matching

1. Place TB Volume after the processor being evaluated.
2. Adjust level until bypassed and processed loudness match.
3. Make the tonal decision only after matching.

Expected result: Comparisons reflect processing character rather than louder-is-better bias.

Simple fade

1. Choose the preferred display mode.
2. Automate Normalized Level from silence to the target.
3. Use the DAW curve shape to define the fade.

Expected result: A clean stereo-linked fade is created with one automation lane.

5. Automation, gain staging, and session use

- Automate only controls that serve a clear musical transition. Fast movement of frequency, time, pitch, mode, oversampling, or algorithm selectors may intentionally create artifacts or require a host-safe transition.
- Match perceived loudness before judging quality. A louder setting will often appear better even when the processing decision is not better.
- Use the plug-in bypass endpoint for comparison and preserve an unprocessed source or earlier project version.
- Factory programs are starting points. Loading a program changes multiple parameters; save a new DAW preset after adapting it to the source.
- The parameter appendix is captured from the installed VST3 host contract. It lists every host-visible endpoint, its displayed range/options, default, automation status, and identifier.

6. Limits, cautions, and troubleshooting

- Peak protection is not true-peak mastering control.
- Percent is a display mapping, not linear perceived loudness for every source.
- Large boosts raise the noise floor and downstream processing level.
- No audible change: confirm the plug-in and relevant sub-block are enabled, Mix/Amount is not at a neutral value, and the source contains energy in the processed region.
- Unexpected level: return input, output, send, feedback, and parallel-mix controls to conservative values, then rebuild the setting one block at a time.
- Automation does not match the panel: reload the project, confirm the DAW is addressing the current plug-in version, and check whether a factory program or state recall replaced values.
- Clicks or transitions: avoid sample-instant changes to algorithm, time, pitch, mode, or oversampling selectors unless the sound is intentional.

7. Complete host parameter reference

This appendix contains all 3 parameters exposed by the current installed VST3 to a host. Repeated EQ-band endpoints are intentionally listed rather than collapsed. Discrete options are printed in full when the host contract exposes them.

Parameter	Range / options	Default	Host status	Function
Bypass VST3 ID 1652125811	Off, On	Off	Automatable; Bypass	Turns the complete plug-in processing path off or on through the host-visible bypass endpoint.
Mode VST3 ID 3357091	dB, %	dB	Automatable	Selects the operating algorithm, response shape, or tonal character for the named block.
Normalized Level VST3 ID 102865796	0.0000 to 1.0000	0.5000	Automatable	Host-automatable control for Normalized Level. Its full range and default are shown in this table; use it with the related feature section above.

Documentation basis

Prepared from the current public catalog, current local product brief and implementation notes where available, existing English manuals where available, and a direct scan of the installed VST3 host contract. Internal implementation details that are not user-facing are intentionally excluded; all user-facing features and host-visible controls are documented.