



TB AUDIO PLUG-INS
Team Impulse Impact

USER MANUAL

TB Volume

Gain Utility


One level control in decibels or perceived-loudness percent, with smoothed changes and a safety limiter at -0.1 dBFS.

One level control

dB or Sone-based %

-0.1 dBFS safety limiter

20 ms smoothing



Contents

- | | | | |
|-----------|-------------|-----------|--------------------------|
| 01 | Overview | 06 | Recipes |
| 02 | Quick start | 07 | Tips and troubleshooting |
| 03 | Interface | 08 | Parameter reference |
| 04 | Controls | 09 | Version history |
| 05 | Presets | 10 | Support and license |

01 Overview


TB Volume is a one-control gain utility. Drag the large numeric value to set the level, and choose whether it reads in decibels or in a perceived-loudness percentage.

dB mode covers -24 to $+24$ dB. Percent mode uses a Sone-based scale from silence (0%) to 300%, where 100% is unity and 200% aims to sound about twice as loud. Level changes are smoothed to avoid clicks, and a stereo-linked sample-peak limiter keeps the output at or below -0.1 dBFS.

Key features

- One **OUTPUT LEVEL** value: drag up to increase, down to decrease
- dB mode (-24 to $+24$ dB) or Sone-based percent mode (0 to 300%)
- Unity by default: 0 dB or 100%
- 20 ms gain smoothing for click-free changes and automation
- Built-in stereo-linked limiter at -0.1 dBFS with 1 ms lookahead
- Init and user presets

Signal flow




About this manual

This manual describes TB Volume 1.2.2 for Windows (VST3). The current macOS build is version 1.0.8 and may differ from the descriptions here.

02 Quick start

- 1 Insert TB Volume where you need a level change. It starts at unity: 0.0 dB.
- 2 Choose **dB** or **%** under MODE.
- 3 Drag the **OUTPUT LEVEL** value up to make the signal louder or down to make it quieter.
- 4 Automate the level if needed; changes are smoothed over 20 ms.

03 Interface



TB Volume 1.2 interface (portfolio image).

Area	What it does
Preset bar	Previous and next preset, the preset list (Init or a saved user preset; CUSTOM after a change), and Save.
MODE	dB or % scale.
OUTPUT LEVEL	The level value. Drag vertically to change it.

04 Controls

Control	Range · default	What it does
OUTPUT LEVEL	dB: -24 to +24 dB · 0 dB; %: 0 to 300% · 100%	Sets the gain. Drag up to increase volume or down to decrease it. Changes are smoothed over 20 ms.
MODE	dB, % · dB	dB uses the -24 to +24 dB scale. % uses the 0 to 300 percent Sone-based scale, where 100% is unity and 0% is silence.

Both modes drive the same Normalized Level parameter, and both read unity at the default value. Away from unity the two scales are mapped differently, so listen again after switching mode.

Safety limiter

After the gain, a stereo-linked sample-peak limiter with 1 ms of lookahead keeps the output at or below -0.1 dBFS. It is always on and has no controls. Because of the lookahead, TB Volume always has about 1 ms of latency, which the host compensates.

The limiter catches sample peaks, not true peaks. It is a safety net, not a mastering limiter. For deliveries with a true-peak limit, use a true-peak limiter at the end of the chain.

05 Presets

Use the arrows to step through presets, or open the list to choose Init or a saved user preset. Save stores the current settings as a .tbvolumepreset file. The name shows CUSTOM after you change a setting.

06 Recipes

Starting points for common jobs.

Gain staging

Bring a track into a healthy range before other plug-ins.

MODE	dB
OUTPUT LEVEL	As needed, usually -12 to $+6$ dB

- 1 Insert TB Volume first in the chain and set the level before the next plug-in.

Loudness-style rides

Moves that should feel proportional to the ear.

MODE	%
OUTPUT LEVEL	50% to 150%

- 1 200% aims to sound about twice as loud as 100%; 50% about half as loud.

Fade or mute automation

Smooth level automation without clicks.

MODE	%
Automation	Normalized Level

- 1 0% in percent mode is silence.

Output trim with safety

A final trim that cannot clip sample peaks.

OUTPUT LEVEL	As needed
Limiter	Always on at -0.1 dBFS

- 1 If the limiter works constantly, lower the level instead.

07 Tips and troubleshooting

Symptom	What to check
The level changed after switching mode.	Both modes share one parameter but use different scales away from unity. Set the level again.
Loud material sounds squashed.	The safety limiter is working. Lower OUTPUT LEVEL.
There is no sound.	In % mode, 0% is silence.

Symptom	What to check
Automation looks stepped in the host.	Automate Normalized Level; the plug-in smooths changes over 20 ms.

08 Parameter reference

Panel label	Host parameter	Range	Default
OUTPUT LEVEL	Normalized Level	0 to 1 (−24 to +24 dB, or 0 to 300%)	0.5 (0 dB, 100%)
MODE	Mode	dB, %	dB

09 Version history

Version	Changes
1.2.2 · 2026-08-17	Reduced the product-title font so TB VOLUME is fully visible in VST3 hosts. Parameters, gain mapping, state compatibility, and limiter behaviour are unchanged.
1.2.1 · 2026-08-14	Restyled the utility with a brighter die-cast interface and clearer numeric readouts.
1.2.0 · 2026-07-30	Moved the effect logo and product name into a shared rack header, and improved previous/next navigation and preset saving and loading.

10 Support and license

Report problems or request features at github.com/TaebeumKim/TB_Audio-Plugins/issues. Include the plug-in version, your DAW, and your operating system.

TB Audio plug-ins are free for personal and commercial work under the TB Audio Plug-ins Freeware License. If you release or monetize work made with them, add a credit such as **Made with TB Audio Plug-ins by Team Impulse Impact**. Selling or bundling the plug-ins is not allowed.

If the plug-ins help your music, you can support development at ko-fi.com/teamimpulseimpact.