




TB AUDIO PLUG-INS
Team Impulse Impact

USER MANUAL

TB Parallel Reverb

Three-Engine Parallel Reverb

Three reverb engines, Glue, Bright, and Space, run side by side. Each has its own send, character, filters, and solo, and all three meet at one WET / DRY control.



Contents

- 01 Overview
- 02 Quick start
- 03 Interface
- 04 Controls
- 05 Presets
- 06 Recipes
- 07 Tips and troubleshooting
- 08 Parameter reference
- 09 Version history
- 10 Support and license

01 Overview


A single reverb algorithm usually forces a compromise between closeness, colour, and long depth. TB Parallel Reverb runs three independent reverb engines in parallel, so each spatial role can be tuned and auditioned on its own before the final blend.

Glue adds short room or chamber body. Bright adds plate or spring character. Space adds a long hall or a loaded impulse response. Each engine has its own send, pre-delay, width, decay, filters, and colour, and you can solo any engine while you tune it. Because the engines are independent, one can change without forcing the others to follow the same decay or colour.

Key features

- Three parallel engines: Glue (Room, Chamber), Bright (Plate, Spring), and Space (Hall, IR)
- Per-engine SEND, PRE-DELAY, WIDE, DECAY, DIFFUSION, LOW CUT, HIGH CUT, and COLOR
- Engine-specific controls: SIZE, DAMPING, EARLY / LATE, MOD RATE, MOD DEPTH, DISTANCE or TENSION, HF DAMPING, and SHIMMER
- Four hall types and impulse response loading (WAV, AIFF, FLAC) in the Space engine
- ON / OFF and SOLO footswitches on each pedal, with an ENGINE STATE overview
- 99 factory presets in ten banks, plus user presets
- Resizable window that opens at 600 × 520

Signal flow



About this manual

This manual describes TB Parallel Reverb 3.1.0 for Windows (VST3). The current macOS build is version 1.0.4 and may differ from the descriptions here.

02 Quick start

- 1 Insert TB Parallel Reverb on an aux (send) track and leave **WET / DRY** **12** at its default of 100%, which outputs only the reverb. On an insert, lower **WET / DRY** to blend the reverb with the dry sound.

- 2 Choose a factory preset from the preset bar 1 that matches your source, or start from the defaults.
- 3 Press **SOLO** 11 on one pedal to hear that engine alone. Set its **SEND**, **DECAY**, and filters 4 6.
- 4 Repeat for the other engines. Switch off any engine you do not need with its **ON / OFF** footswitch 10.
- 5 Turn solo off and balance the three **SEND** levels in the mix.

03 Interface



Captured from an earlier 3.x build. Version 3.1.0 uses the latest pedal design with the same controls and labels, opens at 600 × 520, and scales the pedals and controls when you resize the window.

- 1 **Preset bar** — previous and next factory preset, the PRESET list, Save, Undo, and Redo.
- 2 **INPUT SPLIT** — the same input feeds all three engines.
- 3 **Mode switch** — ROOM / CHAMBER, PLATE / SPRING, or HALL / IR.
- 4 **SEND, PRE-DELAY, WIDE, DECAY** — level, start time, width, and length of the engine.
- 5 **Glue character** — SIZE, DIFFUSION, DAMPING, and EARLY / LATE.
- 6 **LOW CUT, COLOR, HIGH CUT** — filtering and tone of the engine's return.
- 7 **Bright character** — DIFFUSION, MOD RATE, MOD DEPTH, and DISTANCE (TENSION in Spring mode).
- 8 **Space character** — DIFFUSION, HF DAMPING, and SHIMMER.

- 9 HALL TYPE** — the hall model. BROWSE IR... loads an impulse response for IR mode.
- 10 ON / OFF** — switches the engine on or off.
- 11 SOLO** — plays this engine alone.

- 12 WET / DRY** — final blend of the dry signal and the three returns.
- 13 ENGINE STATE** — shows each engine's state, such as ENGAGED, SOLO, or MUTED.

04 Controls

Controls on every pedal

Control	What it does
Mode switch	Chooses the engine's reverb type: Room or Chamber (Glue), Plate or Spring (Bright), Hall or IR (Space).
SEND	How much of the input enters the engine, which sets the level of its return.
PRE-DELAY	Time before the reverb starts. Longer pre-delay separates the reverb from the source.
WIDE	Stereo width of this reverb layer, in degrees. Check wide settings in mono.
DECAY	How long the reverb lasts. In Space IR mode the label is LENGTH .
DIFFUSION	Turns separate echoes into a smoother wash.
LOW CUT , HIGH CUT	High-pass and low-pass filters on the engine's return. Remove low-frequency wash and harsh highs here.
COLOR	Moves the layer from darker and softer toward brighter and more present.
ON / OFF	Switches the engine on or off. All three engines are on by default.
SOLO	Plays one engine's return alone, without the dry signal, so you can tune it. Only one engine can be soloed at a time.

Ranges and defaults

Control	Glue	Bright	Space
Mode	Room, Chamber · Room	Plate, Spring · Plate	Hall, IR · Hall
SEND	−60 to +6 dB · −12 dB	−60 to +6 dB · −15 dB	−60 to +6 dB · −22 dB
PRE-DELAY	0 to 60 ms · 8 ms	0 to 100 ms · 18 ms	0 to 200 ms · 60 ms
WIDE	0 to 180° · 150°	0 to 270° · 210°	0 to 360° · 240°
DECAY	0.5 to 1 s · 0.75 s	1.5 to 2.5 s · 2 s	0.25 to 10 s · 3.2 s
DIFFUSION	0 to 100% · 65%	0 to 100% · 70%	0 to 100% · 72%
LOW CUT	20 to 1500 Hz · 200 Hz	20 to 1800 Hz · 450 Hz	20 to 1500 Hz · 300 Hz
HIGH CUT	1 to 20 kHz · 9 kHz	1.2 to 20 kHz · 13.5 kHz	1 to 20 kHz · 7.5 kHz
COLOR	0 to 100% · 30%	0 to 100% · 45%	0 to 100% · 25%

Engine-specific controls

Control	Range · default	What it does
GLUE: SHORT AMBIENCE		
SIZE	0 to 100% · 50%	Apparent room size.
DAMPING	0 to 100% · 60%	Darkens the layer as it decays.
EARLY / LATE	0 to 100% · 45%	Balances the first reflections against the later tail.
BRIGHT: PLATE AND SPRING		
MOD RATE	0.02 to 5 Hz · 0.35 Hz	Speed of the gentle pitch movement in the tail.
MOD DEPTH	0 to 20 ms · 1.5 ms	Amount of that movement.
DISTANCE / TENSION	0 to 100% · 35%	Plate distance in Plate mode, spring tension in Spring mode.
SPACE: HALL AND CONVOLUTION		
HALL TYPE	Church, Auditorium, Concert Hall, Studio Hall · Church	The basic hall character in Hall mode.
HF DAMPING	0 to 100% · 45%	Softens high frequencies as the reverb fades.
SHIMMER	0 to 100% · 15%	Adds a bright rising tone to the long tail.
BROWSE IR...	WAV, AIF, AIFF, FLAC	Loads an impulse response file for IR mode. NO IR SELECTED shows until a file is loaded.

Master

Control	Range · default	What it does
WET / DRY	0 to 100% · 100%	Blends the original sound with all enabled reverb returns. 100% outputs only the reverb, for aux use.
SOLO (Reverb Solo)	Off, Glue, Bright, Space · Off	Which engine, if any, is soloed.

Send Gain sets each engine's own return level; WET / DRY sets the overall relationship between the source and the summed reverb. Balance the sends first, then set WET / DRY.

05 Presets

Step through the factory presets with the arrows in the preset bar **1**, or open the PRESET list. LOAD USER PRESET... opens a .tbprpreset file, and Save stores the current settings as one. The name shows CUSTOM after you change a preset. Undo and Redo step through recent changes.

Bank	Presets
Essentials	Three Engine Balance, Natural Space, Clean Bus Wash, Dark Bus Glue, Wide Open
Vocals	Vocal Plate Halo, Intimate Vocal Room, Pop Vocal Sheen, Ballad Bloom, Lead Vocal Forward, Breathy Air, Dark Vocal Chamber, Wide Vocal Double, Tight Rap Slap, Gospel Hall, Whisper Cloud, Retro Vocal Spring
Drums	Drum Room Snap, Tight Booth, Ambient Kit, Snare Plate, Gated Burst Room, Big Rock Room, Jazz Brush Room, Lo-Fi Drum Box, Trap Slap, Percussion Shine, Kick Weight Room, Tom Hall
Guitar	Clean Amp Spring, Surf Splash, Crunch Room, Lead Guitar Hall, Acoustic Air, Shoegaze Wash, Slide Chamber, Funk Tight Room, Metal Rhythm Plate, Dream Swell
Keys	Grand Piano Stage, Upright Room, Warm Rhodes, Wurli Spring, Church Organ, Tight Clav, Felt Piano Intimate, Cinematic Piano, Toy Piano Box, Electric Bloom
Synth & Pad	Wide Pad Bed, Pluck Bounce, Arp Shimmer, Saw Stack Space, Glass Bell, Warm Analog Room, Ethereal Lead, Drone Bed, Retro Synth Chamber, Hyper Wide Stack, Soft Synth Keys, Motion Pad
Bass & Low End	Subtle Bass Room, Upright Wood, Synth Bass Depth, Bass Amp Chamber, Clean Low Lift, Dub Cavern
Strings & Orchestra	Concert Strings, Solo Violin Hall, Warm Cello Room, Full Score Hall, Chamber Quartet, Epic Trailer Space, Harp Air, Brass Stage
Ambient & Shimmer	Shimmer Cloud, Octave Bloom, Infinite Drift, Glacier, Cathedral Light, Soft Focus, Deep Space, Slow Swell, Frozen Air, Spring Tape Dream, Night Sky, Underwater, Choir Of Ghosts, Endless Hall
Special FX	Metal Tank, Broken Spring, Warped Tape Space, Tiny Speaker Box, Backwards Feel, Alien Transmission, Bit Cavern, Pitch Riser, Sonar Ping, Haunted Room

06 Recipes

Starting points for common jobs. Adjust them by ear.

Vocal depth without mud

A lead vocal that stays forward with space behind it.

Preset	Lead Vocal Forward or Vocal Plate Halo
--------	--

Bright PRE-DELAY	20 to 40 ms
------------------	-------------

LOW CUT	Raise on every engine
---------	-----------------------

- 1 Solo each engine and cut the lows until the return stops clouding the voice.
- 2 Keep Space low in the send so the tail sits behind the vocal.

Drum room plus plate

Body from a room and snap from a plate.

Glue	Room, short DECAY
------	-------------------

Bright	Plate, SEND lower
--------	-------------------

Space	OFF
-------	-----

- 1 Switch Space off with ON / OFF.
- 2 Raise Glue SEND until the kit sounds like one room.

Ambient wash

Long, soft tails for pads and atmospheres.

Preset	Shimmer Cloud or Endless Hall
--------	-------------------------------

Space DECAY	6 to 10 s
-------------	-----------

SHIMMER	Taste
---------	-------

- 1 Lower HIGH CUT on Space if the tail gets bright and busy.

Real space with an IR

Place a source in a recorded room or hall.

Space mode	IR
------------	----

Impulse	BROWSE IR...
---------	--------------

Glue / Bright	Low or OFF
---------------	------------

- 1 Load a WAV, AIFF, or FLAC impulse response.
- 2 Shape it with LENGTH, LOW CUT, and HIGH CUT.

07 Tips and troubleshooting

Symptom	What to check
I only hear reverb.	WET / DRY is at 100%, the default for aux use. Lower it on an insert.
I cannot hear the dry sound or the other engines.	An engine is soloed. Turn SOLO off before you export.
The reverb is muddy.	Raise LOW CUT on each engine, starting with Space.
The reverb is harsh or splashy.	Lower HIGH CUT or COLOR, or raise DAMPING (Glue) or HF DAMPING (Space).
IR mode makes no sound.	No impulse response is loaded (NO IR SELECTED). Load one with BROWSE IR...
The mix collapses in mono.	Lower WIDE on the engines and check again in mono.
CPU use is high.	Switch off engines you are not using.

08 Parameter reference

Panel label	Host parameter	Range	Default
GLUE			
Mode switch	Glue Mode	Room, Chamber	Room
ON / OFF	Glue Enabled	Off, On	On
SEND	Glue Send Gain	−60 to +6 dB	−12 dB
PRE-DELAY	Glue Pre-Delay	0 to 60 ms	8 ms
WIDE	Glue Wide	0 to 180°	150°
DECAY	Glue Decay	0.5 to 1 s	0.75 s
SIZE	Glue Size	0 to 100%	50%
DIFFUSION	Glue Diffusion	0 to 100%	65%
LOW CUT	Glue High Pass	20 to 1500 Hz	200 Hz
HIGH CUT	Glue Low Pass	1 to 20 kHz	9 kHz
EARLY / LATE	Glue Early Late Mix	0 to 100%	45%
DAMPING	Glue Damping	0 to 100%	60%
COLOR	Glue Color	0 to 100%	30%
BRIGHT			
Mode switch	Bright Mode	Plate, Spring	Plate
ON / OFF	Bright Enabled	Off, On	On
SEND	Bright Send Gain	−60 to +6 dB	−15 dB
PRE-DELAY	Bright Pre-Delay	0 to 100 ms	18 ms
WIDE	Bright Wide	0 to 270°	210°
DECAY	Bright Decay	1.5 to 2.5 s	2 s
DIFFUSION	Bright Diffusion	0 to 100%	70%
MOD RATE	Bright Modulation Rate	0.02 to 5 Hz	0.35 Hz
MOD DEPTH	Bright Modulation Depth	0 to 20 ms	1.5 ms
DISTANCE / TENSION	Bright Plate Distance Spring Tension	0 to 100%	35%
LOW CUT	Bright High Pass	20 to 1800 Hz	450 Hz
HIGH CUT	Bright Low Pass	1.2 to 20 kHz	13.5 kHz
COLOR	Bright Color	0 to 100%	45%
SPACE			
Mode switch	Space Mode	Hall, IR	Hall
ON / OFF	Space Enabled	Off, On	On
SEND	Space Send Gain	−60 to +6 dB	−22 dB
PRE-DELAY	Space Pre-Delay	0 to 200 ms	60 ms

Panel label	Host parameter	Range	Default
WIDE	Space Wide	0 to 360°	240°
DECAY / LENGTH	Space Decay / Length	0.25 to 10 s	3.2 s
HALL TYPE	Space Hall Type	Church, Auditorium, Concert Hall, Studio Hall	Church
DIFFUSION	Space Diffusion	0 to 100%	72%
HF DAMPING	Space HF Damping	0 to 100%	45%
LOW CUT	Space High Pass	20 to 1500 Hz	300 Hz
HIGH CUT	Space Low Pass	1 to 20 kHz	7.5 kHz
COLOR	Space Color	0 to 100%	25%
SHIMMER	Space Shimmer	0 to 100%	15%
MASTER			
WET / DRY	Wet/Dry Mix	0 to 100%	100%
SOLO	Reverb Solo	Off, Glue, Bright, Space	Off

The path of the loaded impulse response is stored with the plug-in state rather than as a host parameter. If you move the file, load it again with BROWSE IR...

09 Version history

Version	Changes
3.1.0 · 2026-09-30	Brought the latest Glue, Bright, and Space pedal design and the current parallel reverb engine to Windows VST3. The default window is now 600 × 520, and the engine pedals and controls scale when you resize it.
3.0.2 · 2026-08-21	Windows maintenance release.
3.0.1 · 2026-08-03	Redesigned the Glue, Bright, and Space pedals in green, orange, and crimson. Routing, engine bypass and solo, factory presets, parameter IDs, and sound were unchanged.

10 Support and license

Report problems or request features at github.com/TaebeumKim/TB_Audio-Plugins/issues. Include the plug-in version, your DAW, and your operating system.

TB Audio plug-ins are free for personal and commercial work under the TB Audio Plug-ins Freeware License. If you release or monetize work made with them, add a credit such as **Made with TB Audio Plug-ins by Team Impulse Impact**. Selling or bundling the plug-ins is not allowed.

If the plug-ins help your music, you can support development at ko-fi.com/teamimpulseimpact.