


TB_Parallel Reverb

Multi-Engine Parallel Reverb English User Manual

GLUE + BRIGHT + SPACE

Three independent wet engines, per-engine send control, focused solo auditioning, tonal COLOR macros, unified LOW CUT / HIGH CUT workflow, and final WET/DRY blending.




Version 1.0.0 - VST3 category: Fx / Reverb

English User Manual

TB_Parallel Reverb - Multi-Engine Parallel Reverb

TB_Parallel Reverb is a three-engine parallel reverb designed to keep the dry source clear while building a rich, dimensional wet field. The GLUE, BRIGHT, and SPACE engines are processed independently, summed into a wet return bus, and then blended with the dry signal at the final WET/DRY stage.



Core Routing

The dry signal is copied into three independent reverb engines. Their wet returns are summed, then blended against the dry path. Per-engine SEND controls the return gain; final WET/DRY controls the global dry/wet balance.

Quick Start

A practical workflow for building a space

- Start with conservative SEND values. SPACE should usually begin very low, close to its -22 dB default.
- Use GLUE first to create the short room or chamber body around the source.
- Use BRIGHT to add plate or spring character, sparkle, and a musically colored tail.
- Use SPACE for depth. In Hall mode, pre-delay may automatically lock to a 1/32 or 1/16 note if host BPM is available.
- Use SOLO to audition each engine without dry signal, then use WET/DRY for the final global balance.

Engine Overview

Each engine has a different spatial role.

Engine	Modes	Role	Common Uses
GLUE	Room / Chamber	Short reflections, body, mix glue	Vocal proximity, drum room, shared space
BRIGHT	Plate / Spring	Colorful tail, metallic shine, character	Vocal tail, snare plate, guitar spring texture
SPACE	Hall / IR	Long depth, background field, convolution space	Cinematic depth, realistic IR ambience, lush pads

Shared Engine Controls

Controls found in the upper area of each engine card

Control	Range / Behavior	Description
Mode Buttons	Both buttons can be off	Selects the active reverb type. If both buttons are off, the engine is bypassed.
SOLO	Exclusive per-engine solo	Auditions only the selected wet return without dry. The focused panel glows and other engines dim.
PRE-DELAY	GLUE 0-60 ms / BRIGHT 10-100 ms / SPACE 40-200 ms	Offsets the reverb start after the dry source. SPACE Hall can tempo-sync to 1/32 or 1/16 when possible.
WIDE	GLUE 0-180 deg / BRIGHT 0-270 deg / SPACE 0-360 deg	Controls the stereo spread of the wet return. Lower values move closer to mono.
SEND	-60 dB to +6 dB	Per-engine wet return gain. This is a send/return gain, not a local dry/wet mix.
DECAY / LENGTH	Engine-specific range	Controls reverb tail length or IR tail length.

GLUE Controls

Shared Room / Chamber controls

Control	Range / Default	Meaning
SIZE	0-100%, default 50%	Controls the perceived room/chamber size.
DIFFUSION	0-100%, default 65%	Controls reflection density and spread.
DAMPING	0-100%, default 60%	High-frequency damping. Higher values sound darker and smoother.
EARLY / LATE	0-100%, default 45%	Blends early reflections against the late reverb tail.
LOW CUT	20-1500 Hz, default 200 Hz	Removes low-frequency buildup from the wet return.
COLOR	0-100%, default 30%	Adds tape-like soft clipping, darker tilt, and low-mid body to the wet return.
HIGH CUT	1000-20000 Hz, default 9000 Hz	Controls the upper brightness of the GLUE return.

BRIGHT Controls

Shared Plate / Spring controls

Control	Range / Default	Meaning
DIFFUSION	0-100%, default 70%	Controls plate/spring density.
MOD RATE	0.02-5 Hz, default 0.35 Hz	Controls modulation speed.
MOD DEPTH	0-20 ms, default 1.5 ms	Controls modulation depth.
DISTANCE / TENSION	0-100%, default 35%	Acts as plate distance in Plate mode and spring tension in Spring mode.
LOW CUT	20-1800 Hz, default 450 Hz	Reduces mud and low-mid masking.
COLOR	0-100%, default 45%	Adds sparkle and exciter-like harmonic color to the wet return.
HIGH CUT	1200-20000 Hz, default 13500 Hz	Controls brightness, edge, and shimmer smoothness.

SPACE Controls

Hall / IR depth engine

Control	Range / Default	Meaning
HALL TYPE	Church, Auditorium, Concert Hall, Studio Hall	Selects the hall model in Hall mode.
BROWSE IR	Visible in IR mode	Loads a user-selected impulse response file.

Control	Range / Default	Meaning
DECAY / LENGTH	0.25-10 s, default 3.2 s	Acts as Hall decay or IR tail length.
DIFFUSION	0-100%, default 72%	Controls Hall tail density.
HF DAMPING	0-100%, default 45%	Controls high-frequency decay in long spaces.
LOW CUT	20-1500 Hz, default 300 Hz	Prevents long reverb from building up low-end mud.
COLOR	0-100%, default 25%	Adds bloom and air to the SPACE tail.
HIGH CUT	1000-20000 Hz, default 7500 Hz	Sets the distance and darkness of the background space.

Final Mix and Solo

How to place the reverb in a mix

Final WET/DRY blends the untouched dry signal with the summed wet return. 0% is dry only, while 100% is wet only. When SOLO is active, the dry path is excluded and only the selected wet engine is heard; the final WET/DRY setting is bypassed for auditioning.

Situation	Suggested Move
General mix	Balance GLUE and BRIGHT first, then add SPACE quietly. Use final WET/DRY last.
Auditioning tone	Use SOLO and adjust SEND, COLOR, LOW CUT, and HIGH CUT for that engine.
Dry attack gets blurred	Increase PRE-DELAY, lower SEND, or raise LOW CUT.
Reverb sounds muddy	Raise LOW CUT, reduce SPACE SEND, and use less late tail.
Reverb feels plain	Increase BRIGHT COLOR or SPACE COLOR and widen WIDE.

Starting Points

Quick musical targets

Target	GLUE	BRIGHT	SPACE
Clear vocal	Room, short decay, low SEND	Plate, COLOR 40-60%, HIGH CUT 10-14 kHz	Very low SEND, 2.5-3.5 s
Snare plate	Short room body	Plate, medium SEND, 15-25 ms pre-delay	Mostly off or very low
Vintage guitar	Chamber, COLOR 35-55%	Spring, adjust TENSION	Low Hall or selected IR
Dreamy pad	Wider WIDE, balanced early/late	Subtle Plate tail	Long Hall/IR, more COLOR and WIDE

Note

Because the plug-in is fully parallel, wet returns can accumulate quickly. Start with low SEND values, especially on SPACE.