


TB Jewel Digger & Finder

USER MANUAL



Purpose

Turns incoming notes into tuned resonance and sparkling crystal-like motion.

License: MIT License

This software is licensed under the MIT License. Copyright (c) 2026 TaebeumKim. See the repository LICENSE file for the full terms.

Controllable properties

Each control is listed by its panel name. Use the description to decide what to listen for, then make small changes in the context of the music.

Control and settings	What it changes
Amount Range: 0 to 1 Default: 0.35	Sets how strongly the named effect changes the sound.
Base Low Cut Range: Off, On Default: Off	Removes low frequencies before they enter the main resonant section.
Base Note Range: C0 to C8 Default: A3	Sets the root note used to build the resonant pattern.
Bypass Range: Off, On Default: Off	Turns the complete effect off or on for a direct before-and-after comparison.
Crystal Damp Range: 0 to 1 Default: 0.45	Darkens the crystal particles and softens their high-frequency tail.
Crystal Mix Range: 0 to 1 Default: 0.35	Sets the level of the crystal particle layer.
Crystal Only Range: Off, On Default: Off	Lets you hear only the crystal layer.

Control and settings	What it changes
Crystal Send Range: 0 to 1 Default: 0.8	Sets how much sound is sent into the crystal particle section.
Crystal Spread Range: 0 to 1 Default: 0.6	Spreads the crystal particles across the stereo field.
Density Range: 1 to 24 Default: 12	Sets how many events or layers overlap at once.
Division Range: 1/64, 1/32, 1/16, 1/8, 1/4, 1/2, 1/1 Default: 1/4	Chooses the tempo division used when Rate Sync is on.
Filter Range: Find, Dig Default: Find	Chooses Find for highlighting resonances or Dig for carving around them.
Grain Attack Range: 0.01 to 0.75 Default: 0.35	Sets how quickly this part reacts when a sound begins.
Grain Decay Range: 0.01 to 0.95 Default: 0.65	Sets how long this part takes to fade or return.
Grain Delay Range: 0 to 1000 Default: 140	Sets how long the crystal particles wait before they are heard.
Grain Feedback Range: 0% to 100% Default: 45%	Returns processed sound into the effect to extend or intensify it.
Grain Size Range: 15 to 400 Default: 120	Sets the amount of particle detail or random variation.
Mix Range: 0 to 1 Default: 1	Blends the original sound with the processed sound.

Control and settings	What it changes
Motion Range: Still, Arp Up, Arp Down, Ramp Up, Ramp Down, Sine, Square, Triangle, Musical Random, Chaos Default: Arp Up	Chooses how the resonant notes move over time.
Motion Depth Range: 0 to 24 Default: 7	Sets how far the resonant pattern moves through the selected scale.
Output Range: -18 to 6 Default: 0	Sets the final listening level after processing.
Pitch Range: -24 to 24 Default: 12	Moves the pitch of the processed sound up or down.
Program Range: 9 factory programs Default: Initialize	Loads a factory starting point. Adjust the controls afterward to fit the current sound.
Q Range: 0.35 to 24 Default: 6	Sets how wide or narrow the selected frequency focus is.
Random Range: 0 to 1 Default: 0.5	Adds variation to the resonant movement and particle pattern.
Rate Range: 0.02 to 64 Default: 0.5	Sets how quickly the movement repeats.
Rate Sync Range: Off, On Default: Off	Locks Motion speed to the song tempo.
Reverse Chance Range: 0 to 100 Default: 0	Sets whether or how often processed fragments play backward.

Control and settings	What it changes
Scale Range: Chromatic, Major, Minor, Major 7, Minor 7, Diminished, Augmented, Pentatonic Major, Pentatonic Minor, Mixolydian Default: Chromatic	Chooses the set of notes used by the moving resonances.
Shovel Range: Crystal, Hollow, Bow, Hammer, Metal, Dirt Default: Crystal	Chooses the material-like character of the resonant layer.