


BRIGHTEDGE

Autopilot

Self Connecting Pages

Integration Overview

AUTOPILOT – Self Connecting Pages




AUTOPILOT – Self Connecting Pages

SDK and BrightEdgeUtil.java

BrightEdgeUtil class

- ▼  com.aem.customer.core.util
 - ▶  BrightEdgeUtil.java

1. Add BrightEdgeUtil class, For the class add the be-ixf-java-sdk-11.jar as dependency to pom.xml.
2. Assign three variables headOpen, BodyString, and closeString with the respective methods.
3. In the template, add the variables in the respective locations.



AUTOPILOT – Self Connecting Pages

BrightEdgeUtil.java

```
package com.aem.customer.core.util;

import javax.annotation.PostConstruct;

@Model(adaptables = SlingHttpServletRequest.class,
defaultInjectionStrategy = DefaultInjectionStrategy.OPTIONAL)
public class BrightEdgeUtil {

    private IXFConfiguration ixfConfig;

    private String headOpen;
    private String bodyString;
    private String closeString;
    private String pagePath;
    private String hostname;
    private String country;

    @Self
    private SlingHttpServletRequest request;

    @Self
    private SlingHttpServletResponse response;

    @PostConstruct
    protected void init() throws Exception {
        String currenturl = request.getRequestURL().toString();

        IXFConfiguration ixfConfig = new IXFSDKConfiguration();
        ixfConfig.setProperty(IXFConfiguration.CAPSULE_MODE, IXFConfiguration.REMOTE_PROD_CAPSULE_MODE);
        ixfConfig.setProperty(IXFConfiguration.ACCOUNT_ID, "f00000000041543");
        ixfConfig.setProperty(IXFConfiguration.API_ENDPOINT, "https://ixfd1-api.bc0a.com/");

        // BE IXF: Update CHARSET if needed
        ixfConfig.setProperty(IXFConfiguration.CHARSET, "UTF-8");

        // BE IXF: By default, all URL parameters are ignored. If you have URL
        // parameters that add value to page content. Add them to this config value,
        // separated by the pipe character (|).
        ixfConfig.setProperty(IXFConfiguration.WHITELIST_PARAMETER_LIST, "ixf");
    }
}
```

AUTOPILOT – Self Connecting Pages

BrightEdgeUtil.java

```
// Log Level
// options:LOG_LEVEL_ALL,LOG_LEVEL_INFO,LOG_LEVEL_WARN,LOG_LEVEL_ERROR,LOG_LEVEL_DEBUG
ixfConfig.setProperty(IXFConfiguration.LOG_LEVEL, IXFConfiguration.LOG_LEVEL_ERROR);

// ixfConfig.setProperty(IXFConfiguration.PAGE_ALIAS_URL,"https://" + hostname + "/" + this.pagePath);
ixfConfig.setProperty(IXFConfiguration.PAGE_ALIAS_URL, currenturl);

// Optional parameters
// ixfConfig.setProperty(IXFConfiguration.PROXY_HOST, hostname);
// ixfConfig.setProperty(IXFConfiguration.PROXY_PORT, "1234");
// ixfConfig.setProperty(IXFConfiguration.PROXY_PROTOCOL, "https");

IXFSDKParameters parameters = new IXFSDKParameters(request);
IXFSDKClient client = new IXFSDKClient(ixfConfig, response, parameters);

headOpen = client.getHeadOpen();
bodyString = client.getBodyString("body_1");
closeString = client.close();
}

public IXFConfiguration getIxfConfig() {
    return ixfConfig;
}

public String getHeadOpen() {
    return headOpen;
}

public String getBodyString() {
    return bodyString;
}

public String getCloseString() {
    return closeString;
}
}
```

AUTOPILOT – Self Connecting Pages

Add calls to template

```
<!doctype html>
<html>
<head>
<!-- BE IXF: BE IXF: Place getHeadOpen just inside of the head tag -->
<sly data-slyuse.
brightEdgeUtil="{com.aem.customer.core.util.BrightEdgeUtil' @pagePath=currentPage.Path}"/>
${brightEdgeUtil.headOpen @context='unsafe'}
</head>
<body>
<footer>
<!-- BE IXF: The following <div> block needs to be placed in the location where the link block will be displayed
BE IXF: For your website, the location is above/below ...-->
<div class="be-ix-link-block">
${brightEdgeUtil.bodyString @context='unsafe'}
${brightEdgeUtil.closeString @context='unsafe'}
</div>
</footer>
</body>
</html>
```

AUTOPILOT – Self Connecting Pages

On-page Diagnostic Information

```
<!-- be_ixf, sdk, gho-->
<meta name="be:sdk" content="java_sdk_1.6.5" />
<meta name="be:timer" content="165ms" />
<meta name="be:norm_url" content="http://localhost:4502/content/brightedge-
plugin/test.html" />
<meta name="be:capsule_url" content="https://ixfd1-
api.bc0a.com/api/ixf/1.0.0/get_capsule/f00000000041543/1404993592" />
<meta name="be:api_dt" content="pny_2022; pnm_11; pnd_09; pnh_07; pnmh_31;
pn_epoch:1668007863136" />
<meta name="be:mod_dt" content="pny_1969; pnm_12; pnd_31; pnh_16; pnmh_00;
pn_epoch:0" />
<meta name="be:orig_url" content="http://localhost:4502/content/brightedge-
plugin/test.html" />
<meta name="be:messages" content="0" />
    </head>
    <body>
```

Example page capsule (HTML block)

BRIGHTEDGE CONFIDENTIAL

AUTOPILOT – Self Connecting Pages

Example page capsule (JSON block)

```
{
  "account_id": "f00000000012345",
  "date_published": 1635531464015,
  "key": "9999651116",
  "is_universal_capsule_enabled": "false",
  "capsule_version": "1.0.0.0",
  "engine_version": "1.0.0.0",
  "version": 2,
  "date_created": 1635531464015,
  "nodes": [
    {
      "feature_group": "body_1",
      "engine_version": "1.0.0.0",
      "content": "{\\\"url\\\":\\\"https://www.example.com/products/xyz\\\", \\\"anchor_text\\\":\\\"Vulputate enim nulla\\\"},{\\\"url\\\":\\\"https://www.example.com/products/abc\\\", \\\"anchor_text\\\":\\\"Pretium nibh ipsum\\\"},{\\\"url\\\":\\\"https://www.example.com/industries/real-estate\\\", \\\"anchor_text\\\":\\\"Ultricies integer quis\\\"},{\\\"url\\\":\\\"https://www.example.com/products/flagship\\\", \\\"anchor_text\\\":\\\"Ut eu sem\\\"},{\\\"url\\\":\\\"https://www.example.com/solutions/industries/mortgage\\\", \\\"anchor_text\\\":\\\"Lorem Ipsum Dolor\\\"}\\n\",
      "date_published": 1635531464015,
      "date_created": 1635531464349,
      "type": "bodystr",
      "publishing_engine": "link-block"
    },
    {
      "feature_group": "_head_open",
      "engine_version": "1.0.0.0",
      "content": "\\n\\n",
      "date_published": 1635531464015,
      "date_created": 1635531464409,
      "type": "headstr",
      "publishing_engine": "pixel"
    }
  ],
  "config": {},
  "publishing_engine": "ixf-compiler"
}
```

AUTOPILOT – Self Connecting Pages

Key take away

Default capsule	Page capsule
key = "-0"	key is not "-0"

Block display options: HTML or JSON

Link assignment refreshes every 30 days, weekly 404 check

BrightEdge Monitoring attributes:

- encapsulate the link in a `<div class="be-ix-link-block"></div>`
- use `<a class="be-related-link" href=""></a>` for the links

BRIGHTEDGE

Thank You!

BRIGHTEDGE CONFIDENTIAL