
Ghost Studio Illustrated Operating Manual

Hybrid Elite Mafia

A practical guide to the 3D rack, preset files, Full DAW, chains, radio, writing tools and all 27 DAW processor types.

Start with the workspace map. Match the numbered diagrams to the control names on your screen, then follow the steps. Control diagrams simplify the layout; they are not screenshots.

Keep a downloaded project backup before changing devices. A local browser save is not cloud sync. Rack presets, DAW plugins, projects and prompt text use different loaders.



Live app: https://ghost-daw-mobile.tthehybridelitemafia.chatgpt.site

Contents

Contents 2

1. Choose the right workspace 5

2. Play a song in the 3D rack 6

3. Adjust Dynamics A 7

4. Import and save presets 9

5. Save and export a rack project 10

6. Use the ZIP plugin and prompt library 11

7. Start here: your first session 13

8. Where everything lives 14

9. Import, save and reopen 15

10. Playback, tempo and timeline 16

11. Faders, knobs and the master bus 18

12. Track detail and clip editing 19

13. Build and insert your own plugin chain 21

14. Choose genre and source chains 22

15. Analyze stems and remove noise 24

16. Use Ghost and understand API access 25

17. MIDI instruments and recording 27

18. Automation and MIDI learn 29

19. Music Library and Prompt Encyclopedia 30

20. Create or rewrite lyrics 31

21. Export the mix or stems 33

22. Listen and adjust the radio EQ 34

23. Upload and manage station songs 35

24. Choose the correct file loader 37

25. Fix common problems 38

Processor 1: High-pass filter 39

Processor 2: Low shelf 40

Processor 3: Parametric EQ 41

Processor 4: High shelf 42

Processor 5: Low-pass filter 43

Processor 6: Compressor 44

Processor 7: Stereo delay 45

Processor 8: Soft saturation 46

Processor 9: Output trim 47

Processor 10: Vocal 73 Front End 47

Processor 11: Smart De-Esser Pro 49

Processor 12: FET Vocal Snap 50

Processor 13: Opto Vocal Leveler 51

Processor 14: Vocal Air EQ 52

Processor 15: Vocal Doubler Wide 53

Processor 16: Plate Vocal Space 54

Processor 17: Throw Delay Vox 56

Processor 18: Master Tone EQ 57

Processor 19: Glue Bus Master 58

Processor 20: Vari-Mu Finish 60

Processor 21: Passive Master Air 61

Processor 22: Tape Master 30 62

Processor 23: Stereo Image Control 63

Processor 24: Dynamic Master Control 64

Processor 25: Final Limit Clipper 65

Processor 26: Master Rack Pro - Complete Mastering Chain 66


Processor 27: Stem Cleanup 70

Glossary 71

1. Choose the right workspace

Home / Ghost Rack > links below the console

The app has separate audio sessions and several kinds of saved files. Start by choosing the workspace for your task.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Open the studio. The photographic console is Ghost Rack; /rack opens the same console directly.
2	For one-file compression, stay in Ghost Rack. For stems, editing or multi-track mixing, use Full DAW below the rack.
3	Use Radio to listen to or upload station tracks. A radio upload does not load a track into the rack or DAW.
4	Use Lyrics for writing. Use Plugin workshop for actual DAW inserts; the prompt library supplies text instructions.
5	Keep the manual in another tab. Use its search box to find the exact label on your screen.

Control details

Control or item	What it does
Audio sessions	Ghost Rack, Full DAW and Radio have separate playback state. Loading a song in one does not load it in the others.
Where files live	Rack presets and DAW saves are local to that browser. Radio uploads are stored on the station. A downloaded backup travels with you.


Control or item	What it does
Phone use	Open the site in your phone browser. Scroll below the photographic rack to reach workspace links and the prompt library.

Illustrations in this manual are labeled control diagrams and operation sequences, not screenshots. Match the printed control names; responsive layouts can place them differently.

2. Play a song in the 3D rack

Ghost Rack > Upload audio and transport

The rack runs one Dynamics A compressor on a mono or stereo audio file. Its other category buttons open plugin references.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Tap Upload audio and select your recording. Wait for the filename and duration to appear.
2	Press Play. Move the seek bar to another part of the song; Pause holds the position.
3	Use Previous or Next to jump five seconds. These are not previous-song and next-song controls.
4	Watch the IN and OUT meters while listening. The waveform is the output signal, not a measurement of mastering quality.
5	To record instead, tap Record and allow the microphone. Tap Record again to finish; the take becomes the rack source. Save your existing project before replacing its source.

Control details

Control or item	What it does
Play with no file	Loads the synthesized sound check. This is demo audio, not your song.
Microphone monitoring	Listening is muted while recording to reduce feedback; the take is captured dry.
Track limits	Rack import supports mono and stereo. Browser codec and memory limits still apply.
Separate session	The rack does not insert itself into a Full DAW track. Export a WAV if you want to transfer its processed result.

3. Adjust Dynamics A

Ghost Rack > six dials and action buttons

Drag a dial upward to increase it and downward to decrease it. Start with Ghost Neutral Start when you want no compression or added gain.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Open Presets and load Ghost Neutral Start if you have imported it. Its ratio is 1:1 and makeup is 0 dB.
2	Play a representative loud section. Enable IN and keep BYPASS off when auditioning processing.
3	Drag one dial at a time. On a keyboard, use arrow keys; Shift gives finer adjustment during dragging.
4	Compare BYPASS and IN at similar listening levels. Read GAIN REDUCTION to see how much the compressor is acting.

Step	Action and result
5	Use A/B to switch between two settings snapshots. Save or download a preset when you want to keep a setting.


Control details

Control or item	What it does
Threshold	-60 to 0 dB. A threshold by itself does not determine gain reduction; source level and ratio matter.
Ratio	1:1 to 20:1. At 1:1, no compression is applied.
Attack / Release	Attack: 0-1,000 ms. Release: 1-1,000 ms. Timing values must be valid, not all literal zero.
Knee / Makeup	Knee: 0-40 dB. Makeup: -12 to +24 dB.
IN / BYPASS	IN off or BYPASS on passes the dry source. Neither unloads your song.
SOLO	There is only one source in this rack. SOLO is a state indicator and does not isolate a separate stem or detector signal.
RESET / double-click	Restores the rack's original default settings, not Ghost Neutral Start: -18 dB, 4:1, 10 ms, 120 ms, 6 dB knee, +3 dB makeup.
A/B	Changes settings snapshots, not source recordings. The current slot is shown on the button.

4. Import and save presets

Ghost Rack > Presets

A preset contains Dynamics A settings only. Importing it updates the six dials without replacing the loaded song.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Download Ghost-Dynamics-A-Neutral.json to your device if you want the neutral starter.
2	Open Presets > Import preset. Choose the JSON from Downloads. Read the result message; it names the preset loaded.
3	Select Ghost Neutral Start in Load preset. Check ratio 1:1 and makeup 0 dB on the rack.
4	To keep your own changes, adjust the dials, open Presets, enter a name, then tap Save preset.
5	Tap Download current settings for a portable file, or Export saved bank to back up all user presets.
6	After a refresh, open Presets > Load preset. If the name is still listed, this browser retained it. Export before clearing browser data.

Control details


Control or item	What it does
Compatible input	Dynamics A preset JSON, its exported bank, the six numeric parameters, or compressor settings extracted from a Ghost Rack project.

Control or item	What it does
Not compatible	A DAW .ghostplugin, lyrics draft, ZIP package or VST/AU preset is not a Dynamics A preset. File extension alone does not make formats interchangeable.
Import limits	10 MB per import, 1-100 presets per file and 200 user presets in the browser. Invalid or out-of-range controls are rejected.
Units	Attack and release are milliseconds. Other values must use the supported numeric ranges.
Duplicate names	The importer adds a numbered suffix rather than overwriting an existing named preset.
Storage unavailable	The result message warns if a preset is only available for the current session. Download a copy immediately.
Prompt reference library	This separate button opens text prompts; it does not apply their settings to the compressor.

5. Save and export a rack project

Ghost Rack > Projects

A rack project preserves its source audio, current settings, A/B snapshots, playback position and switch states. A WAV contains rendered sound only.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Open Projects > Save project before replacing a recording or leaving the rack. Keep the downloaded JSON.
2	To restore it, use Projects > Open project and choose that rack project. This can replace the current source and pauses playback.

Step	Action and result
3	To create an audio file, load your source, set IN/BYPASS and compressor controls, then choose Export WAV.
4	If export reports an output above 0 dBFS, lower Makeup and export again. The rack refuses a clipped integer WAV.
5	Open the downloaded WAV and listen. Keep the project separately if you need editable settings.


Control details

Control or item	What it does
WAV format	Rack export is 16-bit PCM at the source buffer's sample rate, with one or two channels.
Monitor volume	Affects listening but is not included in the exported WAV.
Project limit	Rack project import is limited to 180 MB. Use its own project loader, not the Full DAW project loader.
Settings switches	Animated waveform, LED meters and Reduced motion change visuals. Load sound check replaces the source with the procedural demo.

6. Use the ZIP plugin and prompt library

Rack category tiles / Tools / AI prompts > Plugin Prompt Forge

This library contains 66 plugin references and 531 preset prompts. It helps you write instructions; it is not a bank of 66 working audio effects.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Tap a rack category such as Dynamics or Cleanup. The page scrolls to matching references below the console.
2	Search by name or purpose. Clear filters if a card appears missing; favorites and type filters narrow the results.
3	Choose a preset on the card and inspect its parameters and prompt text. Copy the text you need.
4	Add references to the chain, open the chain drawer, and use its up/down controls to order them. Copy chain prompt exports text.
5	Open Tools for Chain recipes, or AI prompts for Prompt builder. Fill the visible fields and copy the resulting instruction.
6	For a real audio change in this app, return to Dynamics A or use Full DAW > Plugin workshop.


Control details

Control or item	What it does
Built-in / Chat-built labels	These describe references in the supplied library. They do not prove an effect is implemented in this app.
Artifact triage	Choose the problem you hear, read the guidance, and audition any real processing cautiously. The panel does not analyze an uploaded recording.
Favorites / chain	Stored locally in this browser. Copy important chains to a file for a backup.
Preset prompts	These are text, not the JSON settings used by the rack importer.

7. Start here: your first session

Top of the DAW page

A song file contains the recording, including the singer. Stems are separate recordings such as vocals, drums and bass. MIDI contains notes, not the original singer.



Control map: numbers identify the labeled controls for this task.

Follow these steps


Step	Action and result
1	From Ghost Rack, open Full DAW below the console. Tap DAW, then Import song / stems and choose your song or aligned stems.
2	Wait until importing finishes. Read the import report if any file failed. Imported stems start together at 0:00.
3	Press Play. If the app says it is preparing audio, wait for preparation to finish. Stop cancels preparation.
4	Use the Mixer to balance stems. Select a stem before opening Track detail or adding its plugins.
5	Tap Projects > Download project backup to keep the editable project, then Export mix to create a WAV.

The manual uses labeled diagrams of the current controls, not screenshots. On phones, controls wrap into more rows and panels stack vertically. Scroll down within the DAW to find Mixer, Master inserts and Track detail.

8. Where everything lives

Full DAW > navigation under the Creative Studio banner

These navigation groups belong to the Full DAW workspace. From Ghost Rack, first choose Full DAW below the console. Use Search everything to find a tool or source reference.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Open Full DAW from the rack's workspace links.
2	Choose the group for your task, or open Search everything.
3	Type a tool, genre, voice or instrument name and open a matching result.
4	Star useful entries for faster access in this browser.

Control details


Control or item	What it does
Search everything	Search tools and all 1,268 connected workflow references. Filter by category, save favorites, and open a result directly. Ctrl/Cmd+K opens search.
DAW	Session bar at top; transport below; arrangement, mixer, master inserts and selected-track detail underneath.
Plugin workshop	Opens the effect editor in the DAW work area. The current audio session remains loaded.

Control or item	What it does
Music Library	A reference workspace with its own controls in the main page scroll.
Prompt Encyclopedia	An embedded reference browser with category tabs, search and copy controls.
Lyrics Creator	Blueprints and effect references at top, writing form and draft output below.
Ghost connection	Connection dialog. Only the owner can activate or use the API.
Question mark / Capabilities & limits	Short studio guide. The illustrated manual link opens this longer guide.

9. Import, save and reopen

Session bar > Import song / stems, Save or Projects

Save stores one session in this browser. A project backup is the portable copy containing audio and edits. Exporting a mix does not preserve editable tracks.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Name your session and import audio in the Full DAW.
2	Tap Save to keep the current session in this browser.
3	Open Projects > Download project backup and keep the .ghostproject file.
4	To restore it later, use Projects > Open project file; Open saved session restores the local browser save instead.

Control details


Control or item	What it does
Undo / Redo	Step backward or forward through supported edits. They are not a replacement for a project backup.
Save / Save on this browser	Save the current project locally. A later save replaces the single locally saved session.
Projects	Opens the four save/reopen options pictured above.
Import report	Appears below the transport after importing. Shows each file's success or failure; valid files can load even if another file fails.
Load sound check	Creates three synthesized test stems. This is demo audio, not your song; it asks before replacing a populated session.

Limits: up to 24 tracks, 160 MB per audio file and 12-minute stems. Codec support depends on the browser. The phone and PC do not share browser saves. Download a project backup before switching devices or clearing browser data.

10. Playback, tempo and timeline

DAW > transport, Arrangement and time-range row

The timeline shows when each recording plays. Moving and trimming a clip changes the arrangement while retaining the original source.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Press Play and tap the ruler to seek.
2	Select a clip and drag it horizontally to change its start time; use Snap to beat if wanted.
3	Set Time range Start and End to loop or export a region.
4	Seek inside a selected audio clip and choose Split at playhead to make two pieces.


Control details

Control or item	What it does
Stop / Play	Stop returns to the beginning. Play toggles playback and pause. Space works when you are not typing.
Loop session	Repeats the session; when Time range is enabled, repeats that range.
BPM (40-240)	Controls the beat grid, MIDI timing and tempo-synced effects. It does not independently stretch or repitch imported audio.
Zoom	Changes how much of the timeline fits on screen. It does not change audio speed.
Snap to beat	Snaps clip moves to the musical grid.
Follow playhead	Keeps the playback position in view.
Time range / Start / End	Marks a region in absolute session seconds. Choose Time range in Export to render it.
Split at playhead	Select an audio clip, seek inside it, then split. The two pieces can be arranged separately. MIDI notes are edited in the piano roll.

11. Faders, knobs and the master bus

DAW > Mixer, below Arrangement

Each imported stem gets a channel strip. The master controls the combined output. Start by balancing tracks before adding processing.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Select the stem you want to balance.
2	Play the mix and drag its fader; center its pan knob if you do not want panning.
3	Use M to mute or S to solo; clear unwanted solos before exporting.
4	Open Master inserts only when you intend to affect the entire mix.

Control details


Control or item	What it does
Volume fader	Track gain from -60 to +12 dB. 0 dB is unity gain, not silence. Double-click resets to 0 dB.
Pan knob	Center is 0; left is -1 and right is +1. Drag vertically or use arrow keys. Double-click resets.
M / Mute	Exclude that track from audible playback and the mix.
S / Solo	Listen to soloed tracks. Check Solo if some stems seem missing.

Control or item	What it does
Meters	Show signal while playing. A meter alone does not prove a release is mastered correctly.
3D depth on/off	Changes the appearance of the controls, not the audio.
AUTOMATED / PAN · AUTO	An enabled automation lane owns the control. Disable its lane in Track detail to use the manual fader or pan.
Master inserts	A neutral Master Rack Pro is present by default. Enabling and adjusting it affects the full mix.

12. Track detail and clip editing

Select a track > scroll below Master inserts to Track detail

This panel always edits the selected track. Check its displayed name before changing timing, processing or automation.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Select a track in the arrangement or mixer.
2	Check the name in Track detail, then set timeline start and trim points.
3	Use fades or clip gain for local edits; listen before and after.
4	Use Undo for an unwanted edit and save a backup after useful changes.


Control details

Control or item	What it does
Timeline start · seconds	Moves the clip on the session timeline.
Trim in / Trim out · source seconds	Defines the source excerpt. Trim in must precede trim out; trim out must stay within the original file.
Track role	Instrument, Vocal, Drums or Bass. Used by local analysis and suggestions.
Analyze / Analyze stem	Measures the original source before effects. It is not an AI listening session.
Add plugin	Opens Plugin workshop. Choose Selected stem as destination to insert here.
Enable effect / Edit chain / Remove effect	The checkbox engages processing; Edit chain opens its editor; x removes the effect from this track.
Replace with workshop chain	Replaces this track's inserts with the current workshop chain. Use Undo if needed.
Duplicate / Move up / Move down	Copies the clip or changes its track order.
Disable clip / Enable clip	Excludes or restores clip playback without deleting the track.
Reverse clip / Restore forward audio	Reverses audio playback. MIDI notes are not reversed by this action.
Fade in / Fade out	Applies edge fades in seconds, up to 30 seconds, to smooth starts and endings.
Clip gain	Changes the clip's level before later mix processing, from -60 to +12 dB.
Remove track	Removes the selected track from the session. Keep a backup before major edits.

13. Build and insert your own plugin chain

Plugin workshop tab

A workshop plugin is a chain of browser audio processors. It is not a VST or AU plugin file. The selected destination matters: a track chain affects one stem; the master chain affects the whole mix.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Select the stem in the DAW if this chain belongs on one track.
2	Open Plugin workshop. Tap New chain, give it a name, select a module, then Add module.
3	New modules start neutral and bypassed. Enable the module and adjust only what you need. A wet/dry Mix of 0% still gives dry sound.
4	Choose Destination: Selected stem or Master bus. Tap Insert chain.
5	Use Save plugin for the local library, or Download plugin for a portable settings file.

Control details

Control or item	What it does
Zero entire chain	Restores neutral defaults and bypasses processing. Valid frequency, timing and ratio defaults may be nonzero.
Factory preset	An opt-in sound setting. Selecting one can add processing; do not assume it fits every song.


Control or item	What it does
Edit live chain	Opening a track or master chain edits those live inserts. Check the editor's displayed context before adjusting.
A/B compare	Keeps two settings snapshots for comparison. Match perceived level before judging sound quality.
Full vocal chain / Vocal essentials	Loads eight or four vocal modules in the defined order, neutral and bypassed.
Master bus chain / Master essentials	Loads eight or four mastering modules in the defined order, neutral and bypassed.
Download pack settings	Exports the supplied settings catalog, not a desktop plugin installer.
Saved custom plugins	Your browser-local chains. Export important ones before clearing browser storage.

The complete processor and knob reference is further down this manual. Adding saturation, widening, reverb or delay intentionally changes the sound; those are creative effects, not artifact removal.

14. Choose genre and source chains

Full DAW > Workflows & chains

The reference browser connects 1,268 entries to 66 reusable chain templates. Several genres or sources can share a template; the entry's context provides direction.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Open Workflows & chains from a library entry or its workflow button. Search for your source, genre or vocal style.
2	Select Workflow & chains on the matching card. Read Source direction and the recording-to-export workflow.
3	Expand a channel or bus chain. Check whether its destination is Selected track or Master bus.
4	Use the route's workshop button to open a neutral draft. Opening a draft does not insert or activate it.
5	In the workshop, check the destination and Insert chain. Enable one stage at a time and adjust from the actual audio.
6	Copy full workflow or Download guide if you want the text instructions outside the app.


Control details

Control or item	What it does
Channel versus bus	A channel is one selected track. A master-bus chain affects the combined mix.
Shared templates	A large reference count does not mean every entry has a unique DSP chain. Shared templates intentionally start neutral.
Subchain / route	An expandable choice for a source or destination. Read its stage list before loading it.

15. Analyze stems and remove noise

Selected track > Analyze; Plugin workshop > Repair > Stem Cleanup

Work from the cleanest source you have. Cleanup can reduce some noise and isolated clicks, but it cannot guarantee reconstruction of damaged or clipped audio.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Import the original stems and set their roles in Track detail.
2	Select one stem and Analyze it. Read the explanation beside each suggestion.
3	Use Insert suggestion for one recommendation, or ask Ghost: Apply needed plugins to the selected stem.
4	Audition the result. Compare with the original at similar volume. Reduce or undo settings if consonants, transients or sustained notes sound damaged.
5	Stem Cleanup can require background preparation. Playback continues with the previous result until the updated sound is ready. Read the preparation status before judging the new settings.

Control details

Control or item	What it does
Apply needed plugins	This supported local command measures audible imported stems and applies justified processing. Add 'to the selected stem' to limit it to one track.


Control or item	What it does
Noise Reduction	Maximum reduction strength in dB. Start from 0; increase only when necessary.
Noise Floor	Detection reference in dBFS. The neutral 0 value is not an instruction to use it as a real measured noise floor.
Click Repair	Repair strength for isolated clicks. Aggressive values can damage legitimate transients.
Mix	Blends processed and dry signal. At 0%, the original dry signal remains.
S / T harshness	Smart De-Esser Pro or Dynamic Master Control may help specific harshness; they cannot reliably remove every AI artifact.

The source analysis is not an integrated LUFS or certified true-peak measurement. No synthesized hiss or export dither is added by the app. Creative saturation can still produce distortion when deliberately enabled.

16. Use Ghost and understand API access

Ghost panel beside the DAW on wider screens; below on phones

Ghost has local studio commands and an optional online AI connection. Visitors use the local tools. Only the studio owner can save, test, remove or use the OpenAI API connection.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Open Full DAW and locate the Ghost panel.
2	For local operation, type play, stop or set tempo to 120 and press Send.

Step	Action and result
3	Select a stem, set its role and use Analyze stem to inspect source measurements.
4	Use a supported suggestion only after reading it. Online chat and Test Ghost require the owner's API connection and can incur API charges.


Control details

Control or item	What it does
Local command examples	play; stop; set tempo to 120; create MIDI track; add chord C major; apply needed plugins to the selected stem; undo; redo.
Local guide	Handles supported commands and help. It is not a general-purpose language model.
Online AI - owner only	Receives chat, submitted lyrics, track names, settings and measurements. It does not receive or hear the song audio through this connection.
Save connection	Stores the owner's key encrypted on the server. Saving does not make a paid model request.
Test Ghost	Makes one short paid API request. Only the owner can run it.
Use local guide	Disables online AI use on this device; the saved key stays on the server.
Remove saved key	Disconnects the online app. Does not revoke the key at OpenAI or clear usage history.
Usage display	Tracks this app's estimated monthly budget and daily request limit. It is not an account-wide OpenAI billing cap.
Clear chat	Clears session chat. Previously downloaded project backups can still contain their saved chat.

17. MIDI instruments and recording

DAW > Composition and recording > Piano roll

MIDI is an editable performance of instrument notes. A track named 'Synth Voice' still does not contain sung words. Import a WAV/MP3 vocal stem to hear the original singer.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Open Composition and recording and choose + MIDI instrument or Import MIDI notes.
2	Select the note track and edit pitch, timing, duration and velocity in Piano roll / Note detail.
3	Choose a synth patch and Apply instrument controls. Use on-screen keys to preview.
4	Choose Record source, place the playhead and press Record when ready. Stop recording and audition the new material.

Control details

Control or item	What it does
Clip · beats / Grid	Sets MIDI clip length and note-entry time grid.
Quantize starts	Moves note starts toward the selected timing grid. This does not quantize recorded audio.


Control or item	What it does
View from octave / Key / Scale highlight	Changes the visible piano range and scale guides.
Note detail	Select a note to edit its pitch, position, duration or velocity using the displayed fields.
Local synth patch	Chooses the app's synthesizer settings. Tap Apply instrument controls after knob edits.
Musical typing / Octave - / Octave +	Uses a physical keyboard for note previews and shifts its range. The on-screen keys work by touch.
Chord root / Chord / Arpeggio	Adds the chosen note pattern to the selected MIDI instrument.
Metronome · monitor only	Playback guide, not included in the exported mix.
Time signature / Beat unit	Sets the bar grid's musical counting.
Record source / Record	Audio input uses browser microphone recording. MIDI notes record a performance from supported note input. Recording begins at the playhead.
Input offset · ms	Timing adjustment for device recording latency. Test and set it for your own device; automatic calibration is not provided.

Hardware MIDI availability and microphone recording depend on browser and device permissions. Loop takes and comping are not implemented. Keyboard previews do not audition the full track insert chain; timeline playback does.

18. Automation and MIDI learn

Track detail > Track volume & pan automation; Plugin workshop > Automation & MIDI learn

Automation changes a control over time. It is stored in the project and follows session seconds during playback and export.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Select a track and open its volume and pan automation, or focus a plugin control in the workshop.
2	Enable the lane and set points using absolute session seconds.
3	Play the session to hear the lane. Turn the lane off to return control to the manual fader or pan.
4	For a hardware control, Connect MIDI, focus the desired parameter, start its learn action and move the controller. Save the project to keep mappings.

Control details

Control or item	What it does
Track automation points	Time values use absolute session seconds. Enabled lanes override the manual track fader or pan.
Plugin automation focus	Touch or focus the desired plugin control before editing its automation or MIDI mapping.
Record controls	Records gestures at up to 16 points per second; playback applies values per audio block.

Control or item	What it does
Touch override	Touching an automated plugin control overrides it until playback restarts.
Connect MIDI	Requests supported hardware MIDI access. It does not connect an OpenAI API key.
MIDI mappings	Saved with the project. A different device may send different channel/controller numbers.

19. Music Library and Prompt Encyclopedia

Sound Library or Create > search for the reference workspace

These are text reference tools. Copying a plugin prompt or production recipe does not install an audio processor, reproduce a commercial plugin, or guarantee an external music generator will obey it.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Open Music Library or Prompt Encyclopedia from Full DAW.
2	Choose a category and search for the reference you need.
3	Expand Show Prompt and use COPY.
4	Paste it into your writing brief; use Plugin workshop separately for actual processing.


Control details

Control or item	What it does
Music Library	Browse the embedded collection's visible categories, cards, comparisons and saved-style tools. Reference pages expand into the main page scroll.
Library Studio overlay	The embedded Studio tools have PRESETS, VOCALS, BEATS, GENRES, PLUGINS, BUILDER and SUNO GUIDE tabs, their own search field, and CLOSE.
Prompt Encyclopedia	Pick a category, enter a search phrase, then Show Prompt on a matching card. COPY copies its text; Hide Prompt collapses it.
Using a reference	Copy only the direction you need into Lyrics Creator > Story & production direction > Reference / library prompt.
Audio processing	For actual sound changes, return to Plugin workshop and insert an implemented processor.
External app instructions	Some imported references reflect older third-party conventions. Treat them as creative suggestions; verify the destination app's current syntax and capabilities.

20. Create or rewrite lyrics

Create > Lyrics Creator

Use concrete moments, actions and details in the brief. The AI writing action is owner-only. Visitors can still browse references and work with local draft editing, copying and draft files.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Choose Write new lyrics or Rewrite my lyrics. Enter a title if you have one, and explain what actually happens in the song.

Step	Action and result
2	For a rewrite, paste the original or Import a text file. Fill Keep, Exact lines to protect, Fix and Extend as needed. Protected lines must already exist in the original.
3	Open Sound & delivery. Set Genre / blend, Instruments, Lead voice, Tempo, Key, Language, Target length and Writing / rhyme.
4	Open Story & production direction for Audience, Core emotion, Perspective, Reference / library prompt and Avoid.
5	The owner can tap Write song package. Read the result, edit the output cards, and check warnings before copying or exporting.
6	Copy or download anything you want to keep before leaving. The workspace is temporary and clears when you exit.

Control details


Control or item	What it does
Clear lyrics / leaving the page	The bright yellow Clear lyrics button resets the writing form and output. Leaving Lyrics Creator, refreshing or closing the page clears the workspace. Copy or explicitly download first. Browser draft saving is disabled for everyone; old browser drafts are removed when the updated app opens.
Writing / rhyme	No deliberate rhyming, Natural unforced rhyme, or My own scheme. The custom scheme field appears when selected.
Production blueprint	Use blueprint sets the writing tempo to 69 BPM and replaces the reference field. It does not apply the referenced EQs to your audio.
Hybrid effects-chain library	Browse the 25 reference profiles. Use in Lyrics Creator replaces the writing reference, not your live inserts.
Rewrite this draft	Copies current lyrics into rewrite mode. No automatic draft history is kept.
Open draft file	Loads a Ghost lyrics JSON draft without a model request.
Copy full framework / Download	Exports the song brief, style, voice, structure, lyrics, negatives and notes. Individual output cards have their own Copy buttons.
Save draft file	Keeps an editable draft for transfer or backup.
Text limits	Original lyrics: 12,000 characters; brief: 6,000. Output cards display guidance for 1,000-character style/instrumental prompts and 5,000-character lyrics.

Generated text still needs your editorial judgment. A prompt label does not guarantee Suno will sing, pronounce or arrange it exactly as written.

21. Export the mix or stems

Session bar > Export mix

Export renders the audible tracks. A WAV is audio; a .mid is notes; a .ghostproject is the editable session. Choose the right one for the job.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Save a project backup before exporting.
2	Open Export mix and select mix, selected stem, aligned stems or MIDI as appropriate.
3	Choose Full session or Time range, then sample rate, bit depth and peak ceiling for audio.
4	Tap Render / export, wait for the download, and listen to the exported file.

Control details

Control or item	What it does
Audible mix	Stereo WAV including audible tracks, edits, faders, pans and active track/master processing.
Selected stem through master	Exports the selected stem with master-bus processing.
Aligned stems · ZIP · no master	Equal-length stems beginning at the same session time. Includes track processing, fades, automation, faders and pan; excludes master processing and output trim.
Selected MIDI notes · .mid	Exports editable notes, not the instrument's audio and not sung lyrics.


Control or item	What it does
Full session / Time range	Renders all of the session or the range set under Arrangement.
Sample rate / Bit depth	Match the receiving service's requirements. 24-bit PCM WAV is a common production interchange choice; it is not a guarantee every service accepts it.
Peak ceiling · dBTP estimate	Offers -1, -2 and -3 dBTP estimates. Uses 4x interpolation with an extra 0.1 dB margin and only reduces gain when needed.
Render / export	Wait until the download is offered. Keep this tab open while it works.

This app does not provide a certified true-peak meter or an integrated LUFS mastering guarantee. Listen to the exported file. Keep a project backup separately.

22. Listen and adjust the radio EQ

Radio > Listen

The radio streams approved station tracks. Its listening EQ changes what you hear on this device; it does not remaster the uploaded file.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Open Radio and choose Listen. Pick All music or a genre, then tap a song.
2	Use Play/Pause and the position slider. Previous and Next change tracks in this player.
3	Turn Shuffle on for random order; Repeat playlist repeats the playlist rather than selecting one-track looping.

Step	Action and result
4	Open the 10-band equalizer or tap Ghost to reveal it. Start with Reset, then change a band only if wanted.
5	Compare Bypass EQ with the adjusted version. Use Volume for listening level and preamp for additional headroom.


Control details

Control or item	What it does
Band centers	31, 60, 125, 250, 500, 1,000, 2,000, 4,000, 8,000 and 12,000 Hz.
Band gain	-9 to +9 dB in 0.5 dB steps. The app compensates for boosts to provide headroom.
Preamp	-18 to 0 dB. This and EQ affect monitoring only.
Reset	Sets all bands and preamp to 0 dB and turns bypass off.
Preferences	EQ, volume, preamp and bypass are saved locally. They are not a shared station master setting.

23. Upload and manage station songs

Radio > Upload / Manage

Uploading to the radio publishes or submits a station copy. It is separate from importing audio for private editing in the DAW.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Sign in and open Upload. Choose the file or, for the owner, select several tracks.
2	Check titles, artist and genre. An owner batch shares the chosen artist, genre and cover.
3	Choose optional artwork and confirm that you have permission to share the audio and image.
4	Start the upload and wait for the saved result. Use Retry unfinished uploads for failures; avoid uploading successful entries again.
5	The owner opens Manage to Preview submissions, then Approve or Reject. Listener submissions stay private until approved.
6	Use Change cover or Unpublish for existing entries. Delete permanently removes the station copy after confirmation; keep your original files.


Control details

Control or item	What it does
Owner audio	MP3, WAV or MP4, up to 100 MB each, with multiple selection.
Listener audio	One MP3 at a time, up to 12 MB, subject to owner review.
Artwork	Owner: JPG/PNG up to 20 MB. Listener: JPG/PNG up to 1 MB.
Station capacity	The Manage screen displays the 2,000 MB station limit.
Reset stuck upload	Clears a stalled upload session so you can try again; wait until the current upload is no longer active.
New genre	Owner: Manage > Add a genre > enter name > Add.
Install app	Use Install app or the browser's Add to Home screen option. Installing does not change upload permissions.

24. Choose the correct file loader

Presets / Projects / Plugin workshop / Lyrics

A JSON extension is not enough to identify a file. Each loader expects a different document structure.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Identify what the file contains, not just its extension.
2	Use Rack Presets for Dynamics A settings and Rack Projects for a one-source project.
3	Use Full DAW Projects for .ghostproject; use Plugin workshop > Import plugin for .ghostplugin.json.
4	Use Lyrics > Open draft file for lyrics JSON. Use an audio importer for a recording.


Control details

Control or item	What it does
Preset versus project	Presets hold settings; projects can include source audio and editable state.
Prompt text / ZIP	Prompt text does not load into the Dynamics A preset importer. A source-code ZIP is not an audio plugin installer.
Portable backups	Download files you need on another device. A browser-local save is not cloud sync.

25. Fix common problems

Footer > Audio mode & troubleshooting

Save or download a backup before closing the tab, replacing a session, or clearing browser data.



Control map: numbers identify the labeled controls for this task.

Follow these steps

Step	Action and result
1	Read the status or error message without clearing your session.
2	Check source type, track selection, mute/solo, IN/BYPASS and volume.
3	If sound changes are still preparing, wait for the completion message.
4	Save a project backup, then use Audio mode & troubleshooting > Download audio diagnostics when asking for help.

Control details


Control or item	What it does
No singer; only instrument notes	You imported MIDI or loaded the sound check. Import the actual audio through Import song / stems. Check mute and solo if both audio and MIDI are present.
Not every stem loaded	Read the per-file import report. Check the 24-track, 160 MB/file and 12-minute limits, file validity and codec support.
Audio module / worklet error	Choose Prepared playback in the footer. It takes time before audio starts, and edits require preparing again.

Control or item	What it does
Playback stops when I turn a knob	Current plugin and mix edits prepare in the background while playback continues. Wait for Updated sound is playing. If updating fails, the previous sound remains; read the status, save a backup and download diagnostics.
Memory error	Long stems or heavy repair can exceed available memory. Work with shorter source clips or a smaller session after saving a backup. A phone has finite browser memory.
Plugin makes no difference	Check enable, Mix, destination, mute/solo and preparation status. New inserts are bypassed and neutral. Reference prompts do not process audio.
Plugin makes the sound worse	Bypass it or Undo. Reset to neutral; adjust one justified control at a time. Saturation, drive, widening and heavy repair can change or damage the sound.
Cannot connect the API	Only the owner is allowed. Visitors should use local tools. The owner should sign in with the owner account and read the connection error; do not share the API key.
Saved work missing on another device	Saves are local to each browser. Open your downloaded project or draft file on the other device.
Cannot find a panel on mobile	Scroll the whole page. Ghost Rack's workspace links and prompt library sit below the photo. Full DAW panels stack vertically; open the relevant group and use Search everything.

Processor 1: High-pass filter

Remove low-frequency rumble.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.




Control	Range and neutral	Purpose
frequency	0 to 500 Hz; neutral 0 Hz	Cutoff or turnover frequency of the filter.
Q	0.1 to 2 Q; neutral 0.707 Q	Bandwidth or resonance. A higher Q generally narrows the affected band.

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 2: Low shelf

Shape the weight and warmth.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.




Control	Range and neutral	Purpose
frequency	40 to 500 Hz; neutral 180 Hz	Cutoff or turnover frequency of the filter.
gain	-12 to 12 dB; neutral 0 dB	Boost or cut of the EQ band. 0 dB is flat.

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 3: Parametric EQ

Cut or lift a focused frequency range.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.




Control	Range and neutral	Purpose
frequency	80 to 12000 Hz; neutral 2400 Hz	Center frequency of the EQ band.
gain	-12 to 12 dB; neutral 0 dB	Boost or cut of the EQ band. 0 dB is flat.
Q	0.2 to 8 Q; neutral 1 Q	Bandwidth or resonance. A higher Q generally narrows the affected band.

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 4: High shelf

Shape brightness with a broad shelf.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.




Control	Range and neutral	Purpose
frequency	1500 to 16000 Hz; neutral 7000 Hz	Cutoff or turnover frequency of the filter.
gain	-12 to 12 dB; neutral 0 dB	Boost or cut of the EQ band. 0 dB is flat.

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 5: Low-pass filter

Reduce the top end.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.




Control	Range and neutral	Purpose
frequency	0 to 20000 Hz; neutral 0 Hz	Cutoff or turnover frequency of the filter.
Q	0.1 to 2 Q; neutral 0.707 Q	Bandwidth or resonance. A higher Q generally narrows the affected band.

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 6: Compressor

Control dynamics; makeup gain follows compression.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.




Control	Range and neutral	Purpose
threshold	-60 to 0 dB; neutral 0 dB	Level above which detection/compression acts.
ratio	1 to 12 :1; neutral 1 :1	Compression strength above threshold.
attack	1 to 100 ms; neutral 15 ms	How quickly compression responds.
release	30 to 1000 ms; neutral 160 ms	How quickly gain recovers.
knee	0 to 30 dB; neutral 0 dB	Adjusts the labeled processing amount.
makeup	-12 to 12 dB; neutral 0 dB	Adds level after compression.

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 7: Stereo delay

Add linked echoes with a parallel dry signal.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.




Control	Range and neutral	Purpose
time	0 to 600 ms; neutral 0 ms	Delay time when tempo sync is off.
feedback	0 to 60 %; neutral 0 %	Amount of repeat signal fed back into the delay.
mix	0 to 50 %; neutral 0 %	Balances processed and original audio.

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 8: Soft saturation

Add harmonics with a parallel blend.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.




Control	Range and neutral	Purpose
drive	1 to 5 x; neutral 1 x	Input drive into the saturation curve. Unity drive is 1x.
mix	0 to 50 %; neutral 0 %	Balances processed and original audio.

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 9: Output trim

Set the level leaving your effect.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
gain	-24 to 12 dB; neutral 0 dB	Output level trim. 0 dB leaves level unchanged.

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 10: Vocal 73 Front End

Broad vocal tone and original harmonic shaping; not a measured hardware emulation.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.

Vocal 73 Front End

CONTROL MAP · Match the numbers to the labels below

1. **Input Drive**
   Neutral 0 dB · 0 to 24
2. **Output Trim**
   Neutral 0 dB · -24 to 12
3. **HPF**
   Neutral 0 Hz · 0 to 160
4. **Low Body**
   Neutral 0 dB · -6 to 6
5. **Presence**
   Neutral 0 dB · -6 to 6
6. **Air**
   Neutral 0 dB · -6 to 8
7. **Saturation**
   Neutral 0 % · 0 to 100
8. **Tone Mode**
   Neutral 0 · 0 to 2
9. **Mix**
   Neutral 0 % · 0 to 100

Control	Range and neutral	Purpose
input Drive	0 to 24 dB; neutral 0 dB	Raises the level entering the character or peak-control stage.
output	-24 to 12 dB; neutral 0 dB	Final level trim for this processor.
hpf	Off / 50 Hz / 80 Hz / 100 Hz / 160 Hz; neutral 0 Hz	Removes frequencies below the cutoff. Off passes the low end through.
body	-6 to 6 dB; neutral 0 dB	Broad low-frequency body boost or cut.
presence	-6 to 6 dB; neutral 0 dB	Broad vocal definition or upper-mid boost/cut.
air	-6 to 8 dB; neutral 0 dB	High-frequency sheen amount.
saturation	0 to 100 %; neutral 0 %	Harmonic coloration amount. Increase only when wanted.
tone Mode	Clean / Warm / Console; neutral 0	Selects the processor's clean or colored response.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.


Factory presets: Clean Pop Vocal; Warm Rap Lead; Bright Female Lead; Thick Male Lead; Voiceover Front

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 11: Smart De-Esser Pro

Frequency-selective envelope detection. Split and wide modes, reduction metering and a detector audition.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
threshold	-60 to 0 dB; neutral 0 dB	Level above which detection/compression acts.
frequency	2500 to 12000 Hz; neutral 6500 Hz	Frequency region used to detect sibilance.
range	0 to 18 dB; neutral 0 dB	Maximum de-essing reduction.
mode	Wide / Split; neutral 0	Selects the labeled processing mode.
smoothness	0 to 100 ; neutral 0	Softens how quickly control changes.
air Preserve	0 to 100 %; neutral 0 %	Reduces dulling of the upper range during de-essing.
monitor	Monitor off / Monitor sibilance; neutral 0	Auditions the sibilance detector; turn off for normal listening.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.

Factory presets: Pop Smooth; Bright Female Tame; Rap Presence Control; Podcast Clean; Aggressive S Saver

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 12: FET Vocal Snap

Fast feed-forward compression with a filtered detector, parallel blend and harmonic presence.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
input	0 to 30 dB; neutral 0 dB	Level entering the compressor.
output	-30 to 18 dB; neutral 0 dB	Final level trim for this processor.
attack	0.1 to 10 ms; neutral 1 ms	How quickly compression responds.
release	20 to 1000 ms; neutral 100 ms	How quickly gain recovers.
ratio	4:1 / 8:1 / 12:1 / 20:1; neutral 4 :1	Compression strength above threshold.
presence Drive	0 to 100 %; neutral 0 %	Adds harmonic edge.
sidechain HPF	0 to 300 Hz; neutral 0 Hz	Reduces bass influence on the detector.

Control	Range and neutral	Purpose
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.


Factory presets: Lead Vocal Control; Rap Clamp; Pop Edge; Ad-Lib Push; Parallel Energy

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 13: Opto Vocal Leveler

A dual-time-constant leveler with signal-dependent recovery and gentle optional harmonic color.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
peak Reduction	0 to 100 ; neutral 0	Strength of optical leveling.
gain	-24 to 18 dB; neutral 0 dB	Level compensation.
mode	Compress / Limit; neutral 0	Selects the labeled processing mode.
warmth	0 to 100 %; neutral 0 %	Adds gentle coloration.
emphasis	0 to 100 %; neutral 0 %	Weights the leveling response.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.

Factory presets: Smooth Lead; Hook Leveler; R&B Velvet; Ballad Warmth; Soft Voice Control

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 14: Vocal Air EQ

Broad vocal curves for body, mud, presence, air and static upper-mid softening.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
hpf	0 to 250 Hz; neutral 0 Hz	Removes frequencies below the cutoff. Off passes the low end through.
body	-8 to 8 dB; neutral 0 dB	Broad low-frequency body boost or cut.
mud Cut	0 to 100 %; neutral 0 %	Reduces the low-mid region.
presence	-8 to 8 dB; neutral 0 dB	Broad vocal definition or upper-mid boost/cut.
air	0 to 100 %; neutral 0 %	High-frequency sheen amount.
de Harsh	0 to 100 %; neutral 0 %	Calms upper-mid harshness.
output	-24 to 12 dB; neutral 0 dB	Final level trim for this processor.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.


Factory presets: Pop Shine; Rap Clarity; Female Air; Male Presence; Backing Vocal Clean

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 15: Vocal Doubler Wide

Two crossfaded moving delay heads per side provide real micro-pitch doubling. Audition mono compatibility.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
amount	0 to 100 %; neutral 0 %	Strength of doubling.
left Detune	-24 to 24 cent; neutral 0 cent	Left voice pitch offset.
right Detune	-24 to 24 cent; neutral 0 cent	Right voice pitch offset.
left Delay	0 to 80 ms; neutral 0 ms	Left voice delay.
right Delay	0 to 80 ms; neutral 0 ms	Right voice delay.

Control	Range and neutral	Purpose
width	-100 to 100 % change; neutral 0 % change	Stereo width amount.
center Keep	0 to 100 %; neutral 0 %	Retains the centered vocal.
modulation	0 to 100 %; neutral 0 %	Movement in delay or reverb.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.


Factory presets: Hook Width; Chorus Lift; Ad-Lib Spread; Backing Stack; Wide Pop Lead

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 16: Plate Vocal Space

Eight-line modulated feedback reverb inspired by plate density. This is an algorithmic design.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
pre Delay	0 to 180 ms; neutral 0 ms	Gap before the reverb tail begins.
decay	0.1 to 8 s; neutral 0.1 s	Reverb tail duration.
brightness	0 to 100 ; neutral 0	Reverb high-frequency balance.
damping	0 to 100 ; neutral 0	High-frequency loss in the tail.
low Cut	0 to 500 Hz; neutral 0 Hz	Low-frequency cutoff for the effect.
high Cut	1000 to 20000 Hz; neutral 20000 Hz	High-frequency cutoff for the effect.
width	-100 to 100 % change; neutral 0 % change	Stereo width amount.
modulation	0 to 100 %; neutral 0 %	Movement in delay or reverb.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.


Factory presets: Lead Vocal Plate; Tight Pop Plate; Long Ballad Plate; Rap Space; BGV Shine

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 17: Throw Delay Vox

Tempo-aware stereo repeats, envelope ducking, filtered feedback and a finite-export freeze mode.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
time	0 to 2000 ms; neutral 0 ms	Delay time when tempo sync is off.
sync	Free time / Tempo sync; neutral 0	Links delay timing to the session tempo.
division	1/16 / 1/8 / 1/8 dotted / 1/4 / 1/4 dotted / 1/2 / 1 bar; neutral 3	Tempo-synced note division.
feedback	0 to 95 %; neutral 0 %	Amount of repeat signal fed back into the delay.
tone	-100 to 100 ; neutral 0	Color or brightness of the processor.

Control	Range and neutral	Purpose
ducking	0 to 100 %; neutral 0 %	Lowers delay repeats while the dry vocal is present.
saturation	0 to 100 %; neutral 0 %	Harmonic coloration amount. Increase only when wanted.
width	-100 to 100 % change; neutral 0 % change	Stereo width amount.
intensity	0 to 100 %; neutral 0 %	Strength of the vocal throw.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.
freeze	Freeze off / Freeze repeats; neutral 0	Sustains the delay feedback effect.

Factory presets: Clean Slap; Hook Throw; Rap Throw; Wide Delay Wash; Dark Echo Tail

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 18: Master Tone EQ

Broad stereo, mid-only or side-only tonal shaping with independently filtered M/S paths.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
hpf	0 to 200 Hz; neutral 0 Hz	Removes frequencies below the cutoff. Off passes the low end through.
low Shelf	-6 to 6 dB; neutral 0 dB	Broad low-frequency boost/cut.
low Mid Tilt	-6 to 6 dB; neutral 0 dB	Adjusts low-mid tonal balance.
presence	-6 to 6 dB; neutral 0 dB	Broad vocal definition or upper-mid boost/cut.
air Shelf	-6 to 6 dB; neutral 0 dB	Broad high-frequency boost/cut.
de Harsh	0 to 100 %; neutral 0 %	Calms upper-mid harshness.
output	-12 to 12 dB; neutral 0 dB	Final level trim for this processor.
ms Mode	Stereo / Mid only / Side only; neutral 0	Switches to the available mid/side processing mode.

Factory presets: Gentle Polish; Warmth and Air; Low-End Tighten; Bright Mix Softener; Vocal-Forward Master

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 19: Glue Bus Master

Stereo-linked bus compression with a sidechain high-pass and optional signal-dependent release.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
threshold	-48 to 0 dB; neutral 0 dB	Level above which detection/compression acts.
ratio	1.5:1 / 2:1 / 4:1; neutral 1.5 :1	Compression strength above threshold.
attack	0.1 to 100 ms; neutral 10 ms	How quickly compression responds.
release	30 to 1500 ms; neutral 100 ms	How quickly gain recovers.
auto Release	Manual release / Auto release; neutral 0	Enables the compressor's automatic recovery option.
makeup	-12 to 12 dB; neutral 0 dB	Adds level after compression.
sidechain HPF	0 to 300 Hz; neutral 0 Hz	Reduces bass influence on the detector.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.


Factory presets: Mix Glue Light; Pop Cohesion; Rock Tighten; Hip-Hop Bus Lock; Parallel Glue

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 20: Vari-Mu Finish

Original soft-knee, level-dependent compression with adjustable stereo detector linking.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
input	0 to 18 dB; neutral 0 dB	Level entering the compressor.
threshold	-40 to 0 dB; neutral 0 dB	Level above which detection/compression acts.
time Constant	1 · fast / 2 / 3 / 4 / 5 / 6 · slow; neutral 1	Selects a compression timing response.
tone	-100 to 100 ; neutral 0	Color or brightness of the processor.
stereo Link	0 to 100 %; neutral 0 %	Links left and right dynamics behavior.
output	-18 to 12 dB; neutral 0 dB	Final level trim for this processor.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.


Factory presets: Silk Finish; Warm Master; Ballad Smooth; Dense Pop Finish; Luxury Glue

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 21: Passive Master Air

Broad boost and attenuation bands with different turnover frequencies for simultaneous low shaping.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
low Boost	0 to 8 dB; neutral 0 dB	Broad low-frequency boost.
low Attenuation	0 to 8 dB; neutral 0 dB	Broad low-frequency reduction; can combine with boost.
low Frequency	20 Hz / 30 Hz / 60 Hz / 100 Hz; neutral 60 Hz	Frequency used for low shaping.
high Boost	0 to 8 dB; neutral 0 dB	Broad upper-frequency boost.
high Frequency	3 kHz / 5 kHz / 8 kHz / 10 kHz / 12 kHz / 16 kHz; neutral 10000 Hz	Frequency used for high shaping.
bandwidth	0 to 100 ; neutral 0	Width of the high-frequency shaping curve.
high Attenuation	0 to 8 dB; neutral 0 dB	Upper-frequency reduction.

Control	Range and neutral	Purpose
output	-12 to 12 dB; neutral 0 dB	Final level trim for this processor.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.

Factory presets: Master Air; Low-End Roundness; Pop Gloss; Vocal Lift Master; Smooth Brightness

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 22: Tape Master 30

Optional harmonic color and tone shaping. Noise synthesis has been removed; this effect is not a denoiser.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
input Drive	0 to 18 dB; neutral 0 dB	Raises the level entering the character or peak-control stage.
speed	15 ips / 30 ips; neutral 30 ips	Selects the tape-speed character.
bias	-100 to 100 ; neutral 0	Changes tape-style coloration.
saturation	0 to 100 %; neutral 0 %	Harmonic coloration amount. Increase only when wanted.

Control	Range and neutral	Purpose
head Bump	0 to 100 %; neutral 0 %	Low-frequency tape-style emphasis.
hf Smooth	0 to 100 %; neutral 0 %	Softens the upper range.
output	-18 to 12 dB; neutral 0 dB	Final level trim for this processor.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.


Factory presets: Clean Tape Finish; Warm Pop Glue; Vintage Master; Low-End Weight; Subtle Analog Coat

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 23: Stereo Image Control

Complementary M/S bands, low-side filtering and continuous stereo correlation measurement.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
width	-100 to 100 % change; neutral 0 % change	Stereo width amount.
low Mono	0 to 250 Hz; neutral 0 Hz	Centers the lower frequency range.

Control	Range and neutral	Purpose
mid Spread	-100 to 100 % change; neutral 0 % change	Width of the midrange.
high Width	-100 to 100 % change; neutral 0 % change	Width of the upper range.
center Focus	0 to 100 %; neutral 0 %	Emphasizes the centered component.
ms Balance	-100 to 100 ; neutral 0	Balance of center and side components.
output	-12 to 12 dB; neutral 0 dB	Final level trim for this processor.


Factory presets: Gentle Width; Pop Open; Center Focus; Club Mono Low End; Wide Cinematic

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 24: Dynamic Master Control

Four band-envelope detectors drive downward dynamic EQ only above their level thresholds.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
low Control	0 to 100 %; neutral 0 %	Dynamic low-frequency restraint.

Control	Range and neutral	Purpose
low Mid Control	0 to 100 %; neutral 0 %	Dynamic low-mid restraint.
presence Control	0 to 100 %; neutral 0 %	Dynamic presence-region restraint.
harshness Control	0 to 100 %; neutral 0 %	Dynamic upper-mid restraint.
sensitivity	0 to 100 ; neutral 0	How readily the detector responds.
smoothness	0 to 100 ; neutral 0	Softens how quickly control changes.
output	-12 to 12 dB; neutral 0 dB	Final level trim for this processor.


Factory presets: Bright Mix Tamer; Boomy Low-End Control; Presence Smoother; Transparent Fix; Streaming Prep

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 25: Final Limit Clipper

Zero-lookahead peak compression and soft clipping. True peak uses an uncertified 4x FIR estimate.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
input Drive	0 to 18 dB; neutral 0 dB	Raises the level entering the character or peak-control stage.
ceiling	-12 to 0 dBTP est.; neutral 0 dBTP est.	Output peak ceiling target.
clip Amount	0 to 100 %; neutral 0 %	Amount of peak shaving.
limiter Amount	0 to 100 %; neutral 0 %	Strength of final peak control.
release	10 to 1000 ms; neutral 100 ms	How quickly gain recovers.
low Protect	0 to 100 %; neutral 0 %	Reduces low-frequency-driven limiting artifacts.
overshoot	Protection off / Extra peak margin; neutral 0	Additional peak protection.
tone	-6 to 6 dB; neutral 0 dB	Color or brightness of the processor.

Factory presets: Clean Loud; Pop Finish; Hip-Hop Loud; Punchy Streaming; Safe Ceiling

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 26: Master Rack Pro - Complete Mastering Chain

Fixed order: Tone EQ > Glue > Vari-Mu > Passive EQ > Tape > Imaging > Dynamic EQ > Clipper/Limiter. Meter status is not release certification.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.

Control	Range and neutral	Purpose
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.
output Gain	-12 to 12 dB; neutral 0 dB	Final output level.
eq On	Section bypassed / Section engaged; neutral 0	Enables or bypasses this rack section.
eq / hpf	0 to 200 Hz; neutral 0 Hz	Removes frequencies below the cutoff. Off passes the low end through.
eq / low Shelf	-6 to 6 dB; neutral 0 dB	Broad low-frequency boost/cut.
eq / low Mid Tilt	-6 to 6 dB; neutral 0 dB	Adjusts low-mid tonal balance.
eq / presence	-6 to 6 dB; neutral 0 dB	Broad vocal definition or upper-mid boost/cut.

Control	Range and neutral	Purpose
eq / air Shelf	-6 to 6 dB; neutral 0 dB	Broad high-frequency boost/cut.
eq / de Harsh	0 to 100 %; neutral 0 %	Calms upper-mid harshness.
eq / output	-12 to 12 dB; neutral 0 dB	Final level trim for this processor.
eq / ms Mode	Stereo / Mid only / Side only; neutral 0	Switches to the available mid/side processing mode.
glue On	Section bypassed / Section engaged; neutral 0	Enables or bypasses this rack section.
glue / threshold	-48 to 0 dB; neutral 0 dB	Level above which detection/compression acts.
glue / ratio	1.5:1 / 2:1 / 4:1; neutral 1.5 :1	Compression strength above threshold.
glue / attack	0.1 to 100 ms; neutral 10 ms	How quickly compression responds.
glue / release	30 to 1500 ms; neutral 100 ms	How quickly gain recovers.
glue / auto Release	Manual release / Auto release; neutral 0	Enables the compressor's automatic recovery option.
glue / makeup	-12 to 12 dB; neutral 0 dB	Adds level after compression.
glue / sidechain HPF	0 to 300 Hz; neutral 0 Hz	Reduces bass influence on the detector.
glue / mix	0 to 100 %; neutral 0 %	Balances processed and original audio.
mu On	Section bypassed / Section engaged; neutral 0	Enables or bypasses this rack section.
mu / input	0 to 18 dB; neutral 0 dB	Level entering the compressor.
mu / threshold	-40 to 0 dB; neutral 0 dB	Level above which detection/compression acts.
mu / time Constant	1 · fast / 2 / 3 / 4 / 5 / 6 · slow; neutral 1	Selects a compression timing response.
mu / tone	-100 to 100 ; neutral 0	Color or brightness of the processor.
mu / stereo Link	0 to 100 %; neutral 0 %	Links left and right dynamics behavior.
mu / output	-18 to 12 dB; neutral 0 dB	Final level trim for this processor.
mu / mix	0 to 100 %; neutral 0 %	Balances processed and original audio.
passive On	Section bypassed / Section engaged; neutral 0	Enables or bypasses this rack section.
passive / low Boost	0 to 8 dB; neutral 0 dB	Broad low-frequency boost.

Control	Range and neutral	Purpose
passive / low Attenuation	0 to 8 dB; neutral 0 dB	Broad low-frequency reduction; can combine with boost.
passive / low Frequency	20 Hz / 30 Hz / 60 Hz / 100 Hz; neutral 60 Hz	Frequency used for low shaping.
passive / high Boost	0 to 8 dB; neutral 0 dB	Broad upper-frequency boost.
passive / high Frequency	3 kHz / 5 kHz / 8 kHz / 10 kHz / 12 kHz / 16 kHz; neutral 10000 Hz	Frequency used for high shaping.
passive / bandwidth	0 to 100 ; neutral 0	Width of the high-frequency shaping curve.
passive / high Attenuation	0 to 8 dB; neutral 0 dB	Upper-frequency reduction.
passive / output	-12 to 12 dB; neutral 0 dB	Final level trim for this processor.
passive / mix	0 to 100 %; neutral 0 %	Balances processed and original audio.
tape On	Section bypassed / Section engaged; neutral 0	Enables or bypasses this rack section.
tape / input Drive	0 to 18 dB; neutral 0 dB	Raises the level entering the character or peak-control stage.
tape / speed	15 ips / 30 ips; neutral 30 ips	Selects the tape-speed character.
tape / bias	-100 to 100 ; neutral 0	Changes tape-style coloration.
tape / saturation	0 to 100 %; neutral 0 %	Harmonic coloration amount. Increase only when wanted.
tape / head Bump	0 to 100 %; neutral 0 %	Low-frequency tape-style emphasis.
tape / hf Smooth	0 to 100 %; neutral 0 %	Softens the upper range.
tape / output	-18 to 12 dB; neutral 0 dB	Final level trim for this processor.
tape / mix	0 to 100 %; neutral 0 %	Balances processed and original audio.
image On	Section bypassed / Section engaged; neutral 0	Enables or bypasses this rack section.
image / width	-100 to 100 % change; neutral 0 % change	Stereo width amount.
image / low Mono	0 to 250 Hz; neutral 0 Hz	Centers the lower frequency range.
image / mid Spread	-100 to 100 % change; neutral 0 % change	Width of the midrange.

Control	Range and neutral	Purpose
image / high Width	-100 to 100 % change; neutral 0 % change	Width of the upper range.
image / center Focus	0 to 100 %; neutral 0 %	Emphasizes the centered component.
image / ms Balance	-100 to 100 ; neutral 0	Balance of center and side components.
image / output	-12 to 12 dB; neutral 0 dB	Final level trim for this processor.
dyn On	Section bypassed / Section engaged; neutral 0	Enables or bypasses this rack section.
dyn / low Control	0 to 100 %; neutral 0 %	Dynamic low-frequency restraint.
dyn / low Mid Control	0 to 100 %; neutral 0 %	Dynamic low-mid restraint.
dyn / presence Control	0 to 100 %; neutral 0 %	Dynamic presence-region restraint.
dyn / harshness Control	0 to 100 %; neutral 0 %	Dynamic upper-mid restraint.
dyn / sensitivity	0 to 100 ; neutral 0	How readily the detector responds.
dyn / smoothness	0 to 100 ; neutral 0	Softens how quickly control changes.
dyn / output	-12 to 12 dB; neutral 0 dB	Final level trim for this processor.
limit On	Section bypassed / Section engaged; neutral 0	Enables or bypasses this rack section.
limit / input Drive	0 to 18 dB; neutral 0 dB	Raises the level entering the character or peak-control stage.
limit / ceiling	-12 to 0 dBTP est.; neutral 0 dBTP est.	Output peak ceiling target.
limit / clip Amount	0 to 100 %; neutral 0 %	Amount of peak shaving.
limit / limiter Amount	0 to 100 %; neutral 0 %	Strength of final peak control.
limit / release	10 to 1000 ms; neutral 100 ms	How quickly gain recovers.
limit / low Protect	0 to 100 %; neutral 0 %	Reduces low-frequency-driven limiting artifacts.
limit / overshoot	Protection off / Extra peak margin; neutral 0	Additional peak protection.
limit / tone	-6 to 6 dB; neutral 0 dB	Color or brightness of the processor.


Factory presets: Gentle Polish; Pop Finish; Hip-Hop Loud; Rock Tight; Ballad Warmth; Cinematic Wide; Streaming Safe; Vintage Tape Master; Punchy Modern; Transparent Reference; Loud Club Ready

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Processor 27: Stem Cleanup

Conservative spectral noise reduction and isolated click repair. Prepared before playback, with original timing preserved. Cannot reconstruct clipped audio or reliably undo every AI artifact.

Full DAW > Plugin workshop. New inserts start neutral and bypassed. Select the destination, insert the module, then enable and adjust it. A sound preset can engage processing.



Control	Range and neutral	Purpose
noise Reduction	0 to 12 dB; neutral 0 dB	Background-noise reduction amount; start low and listen.
noise Floor	-100 to 0 dBFS; neutral 0 dBFS	Noise threshold used by cleanup.
click Repair	0 to 100 %; neutral 0 %	Click-repair amount. Excessive repair can alter transients.
mix	0 to 100 %; neutral 0 %	Balances processed and original audio.

Factory presets: Light Noise Reduction; Quiet-Section Hiss; Isolated Click Repair

0 dB gain means unchanged level. Neutral frequency, timing and ratio values can be nonzero. Compare at matched listening levels; no preset can guarantee a correct mix for every source.

Glossary

Control or item	What it does
Stem	A separate recorded part such as vocals, bass or drums.
Chain	An ordered set of processors; a prompt chain can instead be text instructions.
Bus / master	A shared signal path; the master receives the combined mix.
Bypass	Passes the original signal without that processor's effect.
Wet / dry	Processed / original signal; Mix blends the two.
dBFS	Digital signal level relative to full scale.
LUFS / true peak	Loudness and reconstructed peak measures; this app does not certify mastering compliance.
MIDI	Note/performance instructions, not a recorded singer.
Preset	Saved parameter settings; the module and file format must match.
Project	Editable session state, potentially including source audio.
Automation	Parameter changes over session time.
Q	EQ bandwidth control; higher Q generally makes a narrower band.

Finding the right help

For a problem, note the workspace, the button you tapped, the exact message and whether sound was playing. Download audio diagnostics from the Full DAW when applicable. Do not share API keys. The online manual has search and enlarged images.