
CAB TESTED FREIGHTLINER · ALL ABOARD STUDIOS · TCA QUADRANT AIRBUS

Class 70

Freightliner ALL ABOARD STUDIOS



Cab setup

- Cab enable and master key in (PARK BRK up); give the key a few seconds before the first reverser move
- AWS/TPWS and DVD to Normal: both aux squares lit (the loco loads with both isolated)
- TMS: F1 Air Brakes, F3 Cut In, F4 Lead, F6 Save when the brake screen shows Cut Out; brake mode Goods / Passenger in the cab
- Headlights to Day (AUTO BRK); Tail in the rear cab when running light
- Automatic brake from Handle off to Full service (the loco loads with the brake pipe cut off), independent applied, throttle Idle
- Parking brake released in the cab; engine stopped itself while parked? Right throttle button starts it again
- Brake mode on the round aux: the loco loads in Passenger; press it so it lights for Goods, the setting for Class 70 freight (the cab switch is on the rear-wall panel beneath the red fuel cut-off)

Cleared to depart

- Check the signal; reverser to Forward a few seconds after PARK BRK (move it again if it does not take)
- Automatic brake to Release (pull back), wait for the brake pipe to reach 5 bar / 72 psi
- Independent brake to Release (flap lever back)
- Throttle notch by notch; a heavy train may need Notch 8 to get going, go easy in the wet
- Acknowledge AWS and the vigilance with the gear lever
- Braking: throttle to Idle, automatic brake into the service zone; the direct brake holds the loco at a stand (bail-off is cosmetic in this add-on)
- TMS says PCS Open (no power after an emergency or a vented pipe): stop, throttle Idle, automatic brake to Emergency for a full minute, then Release; it clears as the pipe recharges

