

Primewave AppV1

Home page — what appears first after load

Only the dashboard-v2 **Home** tab (the screen you see after splash). Top-to-bottom sections, the skeleton → real-content switch, and the functions / APIs each block needs.

Generated 2026-08-17 · app/dashboard-v2.jsx

Screen: Home tab of dashboard-v2. Not login, not splash, not Rooms/CCTV/Settings tabs. File: AppV1/app/dashboard-v2.jsx — block marked ===== HOME TAB =====.

1. What you see, top to bottom

After splash, dashboard-v2 mounts with Home as the default tab. Until data is ready you see grey shimmer skeletons in the same layout. Then the real blocks swap in together (cameras can lag a moment longer).

Order on screen	Component	What it is
Chrome (always)	TabBar (phone) or TabletSidebar (landscape)	Home / Rooms / CCTV / Butler / Settings. Visible even while home is skeleton.
1. Header	HeaderV2	Greeting + name, weather/city, indoor temp, humidity, bell (unread count), mic (Butler).
2. Status row	StatusBadges	Locks pill (dots + All locked / N unlocked) + lights-on count + AC-on count.
3. Optional people	PersonBadges	Only if Settings → show family is on. person.* photos + active alert chips.
4. Health banner	HaSystemBanner	Only if HA or admin is down (shown after a 10s delay). Usually empty.
5. Quick scenes	QuickScenes	Up to 4 scene cards from admin. Tap runs scene.turn_on.
6. Home Access	HomeAccess	Lock pills + garage pills (selected in admin Home Access).
7. Rooms	RoomsList	Parent room cards: photo, name, lights/AC/cover/door badges. Phone: horizontal strip. Tablet: 6-up grid.
8. Cameras	HomeCameraStrip	Live thumbnails (Frigate or HA camera fallback). Extra wait: Frigate config attempt.

2. Two stages of first paint

2.1 Stage A — skeletons (you are waiting)

- If the HA profile is not yet read from SecureStore: full-page **DashboardSkeleton**.
- Once `connectionConfig.loaded` is true: a `ScrollView` of **HeaderSkeleton**, **ScenesSkeleton**, **HomeAccessSkeleton**, **RoomsSkeleton**, **CamerasSkeleton**.
- This is `revealStep === 0`.

2.2 Stage B — real home (first content you recognise)

One effect sets `revealStep = 5` in a single jump (not 1, then 2, then 3...). So header, badges, scenes, home access, and rooms appear **at the same time**. The camera strip stays on `CamerasSkeleton` until Frigate config has been tried.

Must be true	Code flag	Where it comes from
At least one HA entity	<code>entities.length > 0</code>	HA WebSocket <code>get_states</code> after auth
Quick-scenes request finished (ok or fail)	<code>scenesFetched</code>	<code>GET {admin}/api/quick-scenes</code>
Home Access request finished (ok or fail)	<code>homeAccessFetched</code>	<code>GET {admin}/api/home-access</code>

Exception: if the app was opened from a push, `alertNotif` forces `revealStep = 5` immediately so the alert modal can show on top of home.

3. What is fetched so those blocks can render

All of this starts as soon as dashboard-v2 has the active profile (HA URL, token, admin URL). Home does not wait for every call — only the three flags above.

3.1 Home Assistant (one WebSocket)

`new HAService(url, token) → connect() → auth → then Promise.all:`

HA call	Function	Home UI that uses it
auth	HAService.sendAuth()	Unblocks everything else
subscribe_events state_changed	after auth_ok	Live updates after first paint (lights, locks, garage...)
get_states	getStates()	Header weather/temp, badges, locks, rooms, people, alarm
get_config	getConfig()	Header cityName (location_name)
device_registry/list	getDeviceRegistry()	Which devices belong to which room
entity_registry/list	getEntityRegistry()	Entity → area; room cards + home locks fallback
area_registry/list	getAreaRegistry()	Room list names / photos / parent rooms
floor_registry/list	getFloorRegistry()	Not used on Home strip (used on Rooms tab)
category_registry/list	getCategoryRegistry()	Loaded; not drawn on Home
config_entries/get	getConfigEntries()	Music Assistant ids — room media, not Home first paint

3.2 Admin APIs that the Home tab actually needs

API	Function	Home section
GET /api/config	initial-load fetch → setBadgeConfig	Which rooms to show (selected_areas), selected_cameras, camera_sensors, locks_armed
GET /api/quick-scenes	fetchMappings() → setAllowedQuickScenes + scenesFetched	Quick scene cards (max 4). Reveal gate.
GET /api/home-access	fetchMappings() → selectedLockIds / selectedCoverIds + homeAccessFetched	Which locks + garages appear. Reveal gate.
GET /api/covers	fetchMappings / initial-load → coverMappings	Garage pills (coverType === garage) + duration
GET /api/lock-passage	fetchMappings() → lockPassageConfigs	Lock dots: unlocked if lock OR door sensor is on
GET /api/sensors	fetchMappings → sensorMappings	Room door badges; doorsOpen count
GET /api/monitored-entities?type=light + /api/light-types	fetchEnrichedLightMappings()	Not required to show room cards; used when you open a room
GET /api/monitored-entities?type=media_player	fetchMappings()	Room media grouping — not a Home strip item
GET /api/climate-mappings	fetchMappings()	Not drawn on Home
GET /api/alerts	setAlertRules	PersonBadges alert chips (if family row is on)
GET /api/entities	monitored/ignored refs	Not drawn; used for in-app notification filter
GET /api/room-tracking/lookup	setRoomTrackingLookup	May auto-open a RoomSheet after home appears
GET /api/notifications/history + /log	useNotifications()	Bell unread badge in header
GET Frigate config (proxied)	FrigateService.getConfig()	Camera strip. Home does not wait except the strip's own skeleton.
GET /api/cameras	HA camera fallback	Camera strip if Frigate returned nothing
POST /api/sessions/heartbeat	startHeartbeat()	Invisible; session tracking

4. Each Home block — data + functions

4.1 HeaderV2

- **Greeting / name** — route params userName (from splash SecureStore logged_in_user).
- **Weather** — first entity whose id starts with weat her . (temperature, state → icon).
- **City** — HA get_config location_name (cityName).
- **Humidity** — weather.attributes.humidity, else sensor.*humidity.
- **Indoor temp** — sensor with indoor/room + temp in the id, else climate.current_temperature.
- **Bell** — unreadCount from useNotifications (history + log APIs).
- **Mic** — does not load Butler on appear; only canOpenButlerCall() when tapped.

4.2 StatusBadges

- **Lock dots** — all Lock . * entities (up to 6). Lit if lock is unlocked/open OR its passage sensor is on (lockPassageConfigs).
- **Lights count** — sum of room-card activeLights (same rule as room badges: countable units, not master controller).
- **AC count** — climate entities that are not off/unavailable, grouped by selected parent rooms (getAllActiveDevices('ac')).
- Taps: locks → LocksModal; lights/AC → DevicesToggleModal. Those modals are not loaded as visible UI until tap.

4.3 QuickScenes

- IDs from GET /api/quick-scenes, matched to live HA scene entities, sliced to 4.
- Function on tap: handleScenePress → callService(scene, turn_on).
- Edit pencil (if used) hits the same admin API; not required for first appear.

4.4 HomeAccess

- **homeLocks** — lock.* filtered by selectedLockIds from /api/home-access (or by room area if that list is null).
- **homeCovers** — coverMappings where coverType is garage, filtered by selectedCoverIds, joined to live HA state.
- Control: callService('lock', lock|unlock) and callService('cover', open_cover|close_cover|stop_cover).
- Shutters are not on this home strip (they live inside room curtains).

4.5 RoomsList

- **getRoomsWithCounts()** — areas from getSelectedAreasForDashboard(registryAreas, badgeConfig), then filterParentRoomsForDashboard (hides sub-rooms like Toilet from the home strip).
- Per room: getRoomEntities(...) using devices, entity registry, live states, sensorMappings, coverMappings, mediaMappings.
- Badges: activeLights, activeAC, activeCovers, activeDoors, presence.
- Order: savedRoomOrder from SecureStore room_reorder_config.
- Photos: HA area picture via haUrl + token (expo-image).
- Tap: handleRoomPress → setRoomPageBootstrap + navigate to /room (or RoomSheet on home depending on tab).

4.6 HomeCameraStrip

- Stays on CamerasSkeleton until frigateConfigResolved (getConfig success or fail).
- Cameras: Frigate getConfig().cameras, else GET /api/cameras.
- Which ones show: badgeConfig.selected_cameras.
- Each card: WebView of FrigateService.getStreamUrl() or getHASnapshotUrl().
- Overlays: camera_sensors from /api/config + live binary_sensor entities.
- Home page does **not** wait for streams before showing header/rooms — only the strip waits.

5. Local settings read on this page (SecureStore)

Key	Effect on Home
ha_active_profile_id + ha_profiles	HA URL, token, admin URL — nothing else can load without this
settings_show_family	Show or hide PersonBadges
settings_show_voice_assistant	Mic in header (Butler)
room_reorder_config	Order of room cards
settings_auto_room_visit / resume	May open a room sheet after home is up (presence)

6. Loaded in the same page, but not part of first Home content

- Rooms tab, CCTV tab, Settings tab, Brain/Butler tab — mounted hidden or on first visit.
- RoomSheet / room route — only after you tap a room.
- LocksModal, DevicesToggleModal, SecurityControlModal, FrigateCameraModal, NotificationModal — on tap.
- Butler WebSocket / Gemini — only on mic tap (runButlerBackgroundSetup).
- Heartbeat, push token (from root layout), ignored-entity list — background.
- Light/media/climate mappings — needed inside a room, not to draw the home strip.

What “first appear” means in code: connectionConfig.loaded, then skeletons, then entities + scenesFetched + homeAccessFetched → revealStep 5. That is the moment header, badges, scenes, locks/garage, and rooms pop in. Camera thumbnails fill in when Frigate (or /api/cameras) answers.