```
0460
             6800 : V8=00 -- "
  62
             1474 ; BETT2 -- Jump into main part of sub
      BETT1 :3900 ;SK=00 -- If minimum to bet still = $0, skip into next
  64
  66
             1474 BETT2 -- Else jump to continue betting
      ; TEST FOR PASS
  68
                   DINDX -- Set "I" to dealer index storage byte
             F065 ; GET
  6A
                        -- VO= M(I) = the current dealer number
             5040 ;=SKIP -- If V0=V4 (and minimum=30) all pass; skip
  6C
  бE
             1474
                  BETT2 -- Else jump to continue betting
0470
             6F01 : VF=01 -- Set VF=01 to flag no open bets
             00EE ; RET -- Then return (all players passed) (exit sub)
      BETT2:604F; V0=4F -- V0 passes value to timer sub
  76
             2620 : TIMER -- Do sub -- wait before continuing
  78
                  ARROW -- Do sub -- advance arrow next player
  7A.
             8400 ; V4=V0 -- Save player number in V4 (V0=AINDX)
  7C
             2518
                   AMT
                        -- Do sub -- V0=total bet so far for player
             40FF ; SK≠FF -- Skip if total ≠ FF (Player folded if = FF)
  7E
0480
             1464
                   BETT1 -- Jump back to skip the folded player
             4900 ;SK \( \delta 00 -- If \text{ minimum } \neq \$0, \text{ skip (bet was opened)}
  32
  84
                  BETT3 -- Else jump forward to skip next part
             14A8
      FIGURE MINIMUM BET
  86
             2820 ; BET$ -- Do sub -- erase betting amount displayed
  88
             2518 AMT -- Do sub -- V0=total bet by player
  8A.
             8100; V1=V0 -- Save the amount in V1
             A9B2 ; TOTAL -- Set "I" to storage of <u>last</u> betting total
  8C
  8E
             F065 GET
                         -- V0=last player to bet total bet
0490
             8015 : VO-V1 -- Subtract the totals bet
             8900 ; V9=V0 -- Let V9=the result -- the minimum bet
  92
             2820 : BETS -- Do sub -- display the minimum bet
  94
      BET CALLED?
  96
             3900 ;SK=00 -- If minimum goes to $0, skip next
             14A8 BETT3 -- Jump to continue if V9≠00
  98
             6003 ; V0=03 -- Message #3 index (bet called)
  9A
             283E :MCENT -- Do sub-display message
  9C
             282A : RSE$ -- Do sub -- erase raise number
  9E
```