```
0059
      9A
          GHI
                 RA
      BD
          PHI
  5A
                 RD : RD . 1 = RA . 1
  5B
      06
          LDN
                 R6 ;Get next free address in deck (VE)
  5C
      AD
          PLO
                 RD : RD \cdot O = M(R(6)) = VE
  5D
      8F
          GLO
                 RF : D=RF.O: Begin
  5E
5F
                 RA: RA.O=D Restore RA.O to first card
      AA
          PLO
      4C
          LDA
                 RC : D=M(R(C)) Get a throw away
0060
      52
          STR
                 R2 : Push for comparing to hand
  61
      FB
          XRI
                    But check if = FF stop byte
  62
      FF
  63
      3A
          BNZ
                    :If \neq FF, branch to 0C69
  64
      69
  65
66
      8D
          GLO
                 RD : (Begin exit)
      56
          STR
                 R6 : M(R(6)) (VE) = RD.0 to save index
                 R2 ; Reset stack pointer
  67
68
      12
          INC
      D4
          SEP
                 R4 ; Return control to Chip-8 Interpreter
  69
      OA.
          LDN
                 RA : Get a card in hand
  6A
      F3
          XOR
                    ;Compare with card on stack
  6B
      3A
          BNZ
                    :If \( \neq \). skip next exchange - continue
  6C
      71
                                             to search
  6D
      4D
          LDA
                 RD :Get card in deck
  6E
      5A
          STR
                 RA ;Store in hand
  6F
      30
          BR
                    ; Branch to OC5D for another search
0070
      5D
  71
      1A
           INC
                 RA : Else RA=RA+1 to continue search
  72
      30
                    Branch to 0069
          BR
      69
  73
0074
          (12 bytes)
                         -- Available -- not used by program
0080
         (12 bytes)
                         -- More ASCII characters
                       BET MODULE CONTROL SUB
             :6007 ; VO=07 -- Message #7 (TRY AGAIN)
0080
      MOD+
              283E : MCENT -- Do sub -- display error message
  8E
0090
             :3404 ;SK=04 -- Skip next only for user (player #4)
      MOD
              138A BET -- Go betting modules other players
  92
              6100 ; V1=00 -- Initialize V1=00=answer
  94
  96
      MOD1
             :FOOA : VO=KY -- Get keypress in VO (waits)
              400E ;SK≠0E -- If ≠ OE, skip to continue
  98
              1CA2 : MOD2 -- Else go to exit
  9A
```