

MyDAW Operation Manual

From your first recording to editing, mixing and exporting

Version 2.1

MyDAW is Mac software (a DAW) for recording sound from a microphone or audio interface and for playing back, editing and mixing many tracks together.

This manual follows the order in which you actually work, so that even first-time DAW users will not get lost. Start by reading chapters 2 to 5 in order while you record your first song.

The screens can be shown in English or Japanese (chapter 15). This manual describes the English screens.

Contents

1. What you can do with MyDAW
2. Getting ready
3. The main window
4. Your first recording
5. Playback and basic controls
6. Editing clips
7. Punch-in recording and layered takes
8. Recording through effects (input monitoring)
9. Using the mixer
10. Effects (plug-ins) and FX channels
11. Tempo, click and ruler
12. Adjusting the view
13. Saving, opening and moving projects
14. Importing WAV files and exporting
15. Settings (audio and language)
16. Keyboard shortcuts
17. Troubleshooting
18. Glossary

1. What you can do with MyDAW

- **Record** in mono or stereo on as many tracks as you like, at 24-bit and 44.1, 48, 88.2 or 96 kHz.
- **Overdub**: record a new track while listening to tracks you have already recorded.
- **Punch in**: re-record just the part that went wrong. The joins are smoothed automatically.
- **Edit** recordings (clips): move, trim, split, duplicate, change volume, fade (with adjustable curves), normalize and reverse. Select several clips or a time range at once and cut, copy and paste. Everything can be undone.
- **Organise** tracks in folders, which move, mute, solo and fold as one.
- **Mix** with faders, pan, mute, solo and meters.
- **Use effects**: Audio Unit (AU) and VST3 plug-ins such as compressors, EQs, reverbs and amp simulators.
- **Export** the finished mix as one WAV file.

2. Getting ready

What you need

- A Mac with Apple Silicon (macOS 13 or later)
- A microphone or an audio interface (the Mac's built-in microphone also works)
- Headphones (if you use speakers while recording, the microphone picks them up)

Start MyDAW and choose a project

- 1 Double-click `MyDAW.app`.
- 2 On the start screen choose **New Project** or **Open Project** (to continue earlier work).
- 3 For **New Project**, choose a folder in the save panel, type the project name in **Name** and click **Create**. MyDAW creates a `.mydaw` file with that name and a **Recordings** folder for your audio in the chosen folder.
- 4 For **Open Project**, choose the `.mydaw` file of an existing project.

A folder for each project Click **New Folder** at the bottom left of the save panel to make a folder for the project there and then. The new folder is selected, so just type the name and click **Create**. If you choose the Desktop or a similar place directly, the **Recordings** folder is created there.

Recent Projects The **Recent Projects** list below the buttons shows up to 50 projects you have opened or saved, newest first. Click a project name (in orange) to open it without choosing its file. The date on the right is when it was last saved.

First launch only When macOS asks whether “MyDAW” may access the microphone, choose **Allow**. Without it you cannot record.

Plug-in scan Right after launch, a log shows MyDAW looking for installed plug-ins. From the second launch on this takes almost no time.

One-time setup

Click the gear button  at the top to open **Settings** and select your equipment (details in chapter 15).

- 1 Choose your audio interface for **Input device** and **Output device**.
- 2 Set **Buffer size** to **256** to start with.
- 3 Click **Apply**. If you changed a device, choose **Save and Restart** when MyDAW asks to restart.

The macOS input and output change too While it runs, MyDAW also makes the devices chosen here the macOS input and output (System Settings → Sound), and puts the previous ones back when it quits. Do not change the input or output in System Settings while MyDAW is running.

Screen language At first the screens follow the macOS language (Japanese or English). You can choose “English” or “日本語” under **Language** in Settings (chapter 15).

3. The main window




Figure 3-1 Layout of the main window

1	Transport bar: buttons for play, record, save and so on, plus time and tempo displays.
2	Track headers: track name, record arm, mute/solo, input selection and more.
3	Ruler: time (or bars and beats). Click it to move the playback position there.
4	Track lanes: where your recordings (clips) appear as waveforms.
5	Playhead (line and ●): the current playback / recording position. Orange when stopped, green while playing, red while recording (green while waiting for a punch-in). While the transport runs, the ● bounces on every beat.
6	Mixer: volume, pan and effects for every track. Drag its top edge to change its height (at least 220 pt always stays between the send/fader divider and the bottom edge). The ▼ on its bar folds it away (chapter 9).
7	Status bar: the audio device in use, CPU (audio processing load) and where recordings are saved.
8	Punch range: the part re-recorded with punch-in (chapter 7).

The open project's name (the file name without `.mydaw`) is shown in the middle of the bar at the very top of the window, where the close button is.

CPU meter and dropout mark

CPU in the status bar shows how much headroom audio processing has left: the time taken to produce one buffer of sound as a share of how long that sound lasts. Near 100% processing can no longer keep up and the sound breaks up (a dropout).

- **Bar colour:** green while there is room, yellow above 60%, orange above 80%, red at 100%.
- **Dropout:** a red mark shown for 3 seconds when processing fell behind and the sound broke up.
- **Details:** hover over the CPU meter to see the average and peak over the last second, MyDAW's CPU usage across all cores, and how many dropouts there have been since launch and when the last one was.

Why it differs from Activity Monitor Activity Monitor shows how much work the whole Mac is doing. The CPU meter shows whether each buffer is finished in time, so it can be high while the Mac as a whole has room to spare. This is the value that matters for dropouts.

Transport bar




Figure 3-2 Transport bar (hover over a button to see its name)

No.	Button	What it does
1	Settings	Opens Settings (audio devices, language and more; chapter 15).
2	Undo	Undoes the last clip edit ($\text{⌘}Z$).
3	Redo	Redoes an undone edit ($\text{⌘}Z$).
4	Rewind	Returns to the start, 00:00.000 (⏮). With a song start flag, it first returns to the flag (chapter 11).
5	Play / Pause	Starts and stops playback (Space). This button does not record.
6	Record (red circle)	Starts recording on record-armed (R) tracks (R key).
7	P	Turns punch in/out on (chapter 7).
8	Rollback (↶)	Turns rollback recording on: recording starts playing a few bars before the playhead (chapter 4). The number is the bars to roll back (set in Settings). Shown dimmed while punch is on, because punch recording does not use it.
9	Metronome	Click on/off (also while playing or recording). Right-click it for a volume fader that changes the click volume, also while playing.
10	Save	Saves the project ($\text{⌘}S$).
11	Open	Opens a project ($\text{⌘}O$).
12	Snap	Makes clip moves and trims snap to beats.
13	Auto-scroll	Turns on/off the view following the playhead while playing or recording (orange when on). When off, the view stays put even if the playhead leaves the screen.
14	Displays	TIME (position), TEMPO (type the BPM), FORMAT (recording format and sample rate).
15	View scaling	Horizontal zoom, track height, waveform height (chapter 12).
16	Ruler mode	Switches the ruler between time and bars/beats.

Track header




Figure 3-3 Track header

1	Colour bar: click to open a colour palette and change the track colour; "Custom..." lets you pick any colour.
2	Track name: double-click to rename.
3	Mono / Stereo: the track's channel count. Can be switched even on a track that already has recordings. While recording, it is locked (greyed out) on record-armed (R) tracks only. The recording files are not changed: on a mono track, stereo clips play with L and R summed at half level each; on a stereo track, mono clips play on both L and R. Switching back restores the original sound.
4	X: deletes the track after you click Delete in the confirmation message. Deleting a track cannot be undone with  Z.
5	R record arm, M mute, S solo (hear only this track), I input monitoring (chapter 8). M or S lit grey means the track's folder has it on; it cannot be pressed then. R cannot be pressed while recording, and a track being recorded cannot change its input or be deleted.
6	Input channel: the audio interface input used for recording.
7	Meter: input level while armed, output level otherwise.
8	Height: drag the bottom edge to change the track height. Making it lower hides the meter first; it can shrink until only the track name and buttons show.

To add a track, click the **+** button above the track headers and choose **Add Track**. The track is added below the selected track (the current track). For **Add Folder** in the same menu, see "Grouping tracks in folders" below.

Changing the track order

Grab a free spot on a track header (around the track name or the meter) and drag it up or down. While you drag, the track follows the mouse and a white line shows where it will land. Release the mouse to drop it there.

The mixer channels follow the same order (they cannot be reordered in the mixer itself). A drag cannot start on a button, a menu or the bottom edge (height). Reordering tracks cannot be undone with Z.

Grouping tracks in folders

With many tracks, grouping them by part (guitars, keyboards, ...) in folders keeps the list easy to read.




Figure 3-4 A folder and the tracks in it

1	Colour bar: click to change the folder's colour.
2	▼ / ►: closes (►) or opens (▼) the folder. The tracks of a closed folder are not shown, but they still play and record.
3	Folder name: double-click to rename.
4	M / S: mutes / solos every track in the folder, whatever the tracks' own buttons say. Press again and each track goes back to its own state. Not available while the folder is empty.
5	X: deletes the folder after you confirm with Delete . Its tracks are not deleted; they stay where they are, out of the folder.
6	Tracks in the folder: shown indented, with a line in the folder's colour on their left.
7	Grey M / S: on because of the folder's M / S; they cannot be pressed until the folder's button is turned off.

- **Making a folder:** + → **Add Folder**. The folder is placed above the current track (above its folder when the current track is in one). Folders cannot be put inside folders.
- **Moving tracks in and out:** drag the track. When the white drop line is indented, the track goes into the folder. Below a folder's last track, dropping on the lower half of that track puts it inside, and on the upper half of the row below puts it outside. Dropping on a closed folder puts the track at the end of that folder.
- **Moving a folder:** drag the folder's row; its tracks move with it.
- Clicking a folder does not make it the current track. A track added inside a folder takes the folder's colour.

Header right-click menu

Right-clicking a track or folder row shows the menu below. Right-clicking a track makes it the current track.

Item	What it does
Add Track	Adds a track above the clicked track (inside the same folder for a track in a folder). For a folder, adds the track as the folder's first.
Add Folder	Adds a folder above the clicked track or folder. Not shown for a track inside a folder.
Show in Mixer	Scrolls the mixer so the track (for a folder, where the folder starts) is at its left edge.

4. Your first recording

Here you record one track and listen back to it.

- 1 **Choose a track:** click its **R** button so it turns red (armed).
- 2 **Choose the input:** in the input channel menu (figure 3-3, item 6) pick the input your microphone or guitar is connected to. For a single voice or guitar, set the track to **Mono**.
- 3 **Check the level:** play and watch the meter. The loudest parts should reach about the yellow area. If it reaches red, turn down the input gain on your audio interface.
- 4 **Choose where to start:** click the ruler, or press **←** to start from the beginning.
- 5 **Record:** click the red **Record** button (or press **R**) and perform. The waveform is drawn as you go.
- 6 **Stop:** press **Space**. The recording becomes a clip.
- 7 **Listen back:** turn off **R**, press **←**, then **Space**.

Recording along with a backing After the first track, add a new track, arm it and record in the same way. You will hear the first track while recording the second. While recording, older clips on the track being recorded are silenced.

Starting with a run-up (rollback recording) Turn on the rollback button (figure 3-2, item 8) and recording starts playing the set number of bars before the playhead, so you can play along into the take. The recording itself starts at the playhead, and the clip begins there. The run-up is recorded too: drag the clip's left edge to the left to bring it back. Set the number of bars in Settings (**Rollback when recording**). When punch in/out is on, the punch range is used instead.

Recording in time Type the BPM into TEMPO and turn on the metronome before recording to play along with a click (chapter 11).

Recording files Recordings are saved as WAV files in the Recordings folder. The file name contains the track name, channel count and sample rate.

5. Playback and basic controls

To...	Do this
Play / stop	 or the Play button
Go back to the start	 or the Rewind button
Jump to a position	Click the ruler (also while playing)
Hear only some tracks	 (solo) on those tracks
Silence some tracks	 (mute) on those tracks

When the playhead reaches the right edge during playback, the view scrolls on automatically (turn this on or off with the Auto-scroll button in the transport bar). When stopped, drag the knob (●) of the scroll bar below the lanes to move around freely (clicking elsewhere on the bar does nothing).

6. Editing clips

One recording is called a **clip**. Editing never changes the original recording file (non-destructive editing), so feel free to experiment.




Figure 6-1 Clip handles

1	Left / right edges (trim): move the pointer onto the clip's left or right edge line and it turns into an arrow (pointing right → at the left edge, left ← at the right edge); drag to shorten or lengthen the audible part.
2	Fade in: drag the white dot at the top left to the right so the sound starts gradually. Over the dot, the pointer turns into a pointing hand.
3	Fade out: drag the white dot at the top right to the left so the sound ends gradually (the pointer turns into a pointing hand, as for the fade in).
4	Gain: drag the short bar at the top centre up or down to change the clip volume ($-\infty$ to +36 dB; below -72 dB it becomes $-\infty$, silence). Over the bar, the pointer turns into an up-down arrow.
5	Body: click to select (thick white frame), drag to move — also onto another track.
6	Fade curve: the white diamond in the middle of each fade line (the pointer turns into a pointing hand over it). Drag it up or down to change the fade's shape (see “Shaping a fade” below).
7	Value readout: while you hold handle 2, 3, 4 or 6, a small box shows the fade length, the clip volume (dB) or the curve shape.

Waveforms are drawn at the level you will actually hear: they shrink along the fade curves, and raising or lowering the gain makes them taller or shorter.

Shaping a fade

Drag the diamond in the middle of a fade line (figure 6-1, item 6) up or down to bend the fade. The readout shows the level at the exact middle of the fade.

Diamond position	Fade shape
Moved up	Bowed up: a fade-in rises quickly; a fade-out holds its level and drops late.
Middle at -3.0 dB (Equal Power)	Keeps the perceived level steady — the best shape for crossfades. The diamond snaps here when close.
Middle at -6.0 dB (Linear)	A straight line. The diamond snaps here when close.
Moved down	Sagging: a fade-in rises slowly; a fade-out drops early.

Double-click the diamond to return to **Auto**: linear for a fade against silence, equal power for a crossfade over another clip. If a fade is too short to show its diamond, zoom in horizontally.

Selecting clips




Figure 6-2 Marquee (1), the clips it selected (2), and a range selection (3)


To...	Do this
Select one clip	Click it
Add to / remove from the selection	 -click or  -click
Select several at once (marquee)	Drag from an empty spot to draw a frame (figure 6-2, item 1). Every clip the frame touches is selected (item 2), across tracks too.
Add with a marquee	 -drag
Select everything	
Clear the selection	Click an empty spot, or press 

Dragging any selected clip moves all selected clips together as one block (also up or down to other tracks). If you release where any of them would have no track to land on (for example below the last track), they stay on their tracks and move in time only.

Selecting a time range

Instead of whole clips, you can select “from this second to that second”. Use it to remove or keep just part of a clip.

- 1 Hold  and drag from where the range should start to where it should end. You can start on a clip or on an empty spot.
- 2 The range is shown as a white band (figure 6-2, item 3). Drag up or down to extend it over several tracks.
- 3 Then use one of these:

Action	Result
 (or right-click → Delete Range)	Removes the audio inside the range (leaving silence). Clips are split at the range edges.
Right-click → Crop to Range	Keeps only the audio inside the range and removes what is before and after it.
Right-click → Split at Range Edges	Splits clips at both ends of the range.
 / 	Copies / cuts only the audio inside the range.

Cut, copy, paste and duplicate

-  (cut),  (copy): take the selected clips (or, with a range selected, the audio in the range).
-  (paste): pastes at the **playhead**. Material copied from several tracks keeps its layout, with its top track landing on the **selected track**.
-  -drag a clip: leaves a copy in place while you move it (applies to every selected clip).
- Cut / Copy / Paste at Playhead are also in the right-click menu.

While typing a name When you are typing in a text field (such as a track name), , ,  and  edit the text instead.

Right-click menu

Right-clicking a clip that is not selected selects it. Right-clicking a selected clip keeps the selection, and the menu commands apply to **all selected clips** (with several, the items show the count, such as “(3)”). Right-clicking inside a selected range keeps the range and shows the range menu.

- **File name:** the top of the menu shows the name of the clip's audio file (for example *Bass_001.wav*). Choose it to show the file in the Finder (with several clips selected it shows the count, such as “3 Clips”). New recordings are named “*track name_number.wav*”, the number going up by one with each take.
- **Cut / Copy / Paste at Playhead:** cut, copy, and paste at the playhead.
- **Delete Range / Crop to Range / Split at Range Edges:** shown only while a range is selected.

- **Normalize:** sets the clip's gain so its loudest sample reaches 0 dBFS (the 24-bit maximum). The whole recording is measured, including parts hidden by trimming. The audio file is not changed (the gain limit is +36 dB).
- **Reverse:** plays the clip backwards. A reversed WAV file (such as Reverse_Bass_001.wav) is written to Recordings and the clip switches to it. Fade lengths and shapes swap ends as well.
- **Strip Silence...:** removes the parts where the audio stays at or below the silence level for at least the given number of seconds. Useful for clearing the unrecorded parts of stems exported from another DAW. In the dialog, set the silence level (dB, -72 dB at first), the minimum silence length (seconds) and the fade in/out (ms, 10 ms at first). Any single sample above the silence level counts as sound, so for stems with dither or faint noise, set the level above it. To remove only digital zero, use -144 dB. The clips are split around the silent parts, the silent pieces are deleted, and the new clip edges get fades. The fades sit outside the sound (in the silence), so the starts and ends of the sound are not cut into. A fade longer than half the minimum silence length is shortened to half of it. The audio files are not changed.
- **Choose Recording File...:** picks the file again if it cannot be found. Available when a single clip is selected.
- **Mute / Unmute Recording:** silences the clips. If any of them is not muted the item mutes them all; when all are muted it unmutes them.
- **Duplicate Recording:** copies the selected clips as one block whose start lands on the playhead (spacing and tracks kept). The copies become the selection.
- **Split at Cursor:** splits the clips the playhead is inside in two. Unavailable when the playhead is inside none of them.
- **Delete Recording:** deletes it.

Snap

With Snap on (figure 3-2, item 12), clip moves, trims, range selections, moving the playhead by clicking the ruler, and moving the song start / end flags snap to whole beats. Turn it off for fine positioning.

Undo and redo

Moves, trims, fade lengths and shapes, gain, delete, split, duplicate, range edits, cut and paste, normalize, reverse, recordings and WAV imports can be undone with  and redone with  (while stopped).

Undoing a recording or an import removes the clip; the file stays in the Recordings folder.

7. Punch-in recording and layered takes

Use this when a take is almost perfect except for a few bars: re-record only that part.




Figure 7-1 Punch range and the re-recorded part on top

- 1 Drag the red handles of the **punch range** on the ruler (figure 7-1, item 1) to the part you want to redo (they move in beats).
- 2 Click **P** in the transport bar to enable punch in/out (the range turns red).
- 3 Turn on **R** on the track to redo.
- 4 Click Record a little before the range and perform. Only what falls inside the range is used, and only that part is shown while you record.
- 5 When you stop, the new part appears as a new clip (item 2) on top of the original clip.

How overlapping clips play

- Where clips overlap, **only the clip recorded later (the upper clip) plays**. The hidden part of the original clip is shown darker, with a flat (silent) waveform.
- The joins automatically get a **crossfade** (item 3), so there are no gaps or clicks. The default is 10 ms with an equal-power shape. Across the crossfade the upper clip's waveform grows while the lower clip's shrinks.
- Moving the fade handles of the upper clip (item 4) changes the crossfade length, and the diamond in the middle of the fade line changes its shape (chapter 6). The lower clip automatically gets the same shape mirrored. The lower clip's fade on the overlapped side cannot be edited.
- If you move or delete the upper clip, the lower clip automatically plays normally again.
- You can punch in as many times as you like over the same place. The last take is always on top, and every join gets its own crossfade.

Fine-tuning the range The whole pass is saved, including audio outside the range. Drag the edges of the upper clip to extend the re-recorded part.

This rule applies to every overlap Not only punch takes: whenever clips overlap after moving or duplicating, the clip on the higher layer wins.

Clip layers (which clip is on top)

- The layer order is **the order in which clips were added to the track**: the later a clip was recorded, the higher it is.
- Dragging a clip within the same track does **not** change its layer. For example, you cannot bring the first punch take above the second by moving it.
- Clips made with **Duplicate Recording** or paste (V), and clips moved to another track, are placed on **top** of that track.
- With -drag, the copy left behind sits directly below the clip you moved.

8. Recording through effects (input monitoring)

Use this, for example, to hear your guitar through an amp simulator while recording.

- 1 Insert the effect you want (e.g. an amp simulator) on the track (chapter 10).
- 2 Turn on **R** and **I** on the track. When **I** is filled green you hear the input through the effects (also while stopped).
- 3 Record with the Record button as usual.

Turning I on while playing Input monitoring cannot be rewired during playback. If you turn **I** on while playing, you start hearing the input after you stop, once reverb and other tails have faded (usually 1–2 s, at most 8 s). If you turn **I** off while playing, the input stays audible until you stop. Switching **I** while stopped takes effect at once.

The dry signal is recorded The file contains the sound before the effects, so you can change the amp settings later.

If you hear a delay Set **Buffer size** to 128 or 256. If your audio interface's direct monitoring is on, you will hear the dry and processed sound doubled — turn direct monitoring down for that input.

Feedback With a microphone and speakers you may get feedback (a loud squeal). Use headphones.

9. Using the mixer

The mixer at the bottom sets each track's level, left-right position (pan) and effects. Tracks come first (in the same order as the track headers), then FX channels, with MASTER (the overall output) at the right.




Figure 9-1 One mixer channel (strip)

1	INSERT (plug-in list): green dot turns a plug-in on/off, click the name to open its window, drag to reorder, X removes it.
2	+ : adds a plug-in.
3	Section divider: drag up or down to change the height of the INSERT, SEND and control sections (all channels together).
4	SEND: how much goes to an FX channel. Drag sideways, or double-click the value to type it.
5	Pan: drag sideways to place the sound left or right. <C> is centre, L56 left, R75 right.
6	M / S: mute and solo. FX channels have them too.
7	Level value: current fader value in dB. Double-click to type (e.g. -6, -inf).
8	Fader: drag up or down to change the level. 0 dB is the reference; you can go up to +6 dB.
9	Meters (L / R): level of each side. Green → yellow (from -12 dB) → red (from -6 dB). The white line shows the recent peak.
10	Name: click to select the track. Double-click an FX channel's name to rename it. The current track's name is shown black on white.

A vertical line in the folder's colour stands left of each folder's tracks, and one in the FX colour left of the first FX channel. Click a line to open the colour palette: it changes the folder's colour (the folder in the track headers follows), or the colour of every FX channel.

Handy actions

- -click: resets faders and sends to 0 dB and pan to centre.
- -drag: fine adjustment.
- Drag the mixer's top edge: changes the height of the whole mixer.
- ▼ on the mixer's bar: folds the mixer down to its bar; ▲ brings it back.
- Right-click a track header → **Show in Mixer**: scrolls that track's channel to the left edge (unfolding the mixer if needed).
- Right-click in the mixer: **Add FX** adds an FX channel.
- Right-click an FX channel strip: **Remove (channel name)** removes that FX channel.

Level tip Adjust the track faders so the MASTER meter does not reach red. If the mix is too loud, lower the tracks rather than MASTER.

10. Effects (plug-ins) and FX channels

Inserting an effect

- 1 Stop playback (plug-ins cannot be inserted while playing).
- 2 Click  in the channel's INSERT section and choose a plug-in.
- 3 Click the plug-in's name to open its window.

Sound passes through the plug-ins from top to bottom. Drag the names to change the order. Plug-ins on MASTER's **POST** section affect the whole song (a limiter, for example).

Supported formats Audio Unit (AU) and VST3 effects. If a product is installed in both formats, only the AU version is listed (using both at once is unstable). Instruments are not supported.

FX channels (sharing a reverb)

Spatial effects such as reverb are usually placed once on an FX channel; each track then decides how much it sends (SEND).

- 1 Click **Add FX** at the top of the mixer (or right-click → Add FX).
- 2 Insert a reverb on the FX channel and set its Mix (dry/wet) to 100% wet.
- 3 Raise the SEND to that FX on each track.

A send carries the track's sound after its effects, fader and pan, so lowering a track's fader also lowers its reverb.

A new FX channel is named "FX 1", "FX 2", ... with the number after the highest one in use, and takes the colour of the other FX channels (change it by clicking the line left of the FX channels; chapter 9).

Muting and soloing an FX channel

- **M (mute)**: silences the FX channel's output. A reverb tail stops at once.
- **S (solo)**: as with tracks, only soloed channels are heard.
 - Soloing a track also keeps the FX channels it sends to, so you hear its reverb.
 - Soloing an FX channel plays only that FX channel (the effect sound). The dry sound of the tracks sending to it is not heard, which is handy for checking the reverb on its own.

Removing an FX channel

- 1 In the mixer, right-click the strip of the FX channel you want to remove.
- 2 Choose **Remove (channel name)**, for example "Remove Reverb".
- 3 When asked "Delete "FX 1"?" (with the channel's name), click **Delete** (or **Cancel** to keep it).

The plug-ins on that FX channel and every track's send to it are removed as well.

This cannot be undone  does not bring back a removed FX channel. Save the project first if you may need it again.

Automatic delay compensation

Some plug-ins need time to process audio (latency). MyDAW reads the latency they report and adjusts playback timing automatically.

- Latency is compensated for plug-ins on tracks and on FX channels alike, so a reverb on an FX channel stays in time with the dry sound.
- Turning a plug-in off (bypass) does not change the compensation, so switching it during playback never interrupts the sound.
- If a plug-in's latency changes with its settings, the compensation follows.
- The sound right at the start position is heard too. With high-latency plug-ins, playback takes that much longer to get going after you press Play (for example 40 ms).
- A high-latency plug-in on an FX channel also delays input monitoring on armed tracks by that amount (the recording itself is not affected).

11. Tempo, click and ruler

- **Tempo (BPM):** type a number into TEMPO (20–400, default 120).
- **Metronome:** turn it on to hear a click while playing or recording; the first beat of a bar is higher. Turned on during playback or recording, it starts clicking from the next beat.
- **Ruler:** button 16 in figure 3-2 switches between time and bars/beats.
- **Click timing and volume:** **Click timing** (ms) and **Click volume** in the settings.

Song start and end flags

You can place blue song start and end flags on the ruler (the start flag points right, the end flag left). Both are optional.

- **Place:** right-click the ruler and choose **Set Song Start Here** or **Set Song End Here**. The start must be at least one beat before the end.
- **Move:** drag the flag's pennant; the playhead does not move while you hold a flag. Clicking the pole or around it moves the playhead as anywhere else on the ruler. With snap on, the flag moves in beats. While you hold it, its position is shown next to it, in the ruler's units: bar:beat:tick (480 ticks per beat) or h:m:s.ms.
- **Overlapping the punch handles:** the punch handle moves. To move the flag instead, hold  while dragging.
- **Remove:** right-click the ruler and choose **Remove Song Start** or **Remove Song End**.

With flags in place:

- **Rewind** () goes to the start flag. If you are already on it or before it, it goes to 00:00.000.
- **Stop at the end flag:** playback and recording stop when they reach the end flag, and recorded clips are cut at it. Playback started after the end flag does not stop.
- **Export:** the Export Master Mix dialog starts with the flags' positions (chapter 14).

Flags are stored in beats, so they move with a tempo change.

12. Adjusting the view

Adjustment	How
Horizontal zoom	Magnifier buttons, the timeline slider (5–3200 pixels per second), the mouse wheel over the ruler , or a trackpad pinch
Height of all tracks	Track height slider (about 0.3–3×), or  + mouse wheel over the tracks. Using it returns tracks resized one by one to the standard height, so all tracks scale together.
Height of one track	Drag the bottom edge of its header
Waveform height	Waveform slider (1–256×), or   + mouse wheel over the tracks. Does not change the sound.
Mixer height	Drag the mixer's top edge

Zooming with the wheel or a pinch keeps the position under the pointer in place.

Zoomed in far, the waveform shows the individual waves (cycles) of the sound.

The timeline is as long as the song: the end of the last clip (or the song end flag) plus 5 seconds, at least 60 seconds. The part after it is shown darker; the ruler goes on to the right edge of the screen, but clicking there or playing on does not make the song longer. Recording past the end makes the song longer.

13. Saving, opening and moving projects

What a project contains

```
MySong/           ← the folder chosen in the save panel (any name)
├── Ballad.mydaw   ← tracks, clip positions, mixer, plug-in settings, ...
└── Recordings/    ← your recorded WAV files
    └── *.wav
```

The .mydaw file and its folder do not need the same name. Recordings are saved in the Recordings folder next to the .mydaw file. You can rename the .mydaw file in the Finder.

- **Save:** ⌘S, **File** → **Save Project...** or the Save button. “Project saved.” appears when it is done.
- **Save As:** ⌘S or **File** → **Save Project As....** Type a new name and click **Save**: the project is saved as another .mydaw file in the **same folder**, and you go on working in that file. The original file is left as it was. The recordings are not copied, because both use the same Recordings folder. Saving to a different folder is not possible.
- **Open:** ⌘O or the Open button, then choose the project's .mydaw file. You can also click a project name in the **Recent Projects** list on the start screen, or double-click a .mydaw file in the Finder (MyDAW starts if it is not running). If another project is open, you are asked whether to save it first.
- **New:** ⌘N, then choose the folder and name in the save panel (see [chapter 2](#)).

Several projects in one folder You can keep more than one .mydaw file in the same folder. They then all use the same Recordings folder. New recording files get the next free number, so nothing is overwritten.

Recent Projects

- Below the buttons on the start screen, up to 50 projects you have opened or saved are listed, newest first: the project name (without .mydaw) on the left and when it was last saved on the right.
- Hover over a project name to see where the file is. Click it to open the project.
- A project that has been moved or deleted is shown greyed out and struck through, and cannot be opened. Put it back where it was and it can be opened again.
- To take an entry off the list, right-click it and choose **Remove from List** (the project files are not deleted).

Saved with the project: track settings (name, colour, volume, pan, mute, solo, input, R/I), clip positions and edits, mixer and FX, plug-ins and their settings, tempo, metronome, punch range, song start and end flags, and view settings.

Moving to another Mac Copy (or zip) the **whole project folder**, not just the .mydaw file. Install the plug-ins you use on the other Mac too. Renaming or moving the Recordings folder makes clips impossible to load.

Quitting Whether you choose **MyDAW** → **Quit MyDAW** (⌘Q) or close the window, you are asked whether to save (Save / Don't Save / Cancel). Cancel keeps MyDAW open.

Tidying up unused recordings

Repeated punch-ins and deleted takes leave WAV files in the Recordings folder that nothing uses any more. To move them all out of the way:

- 1 Stop playback and recording.
- 2 Choose **File** → **Move Unused Recordings to Unused Folder**.
- 3 When asked that the project needs to be saved, click **Save Project and Continue** (or **Cancel** to stop).
- 4 A list of the moved files appears. Click **OK**.
 - They go to Recordings/Unused. Nothing is deleted, so you can move a file back in the Finder. To free the space, delete the Unused folder in the Finder.
 - Files of deleted clips are moved too. If Undo (⌘Z) could have brought such a clip back, the Undo history is cleared, so Undo never restores a clip whose file has gone.
 - Files that a copied clip uses are kept as in use.
 - When other .mydaw files are in the same folder, the files their projects use are kept too.
 - Only WAV files directly in the Recordings folder are checked.

Why it saves first The check uses the project as it is open now. Saving before moving means no file that the saved project uses is ever moved.

14. Importing WAV files and exporting

Importing a WAV file

- 1 Select the WAV file in Finder.
- 2 Drag it onto a track lane. It is added as a clip at the playhead.

The file is copied into the project's Recordings folder as `Import_001.wav`, `Import_002.wav` and so on (the original is untouched). Files at a different sample rate, and 16-bit or 32-bit files, are **converted automatically to a 24-bit WAV at the current sample rate** as they are copied. Converting a long file may briefly pause the screen.

Exporting the finished mix

- 1 Stop playback and recording.
- 2 Choose **File** → **Export Master Mix...** and pick where to save. The project folder opens, with the name “*project name*_Master_Mix.wav”. The name you choose is saved with the project and offered next time.
- 3 Check the start and end times (seconds). They default to the song start and end flags; without flags, to 0 and the end of the last clip.
- 4 Click **Export**. Exporting takes as long as playing the song. The file runs exactly from the sound at the start to the sound at the end, to the sample (plug-in latency included).




Figure 14-1 Export Master Mix dialog

15. Settings (audio and language)

Open **Settings** with the gear button (not available while playing or recording). Click **Apply** after changing anything.

The screenshot shows a 'Settings' dialog box with a dark background. It is organized into sections: 'Environment', 'Audio', 'Compensation', and 'Other'. Each setting is preceded by a numbered orange circle. The 'Language' dropdown is set to 'English'. The 'Recordings folder' is a text field with '.../MySong/Recordings'. 'Input device' and 'Output device' are dropdowns set to 'Studio 24c'. 'Sample rate' is a dropdown set to '48 kHz'. 'Buffer size' is a dropdown set to '256 frames (5.3 ms)'. Below this, a note states 'Input and output devices use the same Core Audio buffer size.' In the 'Compensation' section, 'Recording latency (optional)' and 'Click timing' are text fields both set to '0.0 ms', with explanatory text below each. In the 'Other' section, 'Click volume' is a slider set to 70%, and 'Rollback when recording' is a text field set to '2 bars' with explanatory text below it. At the bottom right are 'Cancel' and 'Apply' buttons.

Settings

Environment

1 Language English ▾

Audio

2 Recordings folder .../MySong/Recordings

3 Input device Studio 24c ▾

4 Output device Studio 24c ▾

5 Sample rate 48 kHz ▾

6 Buffer size 256 frames (5.3 ms) ▾

Input and output devices use the same Core Audio buffer size.

Compensation

7 Recording latency (optional) 0.0 ms
Corrects the position of recorded clips. Positive values move them earlier.

8 Click timing 0.0 ms
Corrects when the click sounds. Positive values make it sound later.

Other

9 Click volume 70%

10 Rollback when recording 2 bars
In normal recording, the playhead rolls back by this many bars.
Recording starts at the current playhead position.

Cancel Apply

Figure 15-1 Settings

Environment	
1	Language: the screen language (English / 日本語). At first it follows the macOS language.
Audio	
2	Recordings folder: where recordings are saved (normally the project's Recordings folder).
3	Input device: the device you record from.
4	Output device: the device you listen through. It can be the same audio interface as the input or a different device (such as a monitor's speakers).
5	Sample rate: 44.1, 48, 88.2 or 96 kHz. This changes the device's own setting (the one shown in macOS Audio MIDI Setup).
6	Buffer size: smaller means less delay, larger means more stability. Use 128–256 for recording and input monitoring, 512–1024 for mixing. The input and output devices use the same buffer size.
Compensation	
7	Recording latency (optional): corrects the position of recorded clips (ms). Positive values move them earlier. Normally leave at 0.
8	Click timing: corrects when the click sounds (–500 to +500 ms). Positive values make it sound later.
Other	
9	Click volume: loudness of the click.
10	Rollback when recording: how many bars (1–16) the playhead rolls back when rollback recording is on (chapter 4). Recording starts at the playhead position.

Recording with a MacBook's built-in microphone and speakers The built-in microphone and speakers do not tell MyDAW how long their sound processing takes, so recordings may land about 25 ms late (with an audio interface they hardly move). Correct this with **Recording latency (optional)**, set to around **25**.

1. Set the ruler to bars and beats, turn the metronome on, and record a few bars of the click from the built-in speakers with the built-in microphone.
2. Zoom in and see how far right of the beat lines the recorded clicks start.
3. Enter that offset (ms) in **Recording latency (optional)**, click **Apply**, and record again to check that the clicks line up.

When you go back to an audio interface, set the compensation back to 0.

Changes that need a restart When you change Language, Input device, Output device or Sample rate and click Apply, MyDAW asks to restart. Choose **Save and Restart**, **Restart Without Saving**, or **Cancel** (restart yourself later). After the restart the project that was open opens again. A Buffer size change alone takes effect without a restart.

MyDAW also switches the macOS sound devices While it runs, MyDAW makes your chosen input and output the macOS default input and output, and puts the previous ones back when it quits. So while MyDAW is running, other apps also play through the chosen output. If MyDAW crashes they are not restored — set them back in System Settings → Sound.

16. Keyboard shortcuts

Key	Action
	Play / stop
	Record (same as the red Record button; stops when running)
	Go to the song start flag (on or before it: to the beginning)
	Delete the selected clips (or the audio in the selected range)
X / C / V	Cut / copy / paste at the playhead
A	Select all clips
	Clear the selection
Z	Undo
Z / Y	Redo
S	Save
O	Open
N	New project
?	MyDAW Help (opens this manual as a PDF on the web)
-click / -click (clip)	Add to / remove from the selection
Drag (empty spot) / -drag	Marquee select / add with a marquee
-drag (tracks)	Select a time range
-drag (clip)	Duplicate while moving
Double-click (fade diamond)	Reset the fade shape to Auto
Mouse wheel over the ruler / pinch	Horizontal zoom
+ mouse wheel	Track height
+ mouse wheel	Waveform height
-click (mixer)	Fader / send to 0 dB, pan to centre
-drag (mixer)	Fine adjustment
Double-click (values, names)	Type a value / rename

17. Troubleshooting

Problem	What to check
Cannot record / meter does not move	Microphone permission (System Settings → Privacy & Security → Microphone), Input device, the track's R button, the input channel.
No sound	Output device, MASTER and track faders, M (mute) / S (solo), speaker or headphone volume.
Play does not record	Recording uses the red Record button; Play only plays.
Recordings are out of time	Check the buffer size, record the same sound again to measure the offset, and correct it with Recording latency (optional).
The sound breaks up / • Dropout appears in the status bar	Raise the buffer size in Settings (512–1024). Remove or bypass heavy plug-ins. The status bar's CPU meter shows whether the load went down.
Effectuated input sounds late	Buffer size 128–256; turn down the interface's direct monitoring.
A plug-in is missing from the list	Make sure it is an effect (not an instrument). AU effects driven by MIDI are not listed either. Products with an AU version are listed as AU only.
Cannot add a plug-in	Stop playback first.
Cannot import a WAV	Check that the file is an intact audio file such as WAV. Other sample rates and bit depths are converted automatically.
No sound from the chosen output device	After changing devices, restart MyDAW from the dialog. The new device is used only after the restart.
Other apps also play through MyDAW's output	While MyDAW runs, the chosen devices are the macOS defaults. They are put back when MyDAW quits.
After a crash, the Mac still uses MyDAW's devices	Set output and input back in System Settings → Sound.
Playback and recording suddenly stop, and the input stays silent afterwards	This happens when the input or output is changed in System Settings → Sound while MyDAW is running. Restart MyDAW.
Another app's recording (such as a screen recording) is full of loud noise	Launch MyDAW before you start recording, and quit it only after recording ends. MyDAW switches the macOS input and output when it launches and quits.
A clip says its file cannot be found	Right-click → Choose Recording File... and pick the WAV again.
You want the screens in Japanese (or English)	Choose it under Language in Settings, click Apply and restart.

18. Glossary

Term	Meaning
DAW	Digital Audio Workstation — software for recording, editing and mixing.
Track	A lane that records and plays one instrument or part.
Clip	One recorded piece of audio that you can move and edit.
Record arm	Making a track ready to record with its R button.
Punch in/out	Re-recording only a chosen range.
Crossfade	Joining two sounds by fading one out while fading the other in.
Fade curve	The shape in which the level changes during a fade: linear, equal power, bowed up, sagging, and so on.
Equal power	A fade shape that keeps the perceived level steady through a crossfade.
Range selection	Selecting a stretch of time rather than whole clips.
Normalize	Raising or lowering a level so the loudest sample reaches full scale (0 dBFS).
Fader	The control that sets volume.
Pan	Where the sound appears between left and right.
dB (decibel)	Unit of level. 0 dB is the reference; -6 dB is roughly half as loud.
Mute / solo	Silence a track / hear only that track.
Folder	Holds several tracks so they can be moved, muted, soloed and folded together.
Current track	The selected track. New tracks and pastes are placed from it.
Plug-in (effect)	Add-on software that processes sound; formats AU and VST3.
INSERT	Effects placed directly on a channel; sound passes through them top to bottom.
SEND / FX channel	Sending part of a track's sound to a shared effect (the FX channel).
MASTER	The final output where all tracks are combined.
Buffer size	The block size audio is processed in. Smaller means less delay but more CPU load.
Sample rate	How many times per second sound is measured (44.1 / 48 / 88.2 / 96 kHz).
Input monitoring	Listening to the incoming sound through the track's effects.