

# MyDAW Operation Manual

From your first recording to editing, mixing and exporting

Version 3.0

MyDAW is Mac software (a DAW) for recording sound from a microphone or audio interface and for playing back, editing and mixing many tracks together.

This manual follows the order in which you actually work, so that even first-time DAW users will not get lost. Start by reading chapters 2 to 5 in order while you record your first song.

The screens can be shown in English or Japanese (chapter 16). This manual describes the English screens.

# Contents

1. What you can do with MyDAW
2. Getting ready
3. The main window
4. Your first recording
5. Playback and basic controls
6. Editing clips
7. Punch-in recording and layered takes
8. Recording through effects (input monitoring)
9. Using the mixer
10. Effects (plug-ins) and FX channels
11. MyDAW's built-in effects
12. Tempo, click and ruler
13. Adjusting the view
14. Saving, opening and moving projects
15. Importing WAV files and exporting
16. Settings (audio and language)
17. Keyboard shortcuts
18. Troubleshooting
19. Glossary

## 1. What you can do with MyDAW

- **Record** in mono or stereo on as many tracks as you like, at 24-bit and 44.1, 48, 88.2 or 96 kHz.
- **Overdub**: record a new track while listening to tracks you have already recorded.
- **Punch in**: re-record just the part that went wrong. The joins are smoothed automatically.
- **Edit** recordings (clips): move, trim, split, duplicate, change volume, fade (with adjustable curves), normalize and reverse. Select several clips or a time range at once and cut, copy and paste. Everything can be undone.
- **Organise** tracks in folders, which move, mute, solo and fold as one.
- **Mix** with faders, pan, mute, solo and meters.
- **Use effects**: Audio Unit (AU) and VST3 plug-ins such as compressors, EQs, reverbs and amp simulators.
- **Export** the finished mix as one WAV or MP3 file.

## 2. Getting ready

### What you need

- A Mac with Apple Silicon (macOS 13 or later)
- A microphone or an audio interface (the Mac's built-in microphone also works)
- Headphones (if you use speakers while recording, the microphone picks them up)

### Start MyDAW and choose a project

- 1 Double-click `MyDAW.app`.
- 2 On the start screen choose **New Project** or **Open Project** (to continue earlier work).
- 3 For **New Project**, choose a folder in the save panel, type the project name in **Name** and click **Create**. MyDAW creates a `.mydaw` file with that name and a `Recordings` folder for your audio in the chosen folder.
- 4 For **Open Project**, choose the `.mydaw` file of an existing project.

**A folder for each project** Click **New Folder** at the bottom left of the save panel to make a folder for the project there and then. The new folder is selected, so just type the name and click **Create**. If you choose the Desktop or a similar place directly, the `Recordings` folder is created there.

**Recent Projects** The **Recent Projects** list below the buttons shows up to 50 projects you have opened or saved, newest first. Click a project name (in orange) to open it without choosing its file. The date on the right is when it was last saved.

**First launch only** When macOS asks whether “MyDAW” may access the microphone, choose **Allow**. Without it you cannot record.

**Plug-in scan** Right after launch, a log shows MyDAW looking for installed plug-ins. From the second launch on this takes almost no time.

### One-time setup

Click the gear button  at the top to open **Settings** and select your equipment (details in chapter 16).

- 1 Choose your audio interface for **Input device** and **Output device**.
- 2 Set **Buffer size** to **256** to start with.
- 3 Click **Apply**. If you changed a device, choose **Save and Restart** when MyDAW asks to restart.

**The macOS input and output change too** While it runs, MyDAW also makes the devices chosen here the macOS input and output (System Settings → Sound), and puts the previous ones back when it quits. Do not change the input or output in System Settings while MyDAW is running.

**Screen language** At first the screens follow the macOS language (Japanese or English). You can choose “English” or “日本語” under **Language** in Settings (chapter 16).

### 3. The main window




Figure 3-1 Layout of the main window

|   |                                                                                                                                                                                                                                     |
|---|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1 | <b>Transport bar:</b> buttons for play, record, save and so on, plus time and tempo displays.                                                                                                                                       |
| 2 | <b>Track headers:</b> track name, record arm, mute/solo, input selection and more.                                                                                                                                                  |
| 3 | <b>Ruler:</b> time (or bars and beats). Click it to move the playback position there.                                                                                                                                               |
| 4 | <b>Track lanes:</b> where your recordings (clips) appear as waveforms.                                                                                                                                                              |
| 5 | <b>Playhead (line and ●):</b> the current playback / recording position. Orange when stopped, green while playing, red while recording (green while waiting for a punch-in). While the transport runs, the ● bounces on every beat. |
| 6 | <b>Mixer:</b> volume, pan and effects for every track. Drag its top edge to change its height (at least 220 pt always stays between the send/fader divider and the bottom edge). The ▼ on its bar folds it away (chapter 9).        |
| 7 | <b>Status bar:</b> the audio device in use, CPU (audio processing load) and where recordings are saved.                                                                                                                             |
| 8 | <b>Punch range:</b> the part re-recorded with punch-in (chapter 7).                                                                                                                                                                 |

The open project's name (the file name without `.mydaw`) is shown in the middle of the bar at the very top of the window, where the close button is.

## CPU meter and dropout mark

**CPU** in the status bar shows how much headroom audio processing has left: the time taken to produce one buffer of sound as a share of how long that sound lasts. Near 100% processing can no longer keep up and the sound breaks up (a dropout).

- **Bar colour:** green while there is room, yellow above 60%, orange above 80%, red at 100%.
- **Dropout:** a red mark shown for 3 seconds when processing fell behind and the sound broke up.
- **Details:** hover over the CPU meter to see the average and peak over the last second, MyDAW's CPU usage across all cores, and how many dropouts there have been since launch and when the last one was.

**Why it differs from Activity Monitor** Activity Monitor shows how much work the whole Mac is doing. The CPU meter shows whether each buffer is finished in time, so it can be high while the Mac as a whole has room to spare. This is the value that matters for dropouts.

## Transport bar




Figure 3-2 Transport bar (hover over a button to see its name)

| No. | Button              | What it does                                                                                                                                                                                                                      |
|-----|---------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1   | Settings            | Opens Settings (audio devices, language and more; chapter 16).                                                                                                                                                                    |
| 2   | Undo                | Undoes the last clip edit (⌘Z).                                                                                                                                                                                                   |
| 3   | Redo                | Redoes an undone edit (⇧⌘Z).                                                                                                                                                                                                      |
| 4   | Rewind              | Returns to the start, 00:00.000 (⏮). With a song start flag, it first returns to the flag (chapter 12).                                                                                                                           |
| 5   | Play / Pause        | Starts and stops playback (Space). <b>This button does not record.</b>                                                                                                                                                            |
| 6   | Record (red circle) | Starts recording on record-armed (R) tracks (R key).                                                                                                                                                                              |
| 7   | P                   | Turns punch in/out on (chapter 7).                                                                                                                                                                                                |
| 8   | Rollback (↶)        | Turns rollback recording on: recording starts playing a few bars before the playhead (chapter 4). The number is the bars to roll back (set in Settings). Shown dimmed while punch is on, because punch recording does not use it. |
| 9   | Metronome           | Click on/off (also while playing or recording). <b>Right-click</b> it for a volume fader that changes the click volume, also while playing.                                                                                       |
| 10  | Save                | Saves the project (⌘S).                                                                                                                                                                                                           |
| 11  | Open                | Opens a project (⌘O).                                                                                                                                                                                                             |
| 12  | Snap                | Makes clip moves and trims snap to beats.                                                                                                                                                                                         |
| 13  | Auto-scroll         | Turns on/off the view following the playhead while playing or recording (orange when on). When off, the view stays put even if the playhead leaves the screen.                                                                    |
| 14  | Displays            | TIME (position), TEMPO (type the BPM), FORMAT (recording format and sample rate).                                                                                                                                                 |
| 15  | View scaling        | Horizontal zoom, track height, waveform height (chapter 13).                                                                                                                                                                      |
| 16  | Ruler mode          | Switches the ruler between time and bars/beats.                                                                                                                                                                                   |

## Track header




Figure 3-3 Track header

|   |                                                                                                                                                                                                                                                                                                                                                                                                           |
|---|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1 | <b>Colour bar:</b> click to open a colour palette and change the track colour; “Custom...” lets you pick any colour.                                                                                                                                                                                                                                                                                      |
| 2 | <b>Track name:</b> double-click to rename. The current track's name is shown black on white.                                                                                                                                                                                                                                                                                                              |
| 3 | <b>Mono / Stereo:</b> the track's channel count. Can be switched even on a track that already has recordings. While recording, it is locked (greyed out) on record-armed (R) tracks only. The recording files are not changed: on a mono track, stereo clips play with L and R summed at half level each; on a stereo track, mono clips play on both L and R. Switching back restores the original sound. |
| 4 | <b>X:</b> deletes the track after you click <b>Delete</b> in the confirmation message. Deleting a track cannot be undone with  Z.                                                                                                                                                                                        |
| 5 | <b>R</b> record arm, <b>M</b> mute, <b>S</b> solo (hear only this track), <b>I</b> input monitoring (chapter 8). M or S lit grey means the track's folder has it on; it cannot be pressed then. R cannot be pressed while recording, and a track being recorded cannot change its input or be deleted.                                                                                                    |
| 6 | <b>Input channel:</b> the audio interface input used for recording.                                                                                                                                                                                                                                                                                                                                       |
| 7 | <b>Meter:</b> input level while armed, output level otherwise.                                                                                                                                                                                                                                                                                                                                            |
| 8 | <b>Height:</b> drag the bottom edge to change the track height. Making it lower hides the meter first; it can shrink until only the track name and buttons show.                                                                                                                                                                                                                                          |

To add a track, click the **+** button above the track headers and choose **Add Track**. The track is added below the selected track (the current track). For **Add Folder** in the same menu, see "Grouping tracks in folders" below.

## Changing the track order

Grab a free spot on a track header (around the track name or the meter) and drag it up or down. While you drag, the track follows the mouse and a white line shows where it will land. Release the mouse to drop it there.

The mixer channels follow the same order (they cannot be reordered in the mixer itself). A drag cannot start on a button, a menu or the bottom edge (height). Reordering tracks cannot be undone with Z.

## Grouping tracks in folders

With many tracks, grouping them by part (guitars, keyboards, ...) in folders keeps the list easy to read.




Figure 3-4 A folder and the tracks in it

|   |                                                                                                                                                                                              |
|---|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1 | <b>Colour bar:</b> click to change the folder's colour.                                                                                                                                      |
| 2 | ▼ / ►: closes (►) or opens (▼) the folder. The tracks of a closed folder are not shown, but they still play and record.                                                                      |
| 3 | <b>Folder name:</b> double-click to rename.                                                                                                                                                  |
| 4 | <b>M / S:</b> mutes / solos every track in the folder, whatever the tracks' own buttons say. Press again and each track goes back to its own state. Not available while the folder is empty. |
| 5 | <b>X:</b> deletes the folder after you confirm with <b>Delete</b> . Its tracks are not deleted; they stay where they are, out of the folder.                                                 |
| 6 | <b>Tracks in the folder:</b> shown indented, with a line in the folder's colour on their left.                                                                                               |
| 7 | <b>Grey M / S:</b> on because of the folder's M / S; they cannot be pressed until the folder's button is turned off.                                                                         |

- **Making a folder:** + → **Add Folder**. The folder is placed above the current track (above its folder when the current track is in one). Folders cannot be put inside folders.
- **Moving tracks in and out:** drag the track. When the white drop line is indented, the track goes into the folder. Below a folder's last track, dropping on the lower half of that track puts it inside, and on the upper half of the row below puts it outside. Dropping on a closed folder puts the track at the end of that folder.
- **Moving a folder:** drag the folder's row; its tracks move with it.
- Clicking a folder does not make it the current track. A track added inside a folder takes the folder's colour.

## Header right-click menu

Right-clicking a track or folder row shows the menu below (duplicating is not available while playing or recording). Right-clicking a track makes it the current track.

| Item             | What it does                                                                                                                                                                                                                                                                                                                                                                     |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Add Track        | Adds a track above the clicked track (inside the same folder for a track in a folder). For a folder, adds the track as the folder's first.                                                                                                                                                                                                                                       |
| Add Folder       | Adds a folder above the clicked track or folder. Not shown for a track inside a folder.                                                                                                                                                                                                                                                                                          |
| Duplicate Track  | Shown for a track. Adds a copy right below it with the same settings: clips, mixer state (volume, pan, M/S, sends) and plug-ins with their settings. A number is added to the name (“Guitar” → “Guitar 2”, “Guitar 2” → “Guitar 3”; the next free number if that name exists). The copy becomes the current track. Recording files are not copied; the copy uses the same files. |
| Duplicate Folder | Shown for a folder. Copies the folder and its tracks and adds them below the folder's last track. Names follow the same rule as Duplicate Track.                                                                                                                                                                                                                                 |
| Show in Mixer    | Scrolls the mixer so the track (for a folder, where the folder starts) is at its left edge.                                                                                                                                                                                                                                                                                      |

## 4. Your first recording

Here you record one track and listen back to it.

- 1 **Choose a track:** click its **R** button so it turns red (armed).
- 2 **Choose the input:** in the input channel menu (figure 3-3, item 6) pick the input your microphone or guitar is connected to. For a single voice or guitar, set the track to **Mono**.
- 3 **Check the level:** play and watch the meter. The loudest parts should reach about the yellow area. If it reaches red, turn down the input gain on your audio interface.
- 4 **Choose where to start:** click the ruler, or press **←** to start from the beginning.
- 5 **Record:** click the red **Record** button (or press **R**) and perform. The waveform is drawn as you go.
- 6 **Stop:** press **Space**. The recording becomes a clip.
- 7 **Listen back:** turn off **R**, press **←**, then **Space**.

**Recording along with a backing** After the first track, add a new track, arm it and record in the same way. You will hear the first track while recording the second. While recording, older clips on the track being recorded are silenced.

**Starting with a run-up (rollback recording)** Turn on the rollback button (figure 3-2, item 8) and recording starts playing the set number of bars before the playhead, so you can play along into the take. The recording itself starts at the playhead, and the clip begins there. The run-up is recorded too: drag the clip's left edge to the left to bring it back. Set the number of bars in Settings (**Rollback when recording**). When punch in/out is on, the punch range is used instead.

**Recording in time** Type the BPM into TEMPO and turn on the metronome before recording to play along with a click (chapter 12).

**Recording files** Recordings are saved as WAV files in the Recordings folder. The file is named after the track and a take number, such as Bass\_001.wav.

## 5. Playback and basic controls

| To...                 | Do this                                                                                                  |
|-----------------------|----------------------------------------------------------------------------------------------------------|
| Play / stop           |  or the Play button     |
| Go back to the start  |  or the Rewind button   |
| Jump to a position    | Click the ruler (also while playing)                                                                     |
| Hear only some tracks |  (solo) on those tracks |
| Silence some tracks   |  (mute) on those tracks |

When the playhead reaches the right edge during playback, the view scrolls on automatically (turn this on or off with the Auto-scroll button in the transport bar). When stopped, drag the knob (●) of the scroll bar below the lanes to move around freely (clicking elsewhere on the bar does nothing).

## 6. Editing clips

One recording is called a **clip**. Editing never changes the original recording file (non-destructive editing), so feel free to experiment.




Figure 6-1 Clip handles

|   |                                                                                                                                                                                                                                    |
|---|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1 | <b>Left / right edges (trim):</b> move the pointer onto the clip's left or right edge line and it turns into an arrow (pointing right → at the left edge, left ← at the right edge); drag to shorten or lengthen the audible part. |
| 2 | <b>Fade in:</b> drag the white dot at the top left to the right so the sound starts gradually. Over the dot, the pointer turns into a pointing hand.                                                                               |
| 3 | <b>Fade out:</b> drag the white dot at the top right to the left so the sound ends gradually (the pointer turns into a pointing hand, as for the fade in).                                                                         |
| 4 | <b>Gain:</b> drag the short bar at the top centre up or down to change the clip volume ( $-\infty$ to +36 dB; below -72 dB it becomes $-\infty$ , silence). Over the bar, the pointer turns into an up-down arrow.                 |
| 5 | <b>Body:</b> click to select (thick white frame), drag to move — also onto another track.                                                                                                                                          |
| 6 | <b>Fade curve:</b> the white diamond in the middle of each fade line (the pointer turns into a pointing hand over it). Drag it up or down to change the fade's shape (see “Shaping a fade” below).                                 |
| 7 | <b>Value readout:</b> while you hold handle 2, 3, 4 or 6, a small box shows the fade length, the clip volume (dB) or the curve shape.                                                                                              |

Waveforms are drawn at the level you will actually hear: they shrink along the fade curves, and raising or lowering the gain makes them taller or shorter.

### Shaping a fade

Drag the diamond in the middle of a fade line (figure 6-1, item 6) up or down to bend the fade. The readout shows the level at the exact middle of the fade.

| Diamond position                         | Fade shape                                                                                           |
|------------------------------------------|------------------------------------------------------------------------------------------------------|
| Moved up                                 | Bowed up: a fade-in rises quickly; a fade-out holds its level and drops late.                        |
| Middle at -3.0 dB ( <b>Equal Power</b> ) | Keeps the perceived level steady — the best shape for crossfades. The diamond snaps here when close. |
| Middle at -6.0 dB ( <b>Linear</b> )      | A straight line. The diamond snaps here when close.                                                  |
| Moved down                               | Sagging: a fade-in rises slowly; a fade-out drops early.                                             |

**Double-click** the diamond to return to **Auto**: linear for a fade against silence, equal power for a crossfade over another clip. If a fade is too short to show its diamond, zoom in horizontally.

### Selecting clips




Figure 6-2 Marquee (1), the clips it selected (2), and a range selection (3)

| To...                              | Do this                                                                                                                                                                                  |
|------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Select one clip                    | Click it                                                                                                                                                                                 |
| Add to / remove from the selection |  -click or  -click |
| Select several at once (marquee)   | Drag from an empty spot to draw a frame (figure 6-2, item 1). Every clip the frame touches is selected (item 2), across tracks too.                                                      |
| Add with a marquee                 |  -drag                                                                                                |
| Select everything                  |                                                                                                       |
| Clear the selection                | Click an empty spot, or press                                                                         |

Dragging any selected clip moves all selected clips together as one block (also up or down to other tracks). If you release where any of them would have no track to land on (for example below the last track), they stay on their tracks and move in time only.

## Selecting a time range

Instead of whole clips, you can select “from this second to that second”. Use it to remove or keep just part of a clip.

- 1 Hold **⌘** and drag from where the range should start to where it should end. You can start on a clip or on an empty spot.
- 2 The range is shown as a white band (figure 6-2, item 3). Drag up or down to extend it over several tracks.
- 3 Then use one of these:

| Action                                                | Result                                                                                    |
|-------------------------------------------------------|-------------------------------------------------------------------------------------------|
| <b>Delete</b> (or right-click → <b>Delete Range</b> ) | Removes the audio inside the range (leaving silence). Clips are split at the range edges. |
| Right-click → <b>Crop to Range</b>                    | Keeps only the audio inside the range and removes what is before and after it.            |
| Right-click → <b>Split at Range Edges</b>             | Splits clips at both ends of the range.                                                   |
| <b>⌘C</b> / <b>⌘X</b>                                 | Copies / cuts only the audio inside the range.                                            |

## Cut, copy, paste and duplicate

- **⌘X** (cut), **⌘C** (copy): take the selected clips (or, with a range selected, the audio in the range).
- **⌘V** (paste): pastes at the **playhead**. Material copied from several tracks keeps its layout, with its top track landing on the **selected track**.
- **⌘-drag** a clip: leaves a copy in place while you move it (applies to every selected clip).
- Cut / Copy / Paste at Playhead are also in the right-click menu.

**While typing a name** When you are typing in a text field (such as a track name), **⌘X**, **⌘C**, **⌘V** and **⌘A** edit the text instead.

## Right-click menu

Right-clicking a clip that is not selected selects it. Right-clicking a selected clip keeps the selection, and the menu commands apply to **all selected clips** (with several, the items show the count, such as “(3)”).

Right-clicking inside a selected range keeps the range and shows the range menu.

- **File name:** the top of the menu shows the name of the clip's audio file, followed by its channels, bit depth and size (for example *Bass\_001.wav*, mono 24bit 7.8MB). Choose it to show the file in the Finder (with several clips selected it shows the count, such as “3 Clips”). New recordings are named “*track name\_number.wav*”, the number going up by one with each take.
- **Cut / Copy / Paste at Playhead:** cut, copy, and paste at the playhead.
- **Delete Range / Crop to Range / Split at Range Edges:** shown only while a range is selected.

- **Normalize:** sets the clip's gain so its loudest sample reaches 0 dBFS (the 24-bit maximum). The whole recording is measured, including parts hidden by trimming. The audio file is not changed (the gain limit is +36 dB).
- **Reverse:** plays the clip backwards. A reversed WAV file (such as Reverse\_Bass\_001.wav) is written to Recordings and the clip switches to it. Fade lengths and shapes swap ends as well.
- **Strip Silence...:** removes the parts where the audio stays at or below the silence level for at least the given number of seconds. Useful for clearing the unrecorded parts of stems exported from another DAW. In the dialog, set the silence level (dB, -72 dB at first), the minimum silence length (seconds) and the fade in/out (ms, 10 ms at first). Any single sample above the silence level counts as sound, so for stems with dither or faint noise, set the level above it. To remove only digital zero, use -144 dB. The clips are split around the silent parts, the silent pieces are deleted, and the new clip edges get fades. The fades sit outside the sound (in the silence), so the starts and ends of the sound are not cut into. A fade longer than half the minimum silence length is shortened to half of it. The audio files are not changed.
- **Choose Recording File...:** picks the file again if it cannot be found. Available when a single clip is selected.
- **Mute / Unmute Recording:** silences the clips. If any of them is not muted the item mutes them all; when all are muted it unmutes them.
- **Duplicate Recording:** copies the selected clips as one block whose start lands on the playhead (spacing and tracks kept). The copies become the selection.
- **Split at Cursor:** splits the clips the playhead is inside in two. Unavailable when the playhead is inside none of them.
- **Delete Recording:** deletes it.

## Snap

With Snap on (figure 3-2, item 12), clip moves, trims, range selections, moving the playhead by clicking the ruler, and moving the song start / end flags snap to whole beats. Turn it off for fine positioning.

## Undo and redo

Moves, trims, fade lengths and shapes, gain, delete, split, duplicate, range edits, cut and paste, normalize, reverse, recordings and WAV imports can be undone with **⌘Z** and redone with **⇧⌘Z** (while stopped).

Undoing a recording or an import removes the clip; the file stays in the Recordings folder.

## 7. Punch-in recording and layered takes

Use this when a take is almost perfect except for a few bars: re-record only that part.




Figure 7-1 Punch range and the re-recorded part on top

- 1 Drag the red handles of the **punch range** on the ruler (figure 7-1, item 1) to the part you want to redo (they move in beats).
- 2 Click **P** in the transport bar to enable punch in/out (the range turns red).
- 3 Turn on **R** on the track to redo.
- 4 Click Record a little before the range and perform. Only what falls inside the range is used, and only that part is shown while you record.
- 5 When you stop, the new part appears as a new clip (item 2) on top of the original clip.

### How overlapping clips play

- Where clips overlap, **only the clip recorded later (the upper clip) plays**. The hidden part of the original clip is shown darker, with a flat (silent) waveform.
- The joins automatically get a **crossfade** (item 3), so there are no gaps or clicks. The default is 10 ms with an equal-power shape. Across the crossfade the upper clip's waveform grows while the lower clip's shrinks.
- Moving the fade handles of the upper clip (item 4) changes the crossfade length, and the diamond in the middle of the fade line changes its shape (chapter 6). The lower clip automatically gets the same shape mirrored. The lower clip's fade on the overlapped side cannot be edited.
- If you move or delete the upper clip, the lower clip automatically plays normally again.
- You can punch in as many times as you like over the same place. The last take is always on top, and every join gets its own crossfade.

**Fine-tuning the range** The whole pass is saved, including audio outside the range. Drag the edges of the upper clip to extend the re-recorded part.

**This rule applies to every overlap** Not only punch takes: whenever clips overlap after moving or duplicating, the clip on the higher layer wins.

### Clip layers (which clip is on top)

- The layer order is **the order in which clips were added to the track**: the later a clip was recorded, the higher it is.
- Dragging a clip within the same track does **not** change its layer. For example, you cannot bring the first punch take above the second by moving it.
- Clips made with **Duplicate Recording** or paste (V), and clips moved to another track, are placed on **top** of that track.
- With -drag, the copy left behind sits directly below the clip you moved.

## 8. Recording through effects (input monitoring)

Use this, for example, to hear your guitar through an amp simulator while recording.

- 1 Insert the effect you want (e.g. an amp simulator) on the track (chapter 10).
- 2 Turn on **R** and **I** on the track. When I is filled green you hear the input through the effects (also while stopped).
- 3 Record with the Record button as usual.

**Turning I on while playing** Input monitoring cannot be rewired during playback. If you turn I on while playing, you start hearing the input after you stop, once reverb and other tails have faded (usually 1–2 s, at most 8 s). If you turn I off while playing, the input stays audible until you stop. Switching I while stopped takes effect at once.

**The dry signal is recorded** The file contains the sound before the effects, so you can change the amp settings later.

**If you hear a delay** Set **Buffer size** to 128 or 256. If your audio interface's direct monitoring is on, you will hear the dry and processed sound doubled — turn direct monitoring down for that input.

**Feedback** With a microphone and speakers you may get feedback (a loud squeal). Use headphones.

## 9. Using the mixer

The mixer at the bottom sets each track's level, left-right position (pan) and effects. Tracks come first (in the same order as the track headers), then FX channels, with MASTER (the overall output) at the right.




Figure 9-1 One mixer channel (strip)

|    |                                                                                                                                                                                                            |
|----|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1  | <b>INSERT (plug-in list):</b> green dot turns a plug-in on/off, click the name to open its window, drag to reorder (drag to another channel to copy), X removes it.                                        |
| 2  | <b>+</b> : adds a plug-in.                                                                                                                                                                                 |
| 3  | <b>Section divider:</b> drag up or down to change the height of the INSERT, SEND and control sections (all channels together).                                                                             |
| 4  | <b>SEND:</b> how much goes to an FX channel. Drag sideways, or double-click the value to type it.                                                                                                          |
| 5  | <b>Pan:</b> drag sideways to place the sound left or right. <C> is centre, L56 left, R75 right.                                                                                                            |
| 6  | <b>M / S:</b> mute and solo. FX channels have them too.                                                                                                                                                    |
| 7  | <b>Level value:</b> current fader value in dB. Double-click to type (e.g. -6, -inf).                                                                                                                       |
| 8  | <b>Fader:</b> drag up or down to change the level. 0 dB is the reference; you can go up to +6 dB.                                                                                                          |
| 9  | <b>Meters (L / R):</b> level of each side. Green → yellow (from -12 dB) → red (from -6 dB). The white line shows the recent peak.                                                                          |
| 10 | <b>Name:</b> click to select the track (clicking anywhere on the channel outside its controls does too). Double-click an FX channel's name to rename it. The current track's name is shown black on white. |

### Operating several channels together

Other tracks' channels can be operated together with the current track.

- 1 Click the channel to work from in the mixer, making it the current track.

2



- or  -click the channels to operate with it. Add as many as you like; click one again to take it out.

- The channels operated together get a lighter background. Only the current track's name is shown black on white.
- Moving the fader or a send of any of them moves the others by the same number of dB; pan moves them by the same amount. A fader or send at  $-\infty$  follows only when the one you move also starts at  $-\infty$ .
- Pressing **M** / **S** on any of them sets the others to the same state.
- Inserts (plug-ins) change only on the channel you click.
- A plain click on a channel, or making another track current (in the track headers, for example), ends the grouping. The track headers and waveforms do not show it.

A vertical line in the folder's colour stands left of each folder's tracks, and one in the FX colour left of the first FX channel. Click a line to open the colour palette: it changes the folder's colour (the folder in the track headers follows), or the colour of every FX channel.

## Handy actions

-  -click: resets faders and sends to 0 dB and pan to centre.
-  -drag: fine adjustment.
- Drag the mixer's top edge: changes the height of the whole mixer.
- ▼ on the mixer's bar: folds the mixer down to its bar; ▲ brings it back.
- Right-click a track header → **Show in Mixer**: scrolls that track's channel to the left edge (unfolding the mixer if needed).
- Right-click in the mixer: **Add FX** adds an FX channel.
- Right-click an FX channel strip: **Remove (channel name)** removes that FX channel.

**Level tip** Adjust the track faders so the MASTER meter does not reach red. If the mix is too loud, lower the tracks rather than MASTER.

## 10. Effects (plug-ins) and FX channels

### Inserting an effect

- 1 Stop playback (plug-ins cannot be inserted while playing).
- 2 Click  in the channel's INSERT section and choose a plug-in.
- 3 Click the plug-in's name to open its window.

Sound passes through the plug-ins from top to bottom. Drag the names to change the order. Plug-ins on MASTER's **POST** section affect the whole song (a limiter, for example).

Dragging a plug-in name to the INSERT list of **another channel** inserts a copy with the same settings (the original stays where it is). Drop it on a plug-in name to place it before that plug-in, or on an empty part of the list to add it at the bottom. This is handy for using the same effect settings on several tracks.

The effects that come with MyDAW ("MyDAW: ..." in the list) are described in chapter 11.

**Supported formats** Audio Unit (AU) and VST3 effects. If a product is installed in both formats, only the AU version is listed (using both at once is unstable). Instruments are not supported.

**When a plug-in name is shown in red** That plug-in cannot be used. Hold the pointer over the name to see why. "This plug-in cannot be used" means the plug-in is on this Mac but cannot run in MyDAW (such as a mono-only "(m)" version; use the stereo "(s)" version). "This plug-in was not found" means it is not installed on this Mac (for example, a project made on another Mac). A red plug-in does not affect the sound, and you can remove it with X.

### FX channels (sharing a reverb)

Spatial effects such as reverb are usually placed once on an FX channel; each track then decides how much it sends (SEND).

- 1 Click **Add FX** at the top of the mixer (or right-click → Add FX).
- 2 Insert a reverb on the FX channel and set its Mix (dry/wet) to 100% wet.
- 3 Raise the SEND to that FX on each track.

A send carries the track's sound after its effects, fader and pan, so lowering a track's fader also lowers its reverb.

A new FX channel is named "FX 1", "FX 2", ... with the number after the highest one in use, and takes the colour of the other FX channels (change it by clicking the line left of the FX channels; chapter 9).

### Muting and soloing an FX channel

- **M (mute)**: silences the FX channel's output. A reverb tail stops at once.
- **S (solo)**: as with tracks, only soloed channels are heard.

- Soloing a track also keeps the FX channels it sends to, so you hear its reverb.
- Soloing an FX channel plays only that FX channel (the effect sound). The dry sound of the tracks sending to it is not heard, which is handy for checking the reverb on its own.

## Removing an FX channel

- 1 In the mixer, right-click the strip of the FX channel you want to remove.
- 2 Choose **Remove (channel name)**, for example "Remove Reverb".
- 3 When asked "Delete "FX 1"?" (with the channel's name), click **Delete** (or **Cancel** to keep it).

The plug-ins on that FX channel and every track's send to it are removed as well.

**This cannot be undone** Z does not bring back a removed FX channel. Save the project first if you may need it again.

## Automatic delay compensation

Some plug-ins need time to process audio (latency). MyDAW reads the latency they report and adjusts playback timing automatically.

- Latency is compensated for plug-ins on tracks and on FX channels alike, so a reverb on an FX channel stays in time with the dry sound.
- Turning a plug-in off (bypass) does not change the compensation, so switching it during playback never interrupts the sound.
- If a plug-in's latency changes with its settings, the compensation follows.
- The sound right at the start position is heard too. With high-latency plug-ins, playback takes that much longer to get going after you press Play (for example 40 ms).
- A high-latency plug-in on an FX channel also delays input monitoring on armed tracks by that amount (the recording itself is not affected).

## 11. MyDAW's built-in effects

MyDAW comes with four effects ready to use. They appear in the insert  list as "**MyDAW: ...**" (see chapter 10 for inserting effects).

| Effect                | What it does                                           | Where to insert it                         |
|-----------------------|--------------------------------------------------------|--------------------------------------------|
| <b>MyReverb</b>       | Plate reverb: adds space and ambience                  | On an FX channel, fed from tracks by sends |
| <b>MyDelay</b>        | Delay: adds echoes                                     | On an FX channel, fed by sends             |
| <b>MyChannelStrip</b> | 4-band EQ and compressor to shape each sound           | First insert of each track                 |
| <b>MyMaximizer</b>    | Maximizer: makes the whole mix louder without clipping | Last post insert on MASTER                 |

### Common layout and controls

Every effect shows, from the top:

- The **effect name**, with a mode display or switch on the right.
- The **channel name**: the track, FX channel or MASTER the effect is on. It follows when you rename the track.
- **IN / OUT meters**: the level going into and out of the effect. The number on the right is the highest peak so far; click it to clear it.
- **Faders and knobs**, each with its name and current value above it.

| Action                                                                                        | Result                                                                                                                                                                                                       |
|-----------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Drag a fader or knob                                                                          | Changes the value (a click alone does not make it jump). Drag knobs up and down.                                                                                                                             |
| Drag with  | Fine adjustment.                                                                                                                                                                                             |
|  -click    | Back to the default value.                                                                                                                                                                                   |
| Double-click the value                                                                        | Type a value (  to apply,  to cancel). |

Every control can be recorded as automation, and the settings are saved with the project.

MyReverb (reverb)




Figure 11-1 MyReverb

A bright, dense reverb modelled on a metal plate. It gives vocals and snares a natural sense of space.

| Fader | Range (default)        | What it does                                                                                                                   |
|-------|------------------------|--------------------------------------------------------------------------------------------------------------------------------|
| HPF   | Thru to 1 kHz (80 Hz)  | Cuts lows from the reverb. Raise it to keep the low end clean and the mix clear. The bottom is Thru (no cut).                  |
| LPF   | 200 Hz to Thru (8 kHz) | Cuts highs from the reverb. Lower it for a darker, softer sound. The top is Thru (no cut).                                     |
| RT    | 0.1 to 60 s (2.00 s)   | Reverb time: how long the tail takes to fall by 60 dB. About 0.5 to 1 s for a small room, 2 to 3 s for a hall.                 |
| PD    | 0 to 1 s (20 ms)       | Pre-delay: the gap between the sound and the start of the reverb. 20 to 40 ms keeps the sound from being buried in the reverb. |
| MIX   | 0 to 100 % (100 %)     | Amount of reverb. Leave it at 100 % on an FX channel.                                                                          |

- 1
- Add an FX channel and insert MyReverb on it (MIX at 100 %).
- 2
- Raise the send of each track you want to add reverb to. The send sets how much reverb that track gets.
- 3
- Set the length with RT and the start with PD. If the low end gets muddy, raise HPF.

**Inserting it on a track** Lower MIX to about 15 to 30 %. At 100 % you hear only the reverb, not the original sound.

MyDelay (delay)



Figure 11-2 MyDelay

Repeats the sound after a delay (echo). Choose one of four modes from the menu at the top right; the faders shown depend on the mode.

| Mode         | Sound                                                                                     | Faders                     |
|--------------|-------------------------------------------------------------------------------------------|----------------------------|
| Mono Delay   | The same echoes on both sides                                                             | TIME, FEEDBACK, MIX        |
| Stereo Delay | Left and right each get their own echoes (default)                                        | TIME, FEEDBACK, WIDTH, MIX |
| Doubler      | Delays the left by TIME and the right by 1.5 × TIME, once, to thicken and widen the sound | TIME, WIDTH, MIX           |
| Ping-Pong    | Echoes bounce between left and right                                                      | TIME, FEEDBACK, WIDTH, MIX |

| Fader    | Range (default)          | What it does                                                             |
|----------|--------------------------|--------------------------------------------------------------------------|
| TIME     | 1 ms to 10 s<br>(250 ms) | Time between echoes.                                                     |
| FEEDBACK | 0 to 100 %<br>(30 %)     | How long the echoes go on. Even at 100 % they never keep getting louder. |
| WIDTH    | 0 to 100 %<br>(100 %)    | Stereo spread of the echoes; 0 % puts them in the centre.                |
| MIX      | 0 to 100 %<br>(100 %)    | Amount of echo. Leave it at 100 % on an FX channel.                      |

**Matching the tempo** A quarter note lasts  $60000 \div \text{tempo (BPM)}$  ms. At 120 BPM: quarter note 500 ms, eighth note 250 ms, dotted eighth 375 ms.

Changing TIME or the mode during playback causes no clicks or pitch wobble.

## MyChannelStrip (EQ and compressor)



Figure 11-3 MyChannelStrip

A 4-band EQ to shape the tone and a compressor to even out the level, in one effect. Insert it first on each track. When inserted, the EQ is flat (all bands at 0 dB) and the compressor is off, so the sound does not change. Parts that leave the sound unchanged are not computed, so it costs little even on many tracks.

| Part                                         | What it does                                                                                                                                         |
|----------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>EQ ► COMP</b> (top right)                 | Processing order. Click to switch to <b>COMP ► EQ</b> ; the EQ and compressor sections swap places on screen too (top to bottom is the signal flow). |
| <b>EQ</b> and <b>COMP</b> buttons            | Turn each section on or off. A section that is off passes the sound through.                                                                         |
| <b>GAIN</b> (horizontal fader at the bottom) | Final level, -24 to +24 dB. Double-click or  -click for 0 dB.    |

**EQ (4 bands):** the line shows the current frequency response (lows on the left, highs on the right), over a display of the sound's frequency content after the EQ. The four numbered circles (nodes) are the bands.

| On the EQ graph                                                                                                            | Result                                                                                              |
|----------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------|
| Click a node                                                                                                               | Selects that band (the row below switches to it).                                                   |
| Drag a node left or right                                                                                                  | Frequency (FREQ)                                                                                    |
| Drag a node up or down                                                                                                     | Boost or cut (GAIN); it snaps to 0 dB near 0. For Low Cut and High Cut: Q (the bump at the corner). |
| Scroll over a node, or  -drag up and down | Q (width; higher is narrower)                                                                       |
| Drag with                                 | Fine adjustment.                                                                                    |
| Double-click a node                                                                                                        | Turns that band on or off.                                                                          |
|  -click a node                            | Resets that band's GAIN to 0 dB.                                                                    |

The row under the graph shows the selected band: from the left, band on/off, the band number (click for the next band), the **GAIN** (−18 to +18 dB), **FREQ** (20 Hz to 20 kHz) and **Q** (0.1 to 10) knobs, and five type buttons (Low Cut, Low Shelf, Bell, High Shelf, High Cut). For Low Cut and High Cut, **SLOPE** (12 or 24 dB/oct, how steep the cut is) replaces GAIN.

**EQ basics** For a vocal, first set band 1 to Low Cut to remove rumble below 80 to 100 Hz. Cut a little where it sounds boxy (200 to 500 Hz), and add a little at 3 to 5 kHz for presence. Cutting usually sounds more natural than boosting.

**Compressor:** holds down loud passages to even out the level. The graph on the left shows input level (across) against output level (up); the vertical meter on its right shows how much the level is being reduced (gain reduction). The ○ moving along the line is the current level; it turns orange while it is being compressed.

| Knob or button     | Range (default)          | What it does                                                            |
|--------------------|--------------------------|-------------------------------------------------------------------------|
| <b>THR</b>         | –60 to 0 dB<br>(–10 dB)  | Threshold: sound above it is compressed.                                |
| <b>RATIO</b>       | 1:1 to 20:1<br>(2.0:1)   | How hard: at 4:1, what goes over the threshold is reduced to a quarter. |
| <b>KNEE</b>        | 0 to 24 dB<br>(6 dB)     | How gently compression starts; wider is more natural.                   |
| <b>ATK</b>         | 0.1 to 200 ms<br>(15 ms) | Attack: how quickly it reacts when the sound gets louder.               |
| <b>REL</b>         | 5 to 2000 ms<br>(120 ms) | Release: how quickly it recovers when the sound gets quieter.           |
| <b>MAKE</b>        | 0 to +24 dB<br>(0 dB)    | Makeup gain: brings the compressed sound back up.                       |
| <b>AUTO GAIN</b>   | On / off (off)           | Adds makeup gain automatically from THR and RATIO.                      |
| <b>STEREO LINK</b> | On / off (on)            | Compresses left and right equally, so the stereo image stays put.       |
| <b>MIX</b>         | 0 to 100 %<br>(100 %)    | Blend of compressed and original sound (parallel compression).          |

| On the compressor graph                                                                               | Result                          |
|-------------------------------------------------------------------------------------------------------|---------------------------------|
| Drag left or right                                                                                    | THR                             |
| Drag up or down, or drag the ●                                                                        | RATIO (the ● follows the mouse) |
|  -drag up and down | KNEE                            |
| Double-click                                                                                          | Resets THR, RATIO and KNEE.     |

**Compressor basics** Turn COMP on and lower THR until the vertical meter moves 3 to 6 dB on the loudest parts of the vocal. Make up the lost level with MAKE (or AUTO GAIN).

# MyMaximizer (maximizer)




Figure 11-4 MyMaximizer

Makes the whole mix louder while keeping it under a level you set (OUTPUT). Insert it last in the MASTER post inserts.

| Fader   | Range (default)          | What it does                                                                                                                       |
|---------|--------------------------|------------------------------------------------------------------------------------------------------------------------------------|
| INPUT   | –12 to +24 dB<br>(0 dB)  | How hard the mix is driven into the limiter. Higher is louder (too high distorts and flattens the sound).                          |
| UPWARD  | 0 to +9 dB<br>(+2 dB)    | Upward compression: lifts quiet parts (below –6 dB) by up to this much, filling out quiet passages. 0 dB is off.                   |
| THRESH  | –30 to 0 dB<br>(–0.1 dB) | Where compression starts. Peaks above it are pressed softly (soft knee) toward OUTPUT.                                             |
| ATTACK  | 0 to 10 ms<br>(0 ms)     | How early the level comes down before a peak. 0 ms reacts right at the peak (loudest, but distorts most easily); longer is softer. |
| RELEASE | 10 to 500 ms<br>(50 ms)  | How quickly the level comes back. Shorter is louder but pumps and distorts more easily. UPWARD recovers 10 times more slowly.      |
| OUTPUT  | –12 to 0 dB<br>(–0.1 dB) | Ceiling: the output never goes above it. For streaming, use –0.1 to –1 dB.                                                         |

- 1
- When inserted, THRESH and OUTPUT are both –0.1 dB, so it works as a plain limiter (prevents clipping).

- 2 Raise **INPUT** to set the loudness. If the red in the graph (limiting) stays above a few dB, it is too high.
- 3 If the peaks sound hard or crunchy, lower **THRESH**. Everything above THRESH is then pressed gradually, levelling off just below OUTPUT. About -3 to -6 dB is a good start.
- 4 To bring up quiet passages, raise **UPWARD**.
- 5 Start **ATTACK** and **RELEASE** at their defaults (0 ms / 50 ms) and lengthen them only if you hear distortion or pumping.

How THRESH works (OUTPUT -0.1 dB, THRESH -6 dB):

| Peak in  | -6 dB or lower | -3 dB   | 0 dB    | +6 dB   | +12 dB  |
|----------|----------------|---------|---------|---------|---------|
| Peak out | unchanged      | -3.7 dB | -2.2 dB | -0.9 dB | -0.4 dB |

**Graph:** scrolls from right to left and shows the last 6 seconds (click for 3, 6 or 12 seconds). Teal is the output level, red hanging from the top is how much the limiter is reducing the level, and green rising from the bottom is how much UPWARD is lifting it. The white dotted line marks OUTPUT, the red dotted line THRESH (when below OUTPUT). **GR** and **UP** below show the limiting and the upward lift in dB (the largest value is held for 1 second).

**CLIP lamps:** the squares to the right of the IN and OUT meters light red when the signal reaches 0 dB and stay lit until clicked. OUT's CLIP lamp normally never lights.

**Processing delay** MyMaximizer looks 10 ms ahead at the peaks, so its output is 10 ms late. MyDAW compensates for this automatically, so it stays in time with everything else (chapter 10, "Automatic delay compensation"). "LIMITER 10 ms" at the top right shows this delay.

## 12. Tempo, click and ruler

- **Tempo (BPM):** type a number into TEMPO (20–400, default 120).
- **Metronome:** turn it on to hear a click while playing or recording; the first beat of a bar is higher. Turned on during playback or recording, it starts clicking from the next beat.
- **Ruler:** button 16 in figure 3-2 switches between time and bars/beats.
- **Click timing and volume:** **Click timing** (ms) and **Click volume** in the settings.

### Song start and end flags

You can place blue song start and end flags on the ruler (the start flag points right, the end flag left). Both are optional.

- **Place:** right-click the ruler and choose **Set Song Start Here** or **Set Song End Here**. The start must be at least one beat before the end.
- **Move:** drag the flag's pennant; the playhead does not move while you hold a flag. Clicking the pole or around it moves the playhead as anywhere else on the ruler. With snap on, the flag moves in beats. While you hold it, its position is shown next to it, in the ruler's units: bar:beat:tick (480 ticks per beat) or h:m:s.ms.
- **Overlapping the punch handles:** the punch handle moves. To move the flag instead, hold  while dragging.
- **Remove:** right-click the ruler and choose **Remove Song Start** or **Remove Song End**.

With flags in place:

- **Rewind** () goes to the start flag. If you are already on it or before it, it goes to 00:00.000.
- **Stop at the end flag:** playback and recording stop when they reach the end flag, and recorded clips are cut at it. Playback started after the end flag does not stop.
- **Export:** the Export Master Mix dialog starts with the flags' positions (chapter 15).

Flags are stored in beats, so they move with a tempo change.

## 13. Adjusting the view

| Adjustment           | How                                                                                                                                                                                                                                                                                                                                      |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Horizontal zoom      | Magnifier buttons, the timeline slider (5–3200 pixels per second), the <b>mouse wheel over the ruler</b> , or a <b>trackpad pinch</b>                                                                                                                                                                                                    |
| Height of all tracks | Track height slider (about 0.3–3×), or  + mouse wheel over the tracks. The slider scales around the current track, the wheel around the mouse pointer. Using it returns tracks resized one by one to the standard height, so all tracks scale together. |
| Height of one track  | Drag the bottom edge of its header                                                                                                                                                                                                                                                                                                       |
| Waveform height      | Waveform slider (1–256×), or   + mouse wheel over the tracks. Does not change the sound.                                                                               |
| Mixer height         | Drag the mixer's top edge                                                                                                                                                                                                                                                                                                                |

Zooming with the wheel or a pinch keeps the position under the pointer in place.

Zoomed in far, the waveform shows the individual waves (cycles) of the sound.

The timeline is as long as the song: the end of the last clip (or the song end flag) plus 5 seconds, at least 60 seconds. The part after it is shown darker; the ruler goes on to the right edge of the screen, but clicking there or playing on does not make the song longer. Recording past the end makes the song longer.

## 14. Saving, opening and moving projects

### What a project contains

```
MySong/          ← the folder chosen in the save panel (any name)
├── Ballad.mydaw  ← tracks, clip positions, mixer, plug-in settings, ...
└── Recordings/  ← your recorded WAV files
    └── *.wav
```

The .mydaw file and its folder do not need the same name. Recordings are saved in the Recordings folder next to the .mydaw file. You can rename the .mydaw file in the Finder.

- **Save:** , **File** → **Save Project...** or the Save button. “Project saved.” appears when it is done.
- **Save As:**  or **File** → **Save Project As....** Type a new name and click **Save**: the project is saved as another .mydaw file in the **same folder**, and you go on working in that file. The original file is left as it was. The recordings are not copied, because both use the same Recordings folder. Saving to a different folder is not possible.
- **Open:**  or the Open button, then choose the project's .mydaw file. You can also click a project name in the **Recent Projects** list on the start screen, or double-click a .mydaw file in the Finder (MyDAW starts if it is not running). If another project is open, you are asked whether to save it first.
- **New:** , then choose the folder and name in the save panel (see [chapter 2](#)).

**Several projects in one folder** You can keep more than one .mydaw file in the same folder. They then all use the same Recordings folder. New recording files get the next free number, so nothing is overwritten.

### Recent Projects

- Below the buttons on the start screen, up to 50 projects you have opened or saved are listed, newest first: the project name (without .mydaw) on the left and when it was last saved on the right.
- Hover over a project name to see where the file is. Click it to open the project.
- A project that has been moved or deleted is shown greyed out and struck through, and cannot be opened. Put it back where it was and it can be opened again.
- To take an entry off the list, right-click it and choose **Remove from List** (the project files are not deleted).

Saved with the project: track settings (name, colour, volume, pan, mute, solo, input, R/I), clip positions and edits, mixer and FX, plug-ins and their settings, tempo, metronome, punch range, song start and end flags, and view settings.

**Moving to another Mac** Copy (or zip) the **whole project folder**, not just the .mydaw file. Install the plug-ins you use on the other Mac too. Renaming or moving the Recordings folder makes clips impossible to load.

**Quitting** Whether you choose **MyDAW** → **Quit MyDAW** (⌘Q) or close the window, you are asked whether to save (Save / Don't Save / Cancel). Cancel keeps MyDAW open.

## Shrinking recordings for sharing

Before you give a project to someone else, you can rebuild the files in the Recordings folder so that they hold only what the clips play.

- 1 Stop playback and recording.
- 2 Choose **File** → **Optimize Recordings to Minimum Size**.
- 3 When asked to confirm, click **Optimize** (or **Cancel** to stop). The project is saved automatically.
- 4 When it finishes, the number of files created and the total size before and after are shown. Click **OK**.
  - Each clip gets its own recording file (named `Optimized_001.wav` and so on) without the parts hidden by trimming. Clips that play the same part of the same file share one file.
  - Clips on a mono track get mono files. On a stereo track, a file that was mono stays mono.
  - Files at a higher sample rate than the current setting are converted to it (a lower rate is never raised). 32-bit and floating-point files become 24-bit; 16-bit and 24-bit files keep their bit depth.
  - Original files that are no longer used go to Recordings/Unused. Leave the Unused folder out when you share the project.
  - This cannot be undone. The Undo history and copied clips are cleared.
  - When other `.mydaw` files are in the same folder, nothing is done, so their recordings are not broken.

## Tidying up unused recordings

Repeated punch-ins and deleted takes leave WAV files in the Recordings folder that nothing uses any more. To move them all out of the way:

- 1 Stop playback and recording.
- 2 Choose **File** → **Move Unused Recordings to Unused Folder**.
- 3 When asked that the project needs to be saved, click **Save Project and Continue** (or **Cancel** to stop).
- 4 A list of the moved files appears. Click **OK**.
  - They go to Recordings/Unused. Nothing is deleted, so you can move a file back in the Finder. To free the space, delete the Unused folder in the Finder.
  - Files of deleted clips are moved too. If Undo (⌘Z) could have brought such a clip back, the Undo history is cleared, so Undo never restores a clip whose file has gone.
  - Files that a copied clip uses are kept as in use.
  - When other `.mydaw` files are in the same folder, the files their projects use are kept too.
  - Only WAV files directly in the Recordings folder are checked.

**Why it saves first** The check uses the project as it is open now. Saving before moving means no file that the saved project uses is ever moved.

## 15. Importing WAV files and exporting

### Importing a WAV file

- 1 Select the WAV file in Finder.
- 2 Drag it onto a track lane. It is added as a clip at the playhead.

The file is copied into the project's Recordings folder as Import\_001.wav, Import\_002.wav and so on (the original is untouched). Files at a different sample rate, and 16-bit or 32-bit files, are **converted automatically to a 24-bit WAV at the current sample rate** as they are copied. Converting a long file may briefly pause the screen.

### Exporting the finished mix

- 1 Stop playback and recording.
- 2 Choose **File** → **Export Master Mix....** The export dialog opens.
- 3 Set the file name, folder and format (see the table below).
- 4 Check the start and end times (seconds). They default to the song start and end flags; without flags, to 0 and the end of the last clip.
- 5 Click **Export**. If a file with the same name exists, you are asked whether to replace it. Exporting takes as long as playing the song, followed by the conversion to the chosen format. The file runs exactly from the sound at the start to the sound at the end, to the sample (plug-in latency included).




Figure 15-1 Export Master Mix dialog (MP3 selected)

|   |                                                                                                                                                                                                                                     |
|---|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1 | <b>File name:</b> at first “ <i>project name_Master_Mix</i> ”. The extension (.wav / .mp3) follows the format.                                                                                                                      |
| 2 | <b>Folder:</b> at first the project folder. Click <b>Change...</b> to choose another folder.                                                                                                                                        |
| 3 | <b>Format</b> and <b>Sample rate:</b> WAV or MP3, at 44.1, 48 or 96 kHz. MP3 goes up to 48 kHz only, so 96 kHz cannot be chosen for it.                                                                                             |
| 4 | Settings for the format.<br><b>WAV:</b> bit depth 16 bit or 24 bit.<br><b>MP3:</b> mode “Constant” (bitrate 128 / 192 / 256 / 320 kbps) or “VBR” (quality High (V0) / Standard (V2) / Low (V4)). The default is Constant, 320 kbps. |
| 5 | <b>Start</b> and <b>End:</b> the range to export (seconds).                                                                                                                                                                         |
| 6 | Progress: “Exporting master mix...”, then “Converting...”, then “Export completed successfully.”                                                                                                                                    |
| 7 | <b>Cancel</b> stops the export (no partial file is left). <b>Export</b> starts it.                                                                                                                                                  |

**Your choices are kept** The file name, folder and format are saved with the project, and the dialog opens with them next time.

## 16. Settings (audio and language)

Open **Settings** with the gear button (not available while playing or recording). Click **Apply** after changing anything.

The screenshot shows a 'Settings' dialog box with a dark background. It is organized into sections: 'Environment', 'Audio', 'Compensation', and 'Other'. Each setting is preceded by a numbered orange circle. The 'Language' dropdown is set to 'English'. The 'Recordings folder' is a text field with '.../MySong/Recordings'. 'Input device' and 'Output device' are dropdowns set to 'Studio 24c'. 'Sample rate' is a dropdown set to '48 kHz'. 'Buffer size' is a dropdown set to '256 frames (5.3 ms)'. Below it, a note states 'Input and output devices use the same Core Audio buffer size.' In the 'Compensation' section, 'Recording latency (optional)' and 'Click timing' are text fields both set to '0.0 ms', with explanatory text below each. In the 'Other' section, 'Click volume' is a slider set to 70%, and 'Rollback when recording' is a text field set to '2 bars' with explanatory text below it. At the bottom right are 'Cancel' and 'Apply' buttons.

**Settings**

**Environment**

1 Language English ▾

**Audio**

2 Recordings folder .../MySong/Recordings

3 Input device Studio 24c ▾

4 Output device Studio 24c ▾

5 Sample rate 48 kHz ▾

6 Buffer size 256 frames (5.3 ms) ▾  
Input and output devices use the same Core Audio buffer size.

**Compensation**

7 Recording latency (optional) 0.0 ms  
Corrects the position of recorded clips. Positive values move them earlier.

8 Click timing 0.0 ms  
Corrects when the click sounds. Positive values make it sound later.

**Other**

9 Click volume 70%

10 Rollback when recording 2 bars  
In normal recording, the playhead rolls back by this many bars.  
Recording starts at the current playhead position.

Cancel Apply

Figure 16-1 Settings

| Environment  |                                                                                                                                                                                                        |
|--------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1            | <b>Language:</b> the screen language (English / 日本語). At first it follows the macOS language.                                                                                                          |
| Audio        |                                                                                                                                                                                                        |
| 2            | <b>Recordings folder:</b> where recordings are saved (normally the project's Recordings folder).                                                                                                       |
| 3            | <b>Input device:</b> the device you record from.                                                                                                                                                       |
| 4            | <b>Output device:</b> the device you listen through. It can be the same audio interface as the input or a different device (such as a monitor's speakers).                                             |
| 5            | <b>Sample rate:</b> 44.1, 48, 88.2 or 96 kHz. This changes the device's own setting (the one shown in macOS Audio MIDI Setup).                                                                         |
| 6            | <b>Buffer size:</b> smaller means less delay, larger means more stability. Use 128–256 for recording and input monitoring, 512–1024 for mixing. The input and output devices use the same buffer size. |
| Compensation |                                                                                                                                                                                                        |
| 7            | <b>Recording latency (optional):</b> corrects the position of recorded clips (ms). Positive values move them earlier. Normally leave at 0.                                                             |
| 8            | <b>Click timing:</b> corrects when the click sounds (–500 to +500 ms). Positive values make it sound later.                                                                                            |
| Other        |                                                                                                                                                                                                        |
| 9            | <b>Click volume:</b> loudness of the click.                                                                                                                                                            |
| 10           | <b>Rollback when recording:</b> how many bars (1–16) the playhead rolls back when rollback recording is on (chapter 4). Recording starts at the playhead position.                                     |

**Recording with a MacBook's built-in microphone and speakers** The built-in microphone and speakers do not tell MyDAW how long their sound processing takes, so recordings may land about 25 ms late (with an audio interface they hardly move). Correct this with **Recording latency (optional)**, set to around **25**.

1. Set the ruler to bars and beats, turn the metronome on, and record a few bars of the click from the built-in speakers with the built-in microphone.
2. Zoom in and see how far right of the beat lines the recorded clicks start.
3. Enter that offset (ms) in **Recording latency (optional)**, click **Apply**, and record again to check that the clicks line up.

When you go back to an audio interface, set the compensation back to 0.

**Changes that need a restart** When you change Language, Input device, Output device or Sample rate and click Apply, MyDAW asks to restart. Choose **Save and Restart**, **Restart Without Saving**, or **Cancel** (restart yourself later). After the restart the project that was open opens again. A Buffer size change alone takes effect without a restart.

**MyDAW also switches the macOS sound devices** While it runs, MyDAW makes your chosen input and output the macOS default input and output, and puts the previous ones back when it quits. So while MyDAW is running, other apps also play through the chosen output. If MyDAW crashes they are not restored — set them back in System Settings → Sound.

## 17. Keyboard shortcuts

| Key                                | Action                                                         |
|------------------------------------|----------------------------------------------------------------|
|                                    | Play / stop                                                    |
|                                    | Record (same as the red Record button; stops when running)     |
|                                    | Go to the song start flag (on or before it: to the beginning)  |
|                                    | Delete the selected clips (or the audio in the selected range) |
| X / C / V                          | Cut / copy / paste at the playhead                             |
| A                                  | Select all clips                                               |
|                                    | Clear the selection                                            |
| Z                                  | Undo                                                           |
| Z / Y                              | Redo                                                           |
| S                                  | Save                                                           |
| O                                  | Open                                                           |
| N                                  | New project                                                    |
| ?                                  | MyDAW Help (opens this manual as a PDF on the web)             |
| -click / -click (clip)             | Add to / remove from the selection                             |
| Drag (empty spot) / -drag          | Marquee select / add with a marquee                            |
| -drag (tracks)                     | Select a time range                                            |
| -drag (clip)                       | Duplicate while moving                                         |
| Double-click (fade diamond)        | Reset the fade shape to Auto                                   |
| Mouse wheel over the ruler / pinch | Horizontal zoom                                                |
| + mouse wheel                      | Track height                                                   |
| + mouse wheel                      | Waveform height                                                |
| -click (mixer)                     | Fader / send to 0 dB, pan to centre                            |
| -drag (mixer)                      | Fine adjustment                                                |
| Double-click (values, names)       | Type a value / rename                                          |

, and also work while you are using a plug-in window (except while typing a value).

## 18. Troubleshooting

| Problem                                                                     | What to check                                                                                                                                                                                         |
|-----------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Cannot record / meter does not move                                         | Microphone permission (System Settings → Privacy & Security → Microphone), Input device, the track's R button, the input channel.                                                                     |
| No sound                                                                    | Output device, MASTER and track faders, M (mute) / S (solo), speaker or headphone volume.                                                                                                             |
| Play does not record                                                        | Recording uses the red <b>Record</b> button; Play only plays.                                                                                                                                         |
| Recordings are out of time                                                  | Check the buffer size, record the same sound again to measure the offset, and correct it with Recording latency (optional).                                                                           |
| The sound breaks up / • Dropout appears in the status bar                   | Raise the buffer size in Settings (512–1024). Remove or bypass heavy plug-ins. The status bar's CPU meter shows whether the load went down.                                                           |
| Effectuated input sounds late                                               | Buffer size 128–256; turn down the interface's direct monitoring.                                                                                                                                     |
| A plug-in is missing from the list                                          | Make sure it is an effect (not an instrument). AU effects driven by MIDI are not listed either. Products with an AU version are listed as AU only.                                                    |
| Cannot add a plug-in                                                        | Stop playback first.                                                                                                                                                                                  |
| A plug-in name is red and its window does not open                          | Hold the pointer over the name to see why. If it "cannot be used", replace it with another plug-in such as the stereo version; if it "was not found", install the plug-in and open the project again. |
| Cannot import a WAV                                                         | Check that the file is an intact audio file such as WAV. Other sample rates and bit depths are converted automatically.                                                                               |
| No sound from the chosen output device                                      | After changing devices, restart MyDAW from the dialog. The new device is used only after the restart.                                                                                                 |
| Other apps also play through MyDAW's output                                 | While MyDAW runs, the chosen devices are the macOS defaults. They are put back when MyDAW quits.                                                                                                      |
| After a crash, the Mac still uses MyDAW's devices                           | Set output and input back in System Settings → Sound.                                                                                                                                                 |
| Playback and recording suddenly stop, and the input stays silent afterwards | This happens when the input or output is changed in System Settings → Sound while MyDAW is running. Restart MyDAW.                                                                                    |
| Another app's recording (such as a screen recording) is full of loud noise  | Launch MyDAW before you start recording, and quit it only after recording ends. MyDAW switches the macOS input and output when it launches and quits.                                                 |
| A clip says its file cannot be found                                        | Right-click → Choose Recording File... and pick the WAV again.                                                                                                                                        |

You want the screens in  
Japanese (or English)

Choose it under Language in Settings, click Apply and restart.

## 19. Glossary

| Term              | Meaning                                                                                                |
|-------------------|--------------------------------------------------------------------------------------------------------|
| DAW               | Digital Audio Workstation — software for recording, editing and mixing.                                |
| Track             | A lane that records and plays one instrument or part.                                                  |
| Clip              | One recorded piece of audio that you can move and edit.                                                |
| Record arm        | Making a track ready to record with its R button.                                                      |
| Punch in/out      | Re-recording only a chosen range.                                                                      |
| Crossfade         | Joining two sounds by fading one out while fading the other in.                                        |
| Fade curve        | The shape in which the level changes during a fade: linear, equal power, bowed up, sagging, and so on. |
| Equal power       | A fade shape that keeps the perceived level steady through a crossfade.                                |
| Range selection   | Selecting a stretch of time rather than whole clips.                                                   |
| Normalize         | Raising or lowering a level so the loudest sample reaches full scale (0 dBFS).                         |
| Fader             | The control that sets volume.                                                                          |
| Pan               | Where the sound appears between left and right.                                                        |
| dB (decibel)      | Unit of level. 0 dB is the reference; -6 dB is roughly half as loud.                                   |
| Mute / solo       | Silence a track / hear only that track.                                                                |
| Folder            | Holds several tracks so they can be moved, muted, soloed and folded together.                          |
| Current track     | The selected track. New tracks and pastes are placed from it.                                          |
| Plug-in (effect)  | Add-on software that processes sound; formats AU and VST3.                                             |
| INSERT            | Effects placed directly on a channel; sound passes through them top to bottom.                         |
| SEND / FX channel | Sending part of a track's sound to a shared effect (the FX channel).                                   |
| MASTER            | The final output where all tracks are combined.                                                        |
| Buffer size       | The block size audio is processed in. Smaller means less delay but more CPU load.                      |
| Sample rate       | How many times per second sound is measured (44.1 / 48 / 88.2 / 96 kHz).                               |
| Input monitoring  | Listening to the incoming sound through the track's effects.                                           |