

Kit Maker

Browse, build and sequence sample drumkits — random kits, full-control kits, and two built-in pattern sequencers.

by TK & Flurmechanik



BROWSER

Organise sample packs & kits, audition, send them onward.

EXPLOSION

Point at a folder, get a finished random kit.

BUILDER

Define pools & slots yourself, batch-export variations.

STEP

16-lane step sequencer driving the kit's RS5K rack.

EUCLID

Euclidean pattern generator per kit lane.

A typical flow runs left to right across the tabs: **Browser** to collect and audition your samples → **Explosion** or **Builder** to render kits into RS5K racks → **Step** or **Euclid** to program patterns on those racks. The **Kit Manager** button (top bar) opens a 4×4 rack window that ties it all together.

1 Install & requirements

Install through ReaPack — the easiest route, and it stays up to date.

- 1 In REAPER: **Extensions** → **ReaPack** → **Import repositories...** and paste the TK-Scripts repository URL: <https://raw.githubusercontent.com/TouristKiller/TK-Scripts/master/index.xml>
- 2 **Extensions** → **ReaPack** → **Browse packages...**, find **Kit Maker** (by TK & Flurmechanik) and click **Install**.
- 3 Run it from the **Actions** list (search for Kit Maker) — assign it a toolbar button or shortcut if you like.
- 4 Install the dependencies via ReaPack too: **RealmGui** (required — the window needs it to draw) and **SWS/CF** (recommended: folder pickers, audition, “open folder”).

Manual install

Prefer a manual install? Unzip so the TK Kit Maker folder (with core/, ui/, data/) stays intact under .../REAPER/Scripts/, then load TK_Kit_Maker.lua via **Actions** → **New action** → **Load ReaScript...**

Good to know

The sequencers install a small JSFX engine on the kit track automatically, so timing stays tight even when the window is busy. If the Step/Euclid page says the engine isn't running, check that the kit track's FX aren't bypassed.

Your library hub — collect folders, audition samples, send them onward.

The Browser keeps two kinds of collections side by side. Toggle the button top-left to switch between them:

- **Sample Packs** — raw folders of samples you browse and pull from (feeds Explosion & Builder).
- **Sample Kits** — finished kits; from here you can build a playable **RS5K Drum Rack** in REAPER.

LEFT PANEL

Managing collections

- **+ Folder** adds a collection; **Rescan** refreshes its file list.
- View them as a **List** or as cover **Tiles**. Drag the splitter to resize; the **Catalog / Split / Samples** buttons pick which panel gets the focus on a narrow window.
- Right-click a collection for the full menu: **Rename**, **Pin**, **Move Up/Down**, **Include subfolders**, **Set / Clear / Open Cover**, **Open Folder** and **Remove Collection**.

RIGHT PANEL

Auditioning & using samples

- **Filter by filename** narrows the list; folder groups can **Expand / Collapse**.
- Preview with **Audition / Stop**, a **volume** slider, and an **Auto** toggle that plays a sample the moment you click it (double-click always plays).
- Right-click a sample to **Load to RS5K on selected track**, drop it into a specific **rack slot**, or **Show in Explorer**. Drag a sample onto a track to load it; hold **Alt** while dragging for REAPER's native file drag.

Sending a collection onward

- From a **Sample Packs** collection (or its right-click menu): **Use for Explosion** sets it as the Explosion source, or **Add as Builder Pool** creates a pool from it.
- From a **Sample Kits** collection: **Create Drum Rack (RS5K)** builds a ready-to-play rack in REAPER, mapped from note 36 up.
- Moved your samples? Missing folders show a **Relink / Auto relink** button; remembered locations relink future racks automatically.

The fastest route: point at a folder, hit Detonate, get a kit.

Source folder — pick a folder of samples (toggle **Include subfolders**); a live count shows how many were found.

Destination folder — where the finished kit is written.

Kit layout — set an optional **name in filename** (e.g. Kick), the **slot count** (1–128) and the **start note**; the note range is shown live.

Optionally add a **slot pattern** and options (see below), then hit **Detonate**. A result popup reports what was copied, with an **Open folder** button.

Options worth knowing

Control	What it does
Slot pattern	Comma-separated categories or keywords (e.g. Kick, Snare, Hihat, Clap) assigned to slots in order and repeated to fill them all. Empty = any sample; unknown words match as “filename contains”. The + button inserts known categories.
Start word + Generate kit name	Type an optional seed word, then Generate kit name to auto-name the kit (leave the seed empty for a fully random name).
Stitched WAV + cues	Also joins every sample into one WAV with an embedded cue point per slice — ready for slicers. WAV sources only; other formats are skipped.
Max sample length (s)	Samples longer than this are never picked (and stay out of the stitched WAV). 0 = no limit.

4

Builder

Full control: define pools and slots yourself, then batch-export.

Start from **Fresh start** or load a preset. Everything sits in collapsible sections (**Pools**, **Slots**, **Quick layout**, **Presets**, **Export**).

STEP A

Pools

A **pool** is a named group of one or more sample folders.

- **+ Pool**, then set the **Alias**, **+ Add folder(s)** and toggle **Subfolders**.
- **Mode**: *Repeat* (samples may be reused) or *Use up* (no repeats until the pool is exhausted, then reshuffle).
- **Scan** counts available samples. Missing folders can be **Relinked** in place.

STEP B

Slots

Each row is one sound in the kit. Build the table with **+ Slot / + 16 slots**; **Notes from 36** rennumbers notes upward.

Column	Meaning
#	Slot number / order.
Pool	Which pool this slot draws from. Orange (no pool) = link one before exporting.
Note / Pad	MIDI note and pad number for the slot.
Filter	Restrict this slot to a category or a custom keyword; a live count shows how many pool samples match (red = none match).
Lock	Pin one exact file so that slot always uses it instead of a random pick.

SHORTCUT

Quick layout (128 slots)

One click fills a full keyboard: white keys alternate between **pool A / B**, black keys all use **one pool** (e.g. Kick / Snare / Hi-hat).

Watch out: this overwrites your current slots.

STEP C

Presets

- **Save** (type a name) stores the current pools + slots; **Update** overwrites a listed one.
- **Load** restores a preset; **Delete** removes it. Presets also appear on the empty-start screen.

STEP D

Export

Naming — number style, note notation, whether to include the alias, and the separator, with a live **Preview** of the resulting filename.

- **Kit name prefix** (empty = random) and a **Start word** + **Generate kit name** helper.
- **Destination** folder and **Kit count** (1–200) to make many variations in one run.
- Optional logs: **MIDI log**, **Sources log**, **Used-samples log** (avoids repeats across sessions), plus **Stitched WAV + cues** and **Max sample length**.
- **Batch export** runs with a progress bar; each kit is its own subfolder of copied, renamed samples.

5

Kit Manager (RS5K rack)

The 4×4 pad window behind the playable racks.

Open it with the **Kit Manager** button in the top bar. It shows the selected kit's RS5K rack as a 4×4 pad grid and is where racks are created and maintained — the Browser's **Create Drum Rack** and both sequencers all target this rack.

- **New Kit** creates a brand-new empty RS5K rack in REAPER.
- Per rack: **Rename kit**, a **Cover** image, **Rack color** and **Rack volume**.
- Per pad: load / replace a sample, set the **MIDI input**, a per-pad **Note-off** setting (also used to stop the sound on mouse release), and pad **auto-name**.
- **Relink** finds pads whose sample moved or whose drive letter changed — pick the new folder once and future racks relink automatically.

Step sequencer

A 16-lane grid driving kit slots 1–16 on the selected rack.

Select the kit's folder track first (the header will say so if you haven't). Each of the 16 lanes is one kit slot; click cells to place steps. Lanes play through the rack's RS5K instances in real time, and a JSFX engine keeps the timing solid.

Per-step editing

Open a lane (click its name; right-click toggles the editor) and pick a **parameter mode** to draw values across its 16 steps:

Mode	Effect
Velocity	How hard each step hits.
Gate / Length	Note length per step (Gate needs RS5K note-off; hidden for one-shot lanes).
Substeps	Ratchets/rolls — retrigger a step several times.
Pitch / Pan / Volume	Per-step RS5K pitch, pan and level offsets.
Probability	Chance a step actually fires, for variation each loop.
Step-mode mask	A per-loop x / . mask (x = trigger, . = skip) so a step can play on some loop repeats and not others.

Per-lane controls

Control	What it does
Solo / Mute	Focus or silence a lane.
One-shot / Retrigger	Play the whole sample ignoring gate, and choose retrigger behaviour.
Note-off (obey)	Whether the lane respects RS5K note-off (needed for Gate/Length to shorten).
Speed	Lane runs at 1×, 0.5× or 2× the master step rate.
Direction	Forward, reverse and other play orders per lane.
Echo	Built-in repeats with adjustable rate, count and velocity mode/delta.
Copy / Paste / Clear	Move lanes around; auto-name labels lanes from their samples.

TRANSPORT

Pattern pages, presets & playback

- Four **pattern pages** per kit; **copy / paste** a whole page.
- A global **pattern library**: **New**, **Save**, **Rename** and **Delete** presets, selectable per page.
- Play in **pattern mode** (loop the page) or **song mode** (chain pages); **Host** follows REAPER's transport and tempo.
- **Export to MIDI**: left-click exports one pattern, right-click exports all four (the Step-Mode cycle); a separate control does pattern vs. song export.

Euclid sequencer

Generative Euclidean rhythms per kit lane, on the same rack.

Euclid shares the rack and lanes with the Step page but generates each lane's rhythm mathematically: spread a number of hits (**Pulse**) as evenly as possible across a number of **Steps**, then **Rotate** to shift the accent. Select a lane to reveal its knob row.

Knob	What it does
Steps / Pulse / Rotate	Pattern length, number of hits, and rotation of the pattern.
Speed / Sub / Len	Lane speed (0.5×/1×/2×), ratchet substeps, and active pattern length.
Prob	Per-lane probability that a hit fires.
Vel / Gate	Base velocity and note length for the lane.
Pitch / Vol / Pan	RS5K pitch, level and pan for the lane (needs an RS5K instance on the lane).
Attack / Release	RS5K amp envelope shaping per lane.
Vel / Pitch / Vol randomisers	“Dice” that add controlled randomness with an amount level and a seed; re-roll for a new variation while keeping the pattern.

- Lane buttons mirror the Step page: **Solo**, **Mute**, **One-shot**, **Retrig**, **Note-off**.
- Its own preset library (**New**, **Save**, **Rename**, **Delete**), plus **Host** sync, **Export**, and a lane connection-lines toggle.

Good to know

- Exports always **copy** samples — your originals are never modified.
- Explosion, Builder and the Browser all fill the same kit structures and share one export engine, so a kit made one way behaves the same everywhere.
- Both sequencers store their patterns on the kit track itself, so each rack carries its own sequences.
- Presets, logs and pattern libraries live under . . . /REAPER/ alongside the script's data.
- **Esc** or the red dot (top-right) closes the window; your theme choice is remembered.

Kit Maker — by TK & Flurmechanik · part of TK Scripts for REAPER