



ALARM & ALERTS MANAGEMENT · SETUP GUIDE

Stop call failures before they escalate

Configure alarm thresholds in Live Hub to get notified the moment call quality drops or failure rates climb, so you can act before customers notice.

Live Hub checks your call metrics every 5 minutes. The moment a metric crosses a threshold you set, it raises an alarm and sends an email to your nominated contacts. This guide walks you through the complete setup: from enabling email notifications to setting the right threshold values.

STEP 1 OF 3: ENABLE ALARM EMAIL NOTIFICATIONS

A Turn on "Forward alarms via email" in Settings

Go to **Settings** → **Advanced tab**. Find the **"Forward alarms via E-mail"** dropdown. It defaults to **Disabled**. Change it to **Enabled** and click **Update**. Without this step, no alarm emails are sent, regardless of what thresholds you configure.

SETTINGS → ADVANCED TAB

Forward alarms via E-mail Enabled ▲

B Add up to 5 email contacts in Settings → Contacts

Go to **Settings** → **Contacts tab**. Click **Add** to add each recipient email address. You can add up to **5 addresses**. These are the people who will receive alarm notification emails when a threshold is crossed.

SETTINGS → CONTACTS TAB

ACCOUNT DETAILS ADVANCED CONTACTS

EMAIL ADDRESS

⊖ ops-team@yourcompany.com

⊖ support@yourcompany.com

Add

STEP 2 OF 3: UNDERSTAND HOW THRESHOLDS WORK

Minor Alert

An early warning. The metric has crossed your lower limit. Worth watching; investigate when convenient.

Major Alert

A critical signal. The metric has crossed your upper limit. Immediate attention is likely required.

HOW THE TWO LEVELS WORK: FAILED CALLS (%) EXAMPLE

You set two separate percentage limits. When the failed-call rate crosses the first limit, a **Minor alarm** fires as an early warning. If it keeps climbing and crosses the second limit, a **Major alarm** fires to signal a critical issue. Once the rate drops back below a threshold, that alarm clears automatically.

MINOR ALERT FIRES WHEN RATE EXCEEDS**10%**

Early warning. Investigate when convenient.

MAJOR ALERT FIRES WHEN RATE EXCEEDS**16%**

Critical. Immediate action likely needed.

Normal (0–10%)

Minor threshold (10%)

Major threshold (16%)

Critical

Recommended starting values: For most deployments, set **Failed calls** Minor at **10%** and Major at **16%**. Apply the same range to **Poor quality calls**. These values give you an early signal while avoiding alert noise from normal traffic fluctuations. You can tighten them once you've seen your baseline.

STEP 3 OF 3: CONFIGURE YOUR ALARM THRESHOLDS**1 Open Alarms → Thresholds tab**

In the left navigation, click **Alarms**. At the top of the page, select the **Thresholds** tab. You'll see the full list of metrics you can monitor.

2 Check the metrics you want to monitor

Tick the checkbox next to each metric you want active. Start with **Failed calls (%)** and **Poor quality calls (%)**: these are the most actionable signals for call health. Unchecked metrics produce no alarms.

ALARMS → THRESHOLDS TAB☒ **Failed calls (%)**

Exceeds threshold ▾

Minor Alert: Threshold value (%)

10

Major Alert: Threshold value (%)

16☒ **Poor quality calls (%)**

Exceeds threshold ▾

Minor Alert: Threshold value (%)

10

Major Alert: Threshold value (%)

16**3 Set the condition: "Exceeds threshold"**

The dropdown has two options:

- **Exceeds threshold:** the alarm fires when the metric goes *above* your value. Use this for failure rates and poor quality calls, where a high percentage is the problem.
- **Drops below:** the alarm fires when the metric falls *under* your value. Use this for metrics where a low value signals an issue, such as average call duration dropping unexpectedly short, or remaining funds running low.

For **Failed calls** and **Poor quality calls**, always select **Exceeds threshold**.

4 Enter your Minor and Major threshold values

You only need to fill in the levels you want. Both are not required, but using both gives you an early warning before things become critical. The values below are suggested as a starting point for testing and monitoring. Adjust them to match your business needs: **Minor = 10%, Major = 16%**.

5 Optionally set billing thresholds

Scroll down to the **Billing** section to set alerts on **Monthly cost** or **Remaining funds**: useful to catch unexpected spend. Billing thresholds are only available on Standalone or Parent accounts.

ALL AVAILABLE METRICS

Failed calls (%)	Poor quality calls (%)	Avg call duration (sec)	Max concurrent calls
Max call attempts per second	Rejected calls (limit exceeded)	Monthly cost (\$)	Remaining funds (\$)

Recommended starting point for call quality monitoring

Additional call statistics

Billing metrics (Standalone/Parent accounts only)

WHAT THE ALARM HISTORY LOOKS LIKE

Once thresholds fire, the **Alarms History** tab gives you a timestamped record of every alarm raised and cleared, including the exact metric value that triggered it.

TIME	SEVERITY	DESCRIPTION
14:30:00	Cleared	Failed calls (%) value 97.06 dropped back below major threshold of 16
13:23:45	Major	Failed calls (%) value 97.06 is above the major threshold of 16
11:18:45	Major	Failed calls (%) value 10.13 is above the minor threshold of 10

Good to know: Alarms clear automatically once the metric drops back below the threshold. No manual action needed. Live Hub supports up to 20 active alarms at a time. You can export the full history as a CSV using the **Export** button on the Alarms History tab.

Ready to set this up? Start in Settings to enable email forwarding, then head to Alarms, Thresholds tab.

Open Live Hub Docs →

Questions? Contact your AudioCodes support team · [Define thresholds](#) · [Active alarms](#) · [Alarm history](#)