

-
-
-
-
-

Chapter 2

Processing



Drinks Transport Planning Processing Functions

Processing within the system is concerned with the throughput of order / pick note transport requirements as follows:

- Creation of transport requirements from order processing modules.
- Building of loads (assigning order/pick note requirements to specific transport loads).
- Release loads.
- Printing of transport documentation.
- Calculate load charges (where appropriate) by manual or automatic rating.
- Consignment of loads to carriers by confirmation of load despatch (optional).
- Matching and authorisation of carrier invoices (where appropriate), *or*
- Recording of loads paid manually.

The processing options are accessed from the Drinks Transport Planning Processing & Load Enquiries menu.

Create Pending Loads

1... /DTP, THEN F21 **2...**

This option creates new pending loads via the entry of a minimum amount of information such that loads are then available for planning. Automatically generated load numbers can be accepted or overtyped (provided that the load does not already exist). In addition, loads can be generated based on existing 'skeleton loads'. These represent standard loads, which are carried on a regular basis.



Note: Skeleton loads can be defined such that they have default header and text information for a given route. In order to create a skeleton load, a normal load header must be created (as above) and then defined as a skeleton via maintain loads, at which point any additional details and instructions are added to it.



Note: Skeleton loads cannot be processed further i.e. they cannot be released via maintain loads.

Create Pending Loads Details Screen



This facility, is accessed by pressing either **F21=Create Load** from Drinks Transport Planning Processing options, or **F13=Pending Load** from the Build Loads Order Selection screen.

The load criteria are displayed on the screen.

```
DTP                HW - Handy Wholesalers Ltd            User GALBRAIJ      13/09/95
                                                           15:48:35

Transport Planning Processing Menu

Processing                                Enquiry
1. Create load schedule                    14. Outstanding orders
2. Build loads                             15. Load details
3. Maintain load
4. Rate loads automatically
5. Rate load manually
6. Conf
7. Auth
8. Auth
9. Canc

Option
Search
F3=Exit
F16=Change Company
18-32

Create Pending Load

Load number ..... H2
Based on .....?..

Ship date ..... 15/09/95
Route .....?.. NHLT02 Northampton to Luton via M. Keynes
Carrier .....?.. MAERS Maers Haulage
Vehicle type ..?.. 1TON 1 Ton with lifting Tailgate
Ship time ..... 0:00

F4=Prompt F8=Update F12=Previous
F4=Prompt F18=Prints F6=Messages F12=Previous
F20=Change Centre F21=Create Load
18-32 SA MK KS IM II KENB20A PED171S1
```

Fields:

Load Number

A reference for a particular load that is either unique within a transport centre or unique within Transport Company (depending on the company profile setting). Load numbers are assigned when pending loads are created via the build loads function or load schedule creation.

Automatically generated load numbers are created with an alphanumeric prefix and a next available six digit number, e.g. A000067.

Screen entry of load numbers allows the exclusion of leading zeros. For example, A000067 can be entered, and is output as A67, or A67 can be entered directly.

Based On

Skeleton load number which is to be used as a base for creating a new load number.



Note: Load header information together with any associated text will be copied.

Ship Date

Ship date that is planned for a given load.



Note: The ship date defaults to today's date plus the planners' time fence days for planning, but you can enter any date.

Route

Code for the journey between two geographical locations or transport nodes. A customer or delivery point is assigned a particular drop sequence along a route.

Carrier

Reference code for either an internal or external carrier that will be associated with the handling of transport requirements.



Note: If carrier is left blank it defaults to the one specified as a default for the route record in Transport Planning Maintenance.

Vehicle Type

Type of vehicle that is to be associated with a load. Vehicle types have weight and volume capacities defined to them.



Note: If vehicle type is left blank it defaults to the one specified as a default for the route record in Transport Planning Maintenance.

Ship Time

Current ship time to be defined against a load.



Note: If ship time is left blank it defaults to the one specified as a default for the route record.



Press **F8=Update** to save the details to file.

Create Load Schedule



1/DTP

Create load schedule enables the planner to create many loads based on skeleton loads, in a single operation via a batch function. The batch function copies across skeleton load header information and associated text.

Create Load Schedule Ship Date Selection

 Select the Create Load Schedule option.

This screen enables the selection of a load on which to base the new load.

TP480A	HW - Handy Wholesalers Ltd	User GALBRAIJ	13/09/95
	Handy Wholesaler Depot 001		15:14:14
Create Load Schedule			
Ship date.....		13/09/95	
Based on load from...		A000120	
Based on load to.....		A000124	
F3=Exit			
05-24	SF	Mk	KS IM II KENB20A PED171S1

Fields:

Ship Date (Planned)

Ship date that is planned for a given load.



Note: The ship date defaults to today's date plus the planner's time fence days for planning.

Based on Load From/To

Skeleton load number range which is to be used as a base for creating a new load schedule.



Note: Load header information together with any associated text will be copied by the batch program.



Press **Enter** to display the Create Load Schedule Ship Date Details Screen.

Create Load Selection Ship Date Details Screen



This screen is displayed when you have selected valid criteria on the Create Load Schedule Ship Date Selection Screen. The details of the selected load ship date are displayed.

TP480B	HW - Handy Wholesalers Ltd	User GALBRAIJ	13/09/95
	Handy Wholesaler Depot 001		15:17:58
Create Load Schedule			
Ship date..... 13/09/95			
Based on			
load (?)	Route	Route description	
A000120			
A000121			
A000122			
A000123			
A000124			

F3=Exit F4=Prompt F8=Submit F12=Previous			
14-02	Sf	MA	KS IM II KENB20A PED171S1

Fields:

Based on Load

Skeleton load number which is to be used as a base for creating a new load number.



Note: Load header information together with any associated text will be copied by the batch program.



Press **F8=Submit** to submit creation of pending loads.

Build Loads



2/DTP

The build loads function enables the planner to review outstanding order requirements depending on various selection criteria. The planner is able to amend specific transport order/despatch note requirements or drop requirements i.e., accumulated order requirements for a given customer, in order to assign requirements to specific loads.

The planner is able to switch between the review of all orders associated with a delivery point drop and the summarised drop requirement for the delivery point.

The planner is able to control the number of requirements presented via a range of ship dates together with one of the following criteria:

- Route/drop range *or*
- Particular carrier *or*
- Origin and optionally destination.

Build Loads Selection Screen

 Select the Build Loads option.

This screen enables the selection of the load build criteria.

TP420A	HW - Handy Wholesalers Ltd	User GALBRAIJ	22/09/95
	Handy Wholesaler Depot 001		10:38:40
Build Loads			
Ship date..... 22/09/95 to 23/09/95			
Route from.....?.. BIRNOT01 Bham to Nham Direct			
Drop.....			
Route to.....?.. NOTLDS01			
Drop.....			
OR			
Carrier.....?..			
OR			
Origin.....?..			
Destination.....?..			
Preselect drops..... 0 (0=No,1=Yes)			
F3=Exit F4=Prompt			
11-25 SF MW KS IM II KENB20A PED171S1			

Fields:

Ship Date From

Ship date from which orders are to be reviewed.

 *Note: The ship date defaults to the current date plus the planners' time fence days for planning.*

Ship Date To

Ship date up to which orders are to be reviewed.

 *Note: The ship date defaults to Date From plus 1.*

Route From

Route from which orders are to be reviewed.

Drop

Drop sequence within the route from which orders are to be reviewed.

Route To

Route up to which orders are to be reviewed.

Drop

Drop sequence within the route up to which orders are to be reviewed.

Carrier

Reference code for either an internal or external carrier that will be associated with the handling of transport requirements.

Origin

Origin associated with the route, associated with the requirements to be planned. Origins must be defined as Transport Nodes.

Destination

Destination associated with a route, associated with the requirements to be planned. Destinations must be defined as Transport Nodes.

Pre-select Drops

0 - No. No pre-selection of details.

1 - Yes. Select order transport details or drops for placing on a suggested load. This results in all the selected lines being pre-filled with a '1' on the next Screen, to reduce key strokes.



Press **Enter** to display the Build Loads Detail Screen.

Build Loads Detail Screen



This screen is displayed when valid entries have been made on the Build Loads Selection Screen.



Note: If there is no suggested load for the delivery requirement i.e. at the time of creation of the requirement no load with sufficient available capacity could be found with the same transport centre, ship date, route and vehicle type, loads will be rechecked before presentation of the detail Screen.

Once order / drop requirements have been added to a suggested load (via selection of '1' and **F8=Update** to update) they will be removed from the Screen.

The planner's attention is brought to orders having special instructions by a flashing asterisk against orders which have external text recorded against them.

The planner's attention is brought to customers who require delivery confirmation by a flashing asterisk against the customer delivery point code and customer name. The flag can be set in order to draw the planner's attention to specific delivery time slots and/or any planner text that has been assigned to the delivery point (usually to indicate fixed delivery requirements).

All lines with a '1' for the load entered in the header are accumulated with the existing planned totals of the load to provide a total gross weight and volume of the lines about to be added to a load. Multiple loads may be built at the same time by entering different loads against the requirements and selecting the lines. The totals will only show values for the single load in the header.

Build Loads Order Selection Screen



This screen is displayed when you enter a '1' next to a load, and press **Enter**.

TP420U	HW - Handy Wholesalers Ltd	User GALBRAIJ	26/10/95
	Handy Wholesaler Depot 001		15:46:47
Build Loads - Order		Route.?. NHLT01	Load.?. H11
Date.... 30/10/95	Drops.... 1	Kegs Case Crite Clnd Palt Botl Othr	Pending
Weight and Volume.....		982.20	344.00
1 30/10/95	NHLT01	982.20	344.00 0001252 H11
Dog & Partridge		10	
In one-way street - offload from		*	

1=Select 2=Load details 3=Delivery profile enquiry 4=Order enquiry					
F3=Exit F4=Prompt F5=Refresh F8=Update F12=Previous F24=More keys					
07-02	SP	MK	KS	IM	II PLYM400A PED171S1

Fields:

Route

Select a route and Load Number being built, or shows the route for a selected load.

Load

Select a Load Number being built.

Date

Shipment Date of a selected load.

Drops

Number of drops assigned thus far to the selected load.

Container Summary

These seven Container headings come from the set established on the Inventory Descriptions file, major type '@STD', or a specific (overriding) set of headings under major type '@xxx' (where xxx is the Transport Centre).

The Container Summary Totals, Total Weight and Volume are all displayed for the selected load.



*Note: For any line shown a Warning message is displayed if there is an incomplete Container Summary set for the Transport Centre or default. I.e. There are container items on the load with an item type that has not been defined to the '*****'*

inventory description type. (See low level codes in Section1, and the container summary field below).



Note: Outer container is the secondary container associated with the item if two containers are recorded in Drinks Inventory Management. If only the primary container is associated with the item that becomes the outer container for this purpose.

Weight and Volume

Total weight and volume thus far committed to the selected load including those lines now selected to be planned to this load, and any previously planned details.



For each retrieved order, the following information is shown:

Select

This field is untitled. Enter one of the following:

- 1 - Select.
- 2 - Load details.
- 3 - Delivery Profile Enquiry.
- 4 - Order Enquiry.

Date

Order delivery due date.

Route

The route defined on the Customer Delivery Points delivery profile. It can be amended. This can be amended by the user to transfer the requirement to another route, for example onto a neighbouring route which is under capacity.

Weight

Weight of the order line, calculated using the 'weight per selling unit' on the Item Master file, which is a weight in any desired measure, per issue unit - e.g. KG per bottle.

Volume

Volume of the order line in any desired measure, calculated using the 'volume per stock unit' on the Item Master file, which is a volume per stock unit - e.g. cubic metre per case.

Order Number

Sales order number and delivery picking note number.

Load Number

Entered or allocated Load Number for the line.

Customer's Name

Delivery customer.

Container Summary

Shows the total number of outer containers, associated with the item on the order line, that fall into each of the seven column headings. The containers fall into a specific column by matching the container's Item Class to the container columns Inventory Descriptions file entry set up as '*STD' or an (overriding) major file type '*xxx' where xxx is the Transport Centre.



Note: Outer container is the secondary container associated with the item if two containers are recorded in Drinks Inventory Management. If only the primary container is associated with the item that becomes the outer container for this purpose.

Functions:

F8

Update entries, i.e. assign selected requirements (selection of '1') to suggested loads either those originally displayed or as amended by the planner.

F13

Create load - please refer to earlier in this section for full details.

F16

Pending loads.



Note: This function key displays pending loads headers that conform to the initial selection criteria i.e. entered ship date and route, carrier or origin/destination.

F20

Amend Consignee Details.

F21

Text.

F24

Roll through function keys.



Press **F8=Update** to update entries.

Load Details Consignee Details Window (F20)



The Screen is accessed by pressing
F20=Consignee from the Build Loads Details
Screen, and displays the Drinks Transport
Planning Consignee Details Enquiry window.

TP265B	HW - Handy Wholesalers Ltd	User GALBRAIJ	22/09/95
	Handy Wholesaler Depot 001		12:53:36
Load Details Enquiry			
Load number	HS	Load status	Pending
Bulk pick load ..	0 (0/1)		
Ship date	19/09/95	Ship time	1:30
Route	NHLT01	Northampton to Luton Route 01	
Carrier	MAERS	Maers Haulage	
Vehicle type	1TON	1 Ton with lifting Tailgate	
Origin			
Vehicle			
Driver			
Distance			
Trip Number			
Exclusive load ..			
Confirmation			
Bill required ...			
Bill format			
Copies			
Consignee Details Name..... Maers Haulage Address..... Maers Depot Welling Industrial Estate NORTHAMPTON. Post code..... F12=Previous			
F3=Exit	F12=Previous	F14=Drops	F15=Orders
F20=Consignee	F21=Text		F16=Totals
01-02		MW	KS
		IM	II
		KENB20A	PED171S1

Fields:

Name

Enter the consignee name.

Address

Enter the consignee address.

Post Code

Enter the consignee post code.



Press **F8=Update** to save the details and return
to the Build Loads Order Selection Screen.

Load Details Text Entry Window (F21)



The window is accessed by pressing **F21=Text** from the Build Loads Details Screen, and displays the Drinks Transport Planning Text Entry window.

TP265B	HW - Handy Wholesalers Ltd	User GALBRAIJ	28/09/95
	Handy Wholesaler Depot 001		15:35:06
Load Details Enquiry			
Load number	H5	Load status	Pending
Bulk pick load ..	0 (0/1)		
Ship date	19/09/95	Ship time	1:30
Route	NHLT01	Northampton to Luton Route 01	
Carrier	MAERS	Maers Haulage	
Vehicle type	1TON	1 Ton with lifting Tailgate	
Origin	MIDC	Des	
Vehicle		Sea	
Driver		Cre	
Distance	.00	Ske	
Trip Number		Age	
Exclusive load ..	0	Pay	
Confirmation	0	P &	
Bill required ...	1	Rat	
Bill format	01	Rat	
Copies	2	Rat	

Lin External Text

1

2

3

4

5

6

Position to

F3=Exit	F12=Previous	F14	F5=Refresh	F12=Previous
F20=Consignee	F21=Text			
21-50	82	MW	KS	IM II KENB20A PED171S1

Fields:

Position To

Enter the line number to appear at the top of the window.

Insert ... After

Enter the number of lines to be inserted in the text as well as the line number after which they should appear

Delete ... From

Enter the number of lines to be deleted from the text as well as the number of the first line which should be deleted.



Note: Up to 999 lines of text can be entered.



Press **F8=Update** to save the text and return to the Build Loads Details Screen.

Load Details Delivery Profile Enquiry (Option 3)



To examine the details the delivery profile, enter a '4' against an existing line in the Build Loads Details Screen, and press **Enter**. The Delivery Profile Enquiry screen is displayed.

TP224B	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		17:34:02
Delivery Profile Enquiry			
Sales company..... ZM Multi-Currency Company			
Customer.....	G00	000 Graham Johnson	
		Royal Building	
		St. Andrews Cross	
Default planning parameters:			
Route.....	NHLT01	Northampton to Luton Route 01	
Drop.....	001		
Carrier.....	MAERS	Maers Haulage	
Area.....	NHPT	Northampton Main Depot 001	
Customer exclusive loads....	0 (0=No,1=Yes)		
Confirm delivery time slot..	1 (0=No,1=Yes)		
Deliveries allowed: Mon Tue Wed Thu Fri Sat Sun			
	1	1	1 0 0 0 (0=No,1=Yes)
F3=Exit F12=Previous F13=Delivery time slots F21=Text			
20-23	SA	MW	KS IM II KENB20A PED171S1



Note: The details are displayed for information only.



Tip: For further information on the Fields and Functions, please refer to the Enquiries Section on this product information.

Load Details Whole Order Enquiry Details Screen (Option 4)



To examine the details of any order from the Build Loads Order Screen, enter a '4' against an existing line, and press **Enter**. The Sales Order Processing Whole Order Enquiry screen is displayed.

```

OE205                      HW - Handy Wholesalers Ltd          USER GALBRAIJ    22/09/95
                                                                12:44:54

Whole Order Enquiry
Order.. 0001242 Customer?... C005      000 Order ref.. RH-2
                                         Type.....
Order date..... 15/09/95 Delivery Solomon's Wine Bar & Restaurant
System order date.... 15/09/95 address (Solowine plc)
Delivery required.... 19/09/95 0      Jenkin's Court
Order value..        225.48          High Road
Base value...        225.48          Worcester          WR1 6QL
Priced at..... ORDER

Ln. Dn Despatch Qty Description          Order Qty. Due Date S Inv No
- 1          3 0 Chimes Scotch Whisky      3 0 19/09/95 A

1=Select
F3=Exit F12=Previous F13=Further detail F15=Restart F21=Internal text
F10=Suspension history F22=External text
14-02 SF MW KS IM II KENB20A PED171S1
  
```



Note: The details are displayed for information only.



Tip: For further information please refer to the Drinks Sales Order Processing product information, Enquiries Section.

Maintain Loads



3/DTP

This function allows loads to be maintained once they have been processed via build loads or automatically by the system. The details planned onto the load may also be maintained. The maintain loads function enables the planner to review load header, drop and order information. Drop, order and order line details can be moved onto new loads and/or new routes. In addition, order capacities (weight, volume or number of containers) can be amended and consignee name and address details together with load external text can be recorded prior to the load being released for printing of documentation within this function.

The planner is able to control the loads presented via entry of a required ship date together with one of the following criteria:

- Route, *or*
- Particular carrier, *or*
- Origin and optionally destination, *or*
- Particular load.



*Note: In order to maintain a load, it must be at a status of 'pending', i.e. not yet 'released' for printing of transport documentation. If a load is selected at a more advanced state than 'pending', then it is displayed with all the details protected from input. In this case **F13=Release** allows the load to be returned to 'pending' for amendment.*

Maintain Load Selection Screen 1



Select the Maintain Load option.

The Selection Screen is displayed which enables the selection of the load criteria.



Note: You may either select all loads for a specific date or restrict the loads displayed for selection by one of the four groups.

TP430	HW - Handy Wholesalers Ltd	User GALBRAIJ	22/09/95
	Handy Wholesaler Depot 001		13:13:55
Maintain Load			
Ship date		19/09/95	
Route		NHLT01	
OR			
Carrier			
OR			
Origin			
Destination			
OR			
Load number			
F3=Exit F4=Prompt			
07-31	82	MW	KS IM II KENB20A PED171S1

Fields:

Route

Enter the route for which loads are to be reviewed.

Carrier

Enter the carrier for which loads are to be reviewed.

Origin

Enter the origin for which loads are to be reviewed.

Destination

Enter the destination for which loads are to be reviewed.

Load Number

Enter a particular load reference which is to be maintained. Entry of a load number overrides the ship date and displays the Load Details Screen directly.



Press **Enter** to display load headers conforming to the selection criteria. Loads of statuses from 'pending' up to 'despatched' are displayed.

Maintain Load Selection Screen 2



If only one load is found that conforms to the selection criteria, this load reference is automatically returned to the Maintain Load Selection Screen, and the Maintain Load Detail Screen is then displayed (see Load Details section).

TP765	HW - Handy Wholesalers Ltd					User GALBRAIJ	22/09/95	
	Handy Wholesaler Depot 001						13:17:40	
Select Load								
	Ship date	Ship time	Route	Origin	Gross Weight	Carrier	Load Number	Load Status
-	19/09/95	1:30	NHLT01	MIDC	683.20	MAERS	H5	Pending
-	19/09/95	1:30	NHLT01	MIDC	.00	MAERS	H8	Pending
Bottom								
1=Select		2=Load details		3=Load totals		4=Release load		
F3=Exit		F12=Previous		F15=All statuses				
07-02		SA	MW	KS	IM	II	KENB20A	PED171S1

Fields:

Select

Select a load.

1 - To select a load. If the load status is 'pending' the system will display the Load Details Screen, if any other status is shown the Released Loads Screen is displayed.

2 - To view load details. This displays the Load Enquiry.

3 - Display load totals. This displays the Load Totals Window.

4 - To release a load. This allows the loads to be released without further display of load details. An error is displayed if the planner is not authorised to release loads. The Confirm Load Release Window is displayed.

Functions:

F13

Release.



Note: If all orders are not flagged as ready for loading a warning is issued if the Transport Centre allows this condition to be overridden.

Press **F13=Release** again to release the load.



*Note: **F13=Release** updates load details as entered and re-displays the screen with all fields protected with the status moved to 'released'. The load is now available for printing of transport documentation (which is done immediately if the corresponding flag is set for the transport centre). Any automatic processing will occur, e.g. automatic load sheets / bill of lading. If rating is not required for the load, and by-pass confirm despatch of load is set, the load status will move to complete.*

This function key can be limited to certain planners.



Press **Enter** to display the next screen dependent on the option chosen.

Maintain Load Details Screen



This screen is displayed when a load has been selected and allows maintenance of all information relating to the load header.



Note: This Screen is displayed only if the load status is 'pending' release, i.e. still available for amendment.

TP430B	HW - Handy Wholesalers Ltd	User GALBRAIJ	27/03/96
	Handy Wholesaler Depot 001		11:32:59
Maintain Load			
Load number	H4	Load status	Pending
Bulk pick load ..	0 (0/1)		
Ship date	5/10/95	Ship time	1:30
Route	NHLT01		Northampton to Luton Route 01
Carrier	MAERS		Maers Haulage
Vehicle type ..?	1TON		1 Ton with lifting Tailgate
Origin	MIDC	Destination	MIDW
Vehicle		Seal number	
Driver		Crew	
Distance	.00	Skeleton load	1
Trip number		Agent contact	
Exclusive load ..	0	Payment method ..?	
Confirmation	0	P & L override ..?	
Bill required	1	Rating status	1 0
Bill format ..?	01	Rate method	04
Copies	2	Rate code	JK9VT
F3=Exit F4=Prompt F5=Refresh F8=Update F24=More keys			
06-20 S4 MW KS IM II KENB20A PED129S1			

Fields:

Bulk Pick Load

Single digit flag to show whether or not Bulk Picking is to be used.

Ship Date

Required ship or despatch date for the load.

Ship Time

Current ship time that has been defined/maintained against a load.

Route

Route that has been assigned to the load.

Carrier

Reference code for either an internal or external carrier that has been assigned to the load.

Vehicle Type

Type of vehicle that is to be associated with a load. Vehicle types have gross weight and volume capacities defined to them.

Origin

Origin or start point associated with the route that has been assigned to a load. Origins must be defined as transport nodes.

Destination

Destination or end point associated with a route that has been assigned to the load. Destinations must be defined as transport nodes.

Vehicle

Specific vehicle reference that will be associated with the load.

Seal Number

Seal number associated with load. This is used for security tagging and is printed on the bill of lading documentation.

Driver

Specific driver reference that will be associated with the load.

Crew

Reference of a second driver or drivers mate, who will be associated with the load.

Distance

(Optional.) The distance to be covered by this load.

Skeleton Load

Indicates if the load is a skeleton load. Skeleton loads consist of base load detail information with associated text (if required) that can be used as 'based on' information when creating pending loads or load schedules.

Trip Number

(Optional.) A number associated with this load for this delivery.

Agent contact

Agent contact name (if applicable).

Exclusive Load

Exclusive Transport Load. If set to '1' indicates that the load is exclusive i.e. the load consists of requirements for a single customer delivery point (based on its eight character account code and three character delivery sequence). This happens when a delivery profile requiring exclusive loads is planned onto the load. It is not maintainable by the planner.

Payment Method

Freight Payment Method. Defined to the transport centre as a default and maintained against a load. Freight payment methods are defined to the Inventory descriptions file under a major type of 'TPPM', and are printed on bill of lading documentation.

Confirmation

Indicates whether confirmation of a delivery time slot at the customer's depot is required for any of the drop/delivery points on the load, as follows:

0 - No.

1 - Yes.

2 - Yes and confirmation has taken place. (Manually set after conversation with the customer).

P & L Override

Profit and Loss Override account that may be used in conjunction with the Advanced Financial Integrator for posting transport costs to the General Ledger. This is a memo field in the Drinks module.

Bills Required

Indicates if bill of lading documentation is required for this load.

0 - Only a load sheet is produced.

1 - Bill and lading and load sheet are output.

Rating Status

This is in fact two flags, 'rated flag' and 'transport load rated' described as follows:-

Rated Flag

Indicates if rating, i.e. calculation of charges for load, is required or has taken place, as follows:

0 - Rating not required.

1 - Automatic rating required.

2 - Manual rating required.

3 - Load has been rated (manually or automatically).

Transport Load Rated

Rating status of load; indicating if the load has been rated, i.e. charges calculated for load, and if so by what method, as follows:

0 - Load has not been rated.

1 - Load has been rated automatically.

2 - Load has been rated manually.



Note: 'Rated flag' and 'transport load rated' flag indicate the fact that loads may require re-rating i.e. 'rated flag' is a measure of what rating is required, and 'transport load rated' flag indicates what rating has previously taken place.

Bill Format

Bill of Lading Format Code. Format required for the bill of lading documentation.



Note: Four formats are supported and are defined to the Inventory descriptions file against a major type of 'TPBL', as follows:

01 - One document per load. Capacity totals (gross weight, volume, number of containers) from load header. All despatch note numbers associated with the load are output together.

02 - One document per drop / delivery point on route. Capacity totals (gross weight, volume, number of containers) per drop/delivery point. All despatch note numbers associated with the drop/delivery point are output.

03 - One document per load. Capacity totals (gross weight, volume, number of containers) from load header. One totals line per drop. All despatch note numbers for each drop/delivery point are output together.

04 - One document per load. Capacity totals (gross weight, volume, number of containers) per area and totals for load. All despatch note numbers associated with the load are output together.

Rate Method

Transport Rate Method. Method of rating that is associated with the rate code for the load. Rate methods are defined to the Inventory descriptions file under a major type 'TPRM', as follows:

01 - Load and rate table. Charges are calculated based on the load's gross weight, volume or number of containers according to a rating table.

02 - Drop and rate table. Charges are calculated based on each drops gross weight, volume or number of containers according to a rating table.

03 - Fixed rate per area. Charges are calculated based on the gross weight, volume or number of containers dropped into each area, using a fixed rate for each area.

04 - Area and rate table. Charges are calculated based on the gross weight, volume or number of containers for each area according to a capacity table.

Copies

Number of copies of the bill of lading documentation required.

Rate Code

Transport rate code that is associated with the rating method for the load that defines rating criteria that are effective on a given date. This normally identifies the route and carrier to which the rating applies.

Functions:

F13

Release.



*Note: If all orders are not flagged as ready for loading a warning is issued if the Transport Centre allows this condition to be overridden. Press **F13=Release** again to release the load.*



*Note: **F13=Release** updates load details as entered and re-displays Screen with all fields protected with the status moved to 'released'. The load is now available for printing of transport documentation (which is done immediately if the corresponding flag is set for the transport centre). Any automatic processing will occur, e.g. automatic load sheets / bill of lading. If rating is*

*not required for the load, and by pass confirm
despatch of load is set, the load status will move
to complete.*

*This function key can be limited to certain
planners.*

F14

Drops. Drops for the load are displayed for selection to be moved to another load, or removed and re-instated as outstanding.

F15

Orders. Orders for the load are displayed for selection to be amended, moved to another load or removed.

F16

Totals. The Load Totals enquiry is displayed, which gives totals for capacities, drops, orders, rating and payment details.

F20

Consignee. Name and address details for consignee.



*Note: Consignee details for load are printed on
all bill of lading documentation where there is
one document per load i.e. formats '01', '03', and
'04'.*

F21

Text. Load text is printed on all bill of lading documentation and normally contains special delivery instructions.

F24

Roll through function keys.



Select a suitable function key.

Maintain Load Released Loads Screen (Option 4)



This screen is displayed if you have selected option '4' from the Maintain Load Selection Screen. If the load is released (no longer pending) the Maintain Load Details Screen is displayed but cannot be amended.

TP430A		HW - Handy Wholesalers Ltd		User GALBRAIJ		6/10/95	
		Handy Wholesaler Depot 001				15:01:03	
Maintain Load							
Load number		H6		Load status		Released	
Bulk pick load ..		0 (0/1)					
Ship date		15/09/95		Ship time		0:00	
Route		NHLT01		Northampton to Luton Route 01			
Carrier		MAERS		Maers Haulage			
Vehicle type							
Origin		MIDC		Destination		MIDW	
Vehicle				Seal number			
Driver				Crew			
Distance.....		.00		Skeleton load		0	
Trip Number.....				Agent contact			
Exclusive load ..		0		Payment method			
Confirmation		0		P & L override			
Bill required ...		1		Rating status		1 0	
Bill format		01		Rate method		04	
Copies		2		Rate code		JK9VT	
F3=Exit		F5=Refresh		F12=Previous		F13=Hold	
F24=More keys							
01-02		SC		HW		KS	
				IM		II	
				KENB20A		PED171S1	

Functions:

F13

Hold.



Note: This function key updates the status of the load to pending, which puts it on hold for re-planning, and redisplay the Screen with all fields unprotected.



Note: A load must be set back to pending before any maintenance can take place. This may be done to any status of load prior to Complete.

F14

Enquire on Drops.

F15

Enquire on Orders.

F16

Enquire on Totals.

F20

Enquire on Consignee.

F21

Enquire on Text entry.



Select a suitable function key.

Maintain Load Move Drop Detail Screen (F14)



This screen provides the function to remove drop details or move them onto a new load and is accessed by entering '1' against the appropriate drop (after first using **F14=Drops** to display drops).



Note: All order details associated with the drop are moved in line with the drop amendment.

TP775	HW - Handy Wholesalers Ltd	User GALBRAIJ	6/10/95
	Handy Wholesaler Depot 001		15:29:58
Select Drops for a Load			
Load number	H10	Load status.....	Pending
Ship date	5/10/95	Ship time.....	1:30
Route	NHLT01	Northampton to Luton Route 01	
S	Drop		
1	001		

Move Drop Details

Customer..... C005 /000
Solomon's Wine Bar & Restaurant

From

Route..... NHLT01 Northampton to Luton Route 01

Drop..... 001

Load..... H10

To

Route....?..

Drop.....

Load.....

1=Select
F3=Exit

F4=Prompt
F5=Refresh
F8=Update
F24=More keys

F12=Previous

10-34 **SF** HW KS IH II KENB20A PED171S1

Fields:

Route

Enter the route to which the drop is to be moved.

Drop

Enter the drop sequence the customer delivery point has been assigned for the entered route.

Load

Enter the load number which the drop details are to be moved onto.

If a route / drop is entered but the load is left blank, the system will display all loads for selection that are associated with the route on the required date.



If only one load number is found, this is automatically displayed.

Functions:

F14

Orders. All orders associated with drops are displayed for selection for move/amendment.

F16

Pending loads.



Note: Function key displays pending load headers that conform to selection criteria i.e. ship dates, route entered (all routes if blank), and all carriers.



Note: If only one load is found that conforms to the selection criteria, selection is by-passed and the load reference is returned to the Screen.

F24

Roll through function keys.

Maintain Load Enquire on Orders Screen (F15)



This screen displays orders for a load and is displayed when you press **F15=Orders** on the Maintain Load Released Loads Screen.

Fields:

Select

Enter one of the following options:

- 1 - Move the order.
- 2 - Amend the order details.
- 3 - Whole Order Enquiry.
- 4 - Display the customer delivery profile.



Enter an option into the Selection Field and press **Enter**.

Maintain Load Move Order Detail Window (Option 1)



This Screen provides the function to remove order details or move them onto a new load, and is accessed by entering '1' against the appropriate order (after first using **F15=Orders** to display orders), or **F14=Orders** on the Maintain Load Move Drop Detail Window.



Note: All drop details associated with the order are updated in line with the order amendment.

TP780A	HW - Handy Wholesalers Ltd	User GALBRAIJ	6/10/95
	Handy Wholesaler Depot 001		15:41:42
Enquire on Orders for a Load			
Load number.....	H10	Load status.....	Pending
Ship date.....	5/10/95	Ship time.....	1:30
Route.....	NHLT01	Northampton to Luton Route 01	
Move Order Details			
Order..... 0001243			
Stockroom.... 02 Central Depot (W&S)			
From			
Route..... NHLT01 Northampton to Luton Route 01			
Drop..... 001			
Load..... H10			
To			
Route....?.. █			
Drop.....			
Load.....			
1=Select 2=Amend F4=Prompt F5=Refresh F8=Update F24=More keys			
F3=Exit F12=Previous			
18-34 S2 HW KS IM II KENB20A PED171S1			

Fields:

Route

Enter the route which the order details are to be moved onto.

Drop

Enter the drop sequence the customer delivery point has been assigned for the entered route.

Load

Enter the load number which the order details are to be moved onto.

If a route / drop is entered but the load is left blank, the system will display all loads for selection that are associated with the route on the required date.



If only one load number is found, this is automatically displayed.

Functions:

F14

Lines. Lines for the load are displayed for selection to be moved.

F16

Pending loads.



Note: Function key displays pending loads headers that conform to selection criteria i.e. ship dates, route entered (all routes if blank), and all carriers.



Note: If only one load is found that conforms to the selection criteria, selection is by-passed and the load reference is returned to the Screen.

F24

Roll through function keys.

Maintain Loads Amend Orders Detail Window (Option 2)



This is selected by entering a '2' against a line on the Enquire on Orders for a Load Screen.

This screen provides the function to maintain capacity details for transport order/despatch note requirements. In addition, the details can be confirmed as 'ready for loading'.

TP780A	HW - Handy Wholesalers Ltd	User GALBRAIJ	6/10/95
	Handy Wholesaler Depot 001		16:26:32
Enquire on Orders for a Load			
Load number.....	H10	Load status.....	Pending
Ship date.....	5/10/95	Ship time.....	1:30
Route.....	NHLT01	Northampton to Luton Route 01	
S Drop	Wei		
2 001	20		
- 001	27		

Amend Order Details

Order..... 0001242

Stockroom..... 02 Central Depot (W&S)

Gross weight..... 204.96

Net weight..... 204.96

Tare weight..... .00

Volume..... 24.00

Containers..... 0

Ready for loading.. ☒ (0=No, 1=Yes)

COD amount..... .00

1=Select 2=Amend 3=Ord F5=Refresh F8=Update F24=More keys
F3=Exit F12=Previous

19-49 SF HW KS IM II KENB20A PED171S1

Fields:

Gross Weight

Amend the gross weight associated with the order requirement.

Net Weight

Amend the total weight of the actual goods associated with the order.

Tare Weight

Amend the total weight of the containers for the order.



Note: Gross weight must always equal the sum of net and tare weight.

Volume

Amend the total volume associated with the order requirement.

Containers

Amend the total number of containers associated with the order requirement.

Ready for Loading

Indicates that the order/despatch note transport details are ready for loading - i.e. have been confirmed as assembled via Drinks Sales Order Processing.

COD Amount

Amend the amount to be collected by the driver on delivery of the goods (if required). Correct to two decimal places.

Functions:

F14

Lines.

F24

Roll through function keys.

Maintain Loads Order and Delivery Profile Enquiries

Both the order details and the Customer's Delivery Profile may be examined by selecting either '3' or '4', respectively, against an order line for a selected load. These details are for information only, however, at this point.

Maintain Load Move Order Lines Selection Screen (F14)



This Screen allows selection of order lines for movement, and is accessed by using **F14=Lines** from the Maintain Load Move Orders or Amend Order Details Screens.

TP781	HW - Handy Wholesalers Ltd	User GALBRAIJ	6/10/95
	Handy Wholesaler Depot 001		15:55:12
Select Order Lines			
Order number	0001243	Stockroom	02 Central Depot (W&S)
Despatch date ...	5/10/95	Despatch time ...	1:30
Load number	H10	Load status	Pending
Route	NHLT01	Drop	001
	Northampton to Luton Route 01		
Line	Quantity	Weight	Volume Containers
1	4 0	273.28	32.00 0
1=Select 2=Order line enquiry			
F3=Exit F12=Previous			
11-04	SP	HW	KS IM II KENB20A PED171S1

Fields:

Selection

- 1 - Select for move.
- 2 - Order line enquiry.



Press **Enter** to continue.

Maintain Load Move Order Line Window (Option 1)



This screen is displayed by entering '1' against the line(s) to be moved onto a separate load.

This Screen provides the function to move order / despatch note line details onto a new load which can be associated with a different route. This provides the facility to split orders / despatch notes across different loads.

TP781	HW - Handy Wholesalers Ltd	User GALBRAIJ	6/10/95
	Handy Wholesaler Depot 001		15:55:12
Select Order Lines			
Order number	0001243	Stockroom	02 Central Depot (W&S)
Despatch date ...	5/10/95	Despatch time ...	1:30
Load number	H10	Load status	Pending
Drop	001		
Route			
Move Order Line Details			
Line	1		
Order.....	0001243	Line.....	1
Item.....	C101		Chimes Scotch Whisky 8x11
Stockroom....	02		Central Depot (W&S)
From			
Route.....	NHLT01		Northampton to Luton Route 01
Drop.....	001		
Load.....	H10		
To			
Route....?..			
Drop.....			
Load.....			
F4=Prompt F5=Refresh F8=Update F24=More keys			
1=Select F3=Exit F12=Previous			
18-34	SF	MW	KS IM II KENB20A PED171S1

Fields:

Route

Enter the route which the despatch note line is to be moved onto.

Drop

Enter the drop sequence the customer delivery point has been assigned for the entered route.

Load

Enter the load number which the despatch note line details are to be moved onto.

If a route/drop is entered but the load is left blank, the system will display all loads for selection that are associated with the route on the required date. If only one load number is found, this is automatically displayed.

Functions:

F16

Pending loads



Note: Function key displays pending load headers that conform to selection criteria i.e. ship dates, route entered (all routes if blank), and all carriers.



Note: If only one load is found that conforms to the selection criteria, selection is by-passed and the load reference is returned to the Screen.

F24

Roll through function keys.

Maintain Loads Consignee Details Window (F20)



This Screen allows the consignee name and address to be overridden and is accessed via **F20=Consignee** from the Maintain Loads Initial Detail Screen.

TP430B	HW - Handy Wholesalers Ltd	User GALBRAIJ	6/10/95
	Handy Wholesaler Depot 001		16:54:10
Maintain Load			
Load number	H10	Load status	Pending
Bulk pick load ..	0 (0/1)		
Ship date	5/10/95	Ship time	1:30
Route	NHLT01	Northampton to Luton Route 01	
Carrier	MAERS	Maers Haulage	
Vehicle type .?	1TON	1 Ton with lifting Tailgate	
Origin	M		
Vehicle	-		
Driver	-		
Distance	-		
Trip number	-		
Exclusive load ..	0		
Confirmation	0		
Bill required ...	1		
Bill format ..?	0		
Copies	-		
Consignee Details Name..... Maers Haulage Address..... Maers Depot Welling Industrial Estate NORTHAMPTON. Post code.....			
F5=Refresh F8=Update F12=Previous			
F3=Exit F4=Prompt F5=Refresh F8=Update F24=More keys			
14-42 S2 MW KS IM II KENB20A PED171S1			

Fields:

Name and Address

Consignee name and address details. This defaults to the carrier name and address where there is one BoL per load. Where there is one BoL per order the consignee printed is always the customer.

Post Code (1)

First portion of post code.

Post Code (2)

Second portion of post code.



Press **F8=Update** to save the changes to file.

Maintain Load Load Text Window (F21)



This Screen is displayed when you press **F21=Text** from the initial Maintain Loads Detail Screen and allows maintenance of text to be printed on the load documentation.

TP430B	HW - Handy Wholesalers Ltd	User GALBRAIJ	6/10/95
	Handy Wholesaler Depot 001		16:54:10
Maintain Load			
Load number	H10	Load status	Pending
Bulk pick load ..	0 (0/1)		
Ship date	5/10/95	Ship time	1:30
Route	NHLT01		Northampton to Luton Route 01
Carrier	MAERS		Maers Haulage
Vehicle type ..?	1TON		1 Ton with lifting Tailgate
Origin	MIDC	Des	
Vehicle		Sea	
Driver		Cre	
Distance	.00	Ske	
Trip number		Age	
Exclusive load ..	0	Pay	
Confirmation	0	P &	
Bill required ...	1	Rat	
Bill format ..?	01	Rat	
Copies	2	Rat	
F3=Exit		F4=Prompt	F5=
15-50		82	MW KS IM II KENB20A PED171S1

Lin External Text

1	Joint delivery with H9 for
2	Solowine
3	
4	
5	
6	

Position to ____ Insert ____ after ____
Delete ____ from ____

F5=Refresh F8=Update F12=Previous

Fields:

Position To

The cursor will position to the line entered here.

Insert

Type the number of the lines that you wish to insert.

After

Type in the line number you wish the inserted lines to follow.

Delete

Enter the number of lines that you wish to delete from this text.

From

Type in the number of the line that you wish to start the deletion from.



Press **F8=Update** to save the changes to file.

Rate Loads Automatically



4/DTP

This Screen provides function for the calculation of the expected carrier charge for selected loads via a submitted batch job. A particular load can be selected, or a rate method entered, which selects all loads that are to be rated by that particular rate method for the entered ship date.

If a particular load cannot be rated, it's details are output on a rating exceptions report.



Note: If neither rate method nor load are entered, all loads requiring rating for the entered ship date will be rated regardless of rate method.



Note: A load is only selected after its transport documentation has been produced and it's rating status is '1' (to be rated automatically).

Rate Loads Automatically Selection Screen



Select the Rate Loads option.

The system will display the Rate Loads Automatically Screen on which you can select a load.

TP440	HW - Handy Wholesalers Ltd	User GALBRAIJ	3/10/95
	Handy Wholesaler Depot 001		11:22:38
Rate Loads Automatically			
Ship date	4/10/95		
Rate method	?		
OR			
Load number			
F3=Exit F4=Prompt F8=Submit F16=Load number			
05-34 SF MW KS IM II PLYM400A PED171S1			

Fields:

Ship Date

Ship date for selection of loads - defaults to the current date plus planner's time fence days for planning.

Rate Method

Method of Transport Rating that is associated with a particular rate code. Rate methods are defined to the Inventory descriptions file under major type 'TPRM', as follows:

01 - Load and rate table. Charges are calculated based on the load's gross weight, volume or number of containers according to a rating table.

02 - Drop and rate table. Charges are calculated based on each drop's gross weight, volume or number of containers according to a rating table.

03 - Fixed rate per area. Charges are calculated based on the gross weight, volume or number of containers dropped into each area.

04 - Area and rate table. Charges are calculated based on the gross weight, volume or number of containers for each area according to a capacity table.

Load Number

Enter a particular load reference which is to be rated. The entered load must be at status '60' i.e. 'awaiting rating'.

Functions:

F16

Load Number.

This displays printed load headers, i.e. which are awaiting rating, for the entered ship date.



Note: If only one load number is found, selection is by-passed and the load is returned to the Screen.



Note: In order to re-rate a load - i.e. recalculate transport charges, the following procedure must be followed:

Set load back to a pending state via the Maintain Loads function (using Function Key F13=Maintain Loads).

Make order/drop changes (if required), reset the rated flag, and set the load back to a released state via the Maintain Loads function (again using Function Key F13).

Print bill of lading documentation and/or load sheets.

Re-rate via automatic or manual method (depending on whether the rated flag is '1' or '2' respectively).



Press **F8=Submit** to submit the process.

Rate Load Manually



5/DTP

This option allows the calculation of the expected carrier charge for a selected load based on manual input as opposed to automatic rating. Automatic rating uses the rating criteria maintained for an appropriate rate method and rate code that is effective on a given date (see Rate Load Automatically).



Note: The load must have transport documentation printed and its rated status set to '2' (to be rated manually). If its status is '1', a warning message is displayed to suggest that this load should be automatically rated. This warning may be overridden. If you override this condition the load is changed for manual rating. You must hold the load to change it back to automatic rating and re-release it.

Rate Load Manually Selection Screen



Select the Rate Load Manually option.

Fields:

Load Number

Enter a valid load reference which is to be rated. The entered load must be at status '60' ('awaiting rating').

Functions:

F16

Printed loads.

This displays all printed load headers - i.e. those awaiting rating



Note: If only one load number is found, selection is bypassed and the load is returned to the Screen.



Press **Enter** to display the Rate Load Manually Detail Screen.

Rate Loads Manually Detail Screen



This screen is displayed when you have entered the load number into the Rate Load Manually Selection Screen and pressed **Enter**.

Load Number, Route, Carrier and Load Containers have already been assigned, and are displayed for information only. Load containers may display as 'Load Volume' or 'Load Weight' depending on the default capacity for the Transport Centre, and function keys **F15=Weight**, **F16=Volume**, and **F17=Containers**.

TP450B	HW - Handy Wholesalers Ltd	User GALBRAIJ	3/10/95
	Handy Wholesaler Depot 001		12:12:28
Rate Loads Manually			
Load number	H2	Route.....	NHLT01
Load containers.....		Carrier.....	MAERS
			0
VAT code.....?	8		
Rate.....			.00
Conversion factor.....			1.00000
Minimum containers.....			0
Surcharge percentage.....			.00
Surcharge value.....			.00
Total charges.....			.00
Drop charges.....			.00
Penalties.....			.00
Surcharges.....			.00
Load grand total.....			.00
F3=Exit	F4=Prompt	F5=Refresh	F8=Update
F15=Weight	F16=Volume		F12=Previous
08-45	8	MW	KS
		IM	II
		PLYM400A	PED171S1

Fields:

VAT Code

VAT code to be associated with the calculation of VAT on load charges. VAT code must be defined to the General Ledger if it is attached - i.e. a General Ledger company code defined to the Drinks Transport Planning company profile.

If General Ledger is not attached, the VAT code must be defined to the Inventory Descriptions file under major type 'VAT'.

Rating is always calculated exclusive of VAT, which is only applied once the carrier invoice is transferred to Accounts Payable.

Rate

(Optional). Rate for single unit of capacity (gross weight, volume or number of containers depending on the capacity type) to two decimal places.

Conversion Factor

Conversion factor, to five decimal places, associated with rating of loads.

In accordance with the capacity type associated with the rating details, the load gross weight, volume or number of containers is divided by this factor before calculation of a rate for a given quantity.

Minimum Weight / Containers / Volume

(Optional). Used in the calculation of penalties if the load gross weight (number of containers or volume) is less than the minimum weight (number of containers or volume).

Surcharge Percentage / Value

A percentage (to two decimal places) or a value, that can be applied to calculated load charges in order to accommodate unforeseen extras e.g. government fuel tax charges.



Note: Either a surcharge percentage or value can be entered but not both.

Total Charges

If no charge rate has been entered, this field may be manually entered (to two decimal places).

If a charge rate has been entered, the total charge is calculated as follows:

Rating Quantity x Charge Rate = Total Charge

Conversion Factor

Drop Charges

(Optional). The fixed charge, to two decimal places, associated with the number of drops on the load.

Penalties

Calculated penalty charge, to two decimal places. Penalties will only apply when the load capacity is less than the minimum capacity, and are calculated by rating the difference between the minimum capacity and the actual capacity to be shipped.

Surcharges

Surcharge value entered, or value based on the surcharge percentage if entered.

Load Grand Total

Grand total charge, to two decimal places, calculated as follows:

Total charge + drop charge + penalty charge + surcharge

Functions:

F15

Weight - switches to rating by weight of the load.

F16

Volume - switches to rating by volume of the load.

F17

Containers - switches to rating by containers on the load.



*Note: **F15=Weight**, **F16=Volume** and **F17=Containers** are used to define the capacity type that is to be associated with the rating information.*



Note: In order to re-rate a load - i.e. recalculate transport charges, the following procedure must be followed:

*Set load back to a pending state via the Maintain Loads function (using **F13=Maintain Loads**).*

*Make order/drop changes (if required), reset the rated flag, and set the load back to a released state via the Maintain Loads function (again using **F13=Maintain Loads**).*

Print bill of lading documentation and/or load sheets..

Re-rate via automatic or manual method (depending on whether the rated flag is '1' or '2' respectively).



Press F8=Update to save the details to file.

Confirm Despatch of Load



6/DTP

This function provides the optional facility for date stamping the load, in order to confirm that the load has left the transport centre. It is by-passed if the flag for the transport centre is set accordingly.

The planner is able to control the loads presented via entry of a required ship date together with one of the following criteria:

- Route, *or*
- Particular carrier, *or*
- Origin and optionally destination, *or*
- Particular load.



Note: If the load requires authorisation of payments i.e. rating has taken place, the load status is updated as awaiting payment.



Note: If rating was not applicable the load status is updated such that it is awaiting drop to history, i.e. payment authorisation is by-passed.

Confirm Despatch Load Selection Screen

 Select the Confirm Despatch of Load option.

TP460A

HW - Handy Wholesalers Ltd

User GALBRAIJ

3/10/95

Handy Wholesaler Depot 001

13:27:39

Confirm Despatch of Load

Ship date 3/10/95

Route?..

OR

Carrier?..

OR

Origin?..

Destination ..?..

OR

Load number HS

F3=Exit

F4=Prompt

F16=Select load

18-25

SF

HW

KS

IM

II

PLYM400A

PED171S1

Fields:

Ship Date

Ship date for which loads are to be reviewed - defaults to the current date.

Route

Enter the route for which loads are to be reviewed.

Or

Carrier

Enter the carrier for which loads are to be reviewed.

Or

Origin

Enter the origin for which loads are to be reviewed. This must be a valid Transport Node.

And

Destination

Enter the destination for which loads are to be reviewed. This must be a valid Transport Node.

Or

Load Number

Enter a particular load reference which is to be reviewed.

Functions:

F16

Select loads.

This displays load headers conforming to the selection criteria - i.e. printed and rated loads (for loads that have been rated), and printed loads (for loads where rating is not applicable).



Note: If only one load is found, selection is bypassed and the load reference is returned to the Screen.



Press **Enter** to display the Confirm Despatch Load Details Screen.

Confirm Despatch - Load Details Screen



The Confirm Despatch Load Details Screen is displayed when you have selected a valid load from the Confirm Despatch Load Selection Screen and displays load header information for review / confirmation.

Functions:

F20

Display consignee details.

F21

Display load external text which has been printed on the transport documentation.

Authorise Payments



7/DTP



Warning: This option is not currently supported!

This function allows payments to be matched and recorded, on receipt of an external carrier's invoice. Invoice details are matched against the calculated load charges. If there is any discrepancy between the calculated charges and the payment amount, only authorised users can authorise the payment.

Accounts payable log entries may be created if the carrier has an associated supplier and the carrier invoice date is entered.



Note: Once authorised, the load status is updated such that it can be dropped to history.



```

TP490A          HW - Handy Wholesalers Ltd      User GALBRAIJ  3/10/95
                  Handy Wholesaler Depot 001      13:38:27
Authorise Payments

Carrier .....?.. MAERS

```

```

F3=Exit      F4=Prompt

05-36      Sr      MW      KS      IM      II      PLYM400A PED171S1

```

Carrier

Press **Enter** to display the Authorise Payments Invoice Details Screen.

Authorise Payments Invoice Details Screen



This screen is displayed when you have entered a valid carrier code into the Authorise Payments Carrier Selection Screen.

TP490B	HW - Handy Wholesalers Ltd	User GALBRAIJ	3/10/95
	Handy Wholesaler Depot 001		13:41:12
Authorise Payments			
Carrier	MAERS	Maers Haulage	
Carrier invoice number	MAE651234		
Carrier invoice date	310795		
Invoiced freight amount			
Load number			
F3=Exit	F12=Previous	F16=Unpaid loads	
11-31	SF	HW	KS IM II PLYM400A PED171S1

Fields:

Carrier Invoice Number

Carrier's invoice reference.

Carrier Invoice Date

Carrier's Invoice Date. If you wish to post to the Accounts Payable log, you must enter a valid date.

Invoiced Freight Amount

(Reference only). Invoice total as detailed on the carrier's invoice. (May be zero for a free of charge delivery.)

Load Number

Enter the appropriate load reference associated with the carrier's invoice (if there is only one load on the invoice.)

The entered load must be at status '80' i.e. 'awaiting authorisation of payments'.

This requires that the load must have been rated (and confirmed as despatched, if the despatch function is used).

Functions:

F16

Unpaid loads.



Note: This displays load headers conforming to the selection criteria - i.e. loads that have been rated and despatched but not yet authorised for payment.



Note: If only one load is found, selection is bypassed and the load reference is returned to the Screen.



Press **Enter** to display the Authorise Payments Payment Details Screen.

Authorise Payments Payment Details Screen



The Payment Details screen is automatically displayed if a single load has been selected.

Fields:

Route

Route code and name associated with the load.

Ship Date

Date on which the load was despatched.

Calculated Amount

The rated value of the load.

Payment Amount Excluding VAT

Amount (excluding tax) which is to be authorised for payment, normally the calculated amount (which should also be the invoiced amount.)

Payment Reference

Payment reference that is to be associated with the payment being made to the carrier. This reference may be carried forward into the financial systems for reference.



*Note: Reference defaults to the load reference.
This field is upper case only.*



*Note: This presents an additional adjustments
Screen if the payment amount is not the same as
the calculated charge amount*



Press **F8=Update Payment Details**. This may also transfer to the Accounts Payable invoice log if no adjustment.

Authorise Payments Adjustment Details Screen



This Screen is automatically displayed where there is a difference between the payment and calculated amounts.

Fields:

Adjustment Amount

This is calculated and displayed as:

Payment Amount - Calculated amount

A positive value indicates payment greater than calculated.

Adjustment Reason

This must be a valid reason code associated with the adjustment. Reason codes are maintained on the Inventory descriptions file under a major type of 'TPAR'. This may be used for analysis purposes.

Adjustment Reference

Optional adjustment reference that is to be associated with the difference between the payment amount and the calculated charge amount.



Press **F8=Update**. This will update the file and may also transfer details to the AP invoice log.

Authorise Payments Warning Screen



A warning is displayed if there is a discrepancy between the calculated charges and the entered payment amount, and the user is not authorised to make payment adjustments.



*Note: The payment entry can be bypassed by pressing **Enter** or can be recorded by pressing **F8=Update**. If the payment details are entered, an appropriate user who has been authorised to make adjustments will need to review the details before the payment transaction can be completed (via this Authorise Payments option).*

Authorise Manual Payments



8/DTP

This function is used as an exception where the carrier has been paid directly for delivery of a load through Accounts Payable. No matching of carrier invoice is required and the load is completed without posting the invoice as it has already been settled.

In other respects this process is similar to the Authorise Payments function.

Cancel Loads



9/DTP

This function allows load headers to be cancelled. All associated transport order requirements are put back to an outstanding state such that they can be reviewed again via the build loads function.

The planner is able to control the loads presented via entry of a required ship date together with one of the following criteria:

- Route, *or*
- Particular carrier, *or*
- Origin and optionally destination, *or*
- Particular load.



Note: Once cancelled, the Load Status is updated such that it can be deleted via the drop to history utility.

Cancel Loads Selection Screen

 Select the Cancel Loads option.

TP470A

HW - Handy Wholesalers Ltd

User GALBRAIJ

26/10/95

Handy Wholesaler Depot 001

16:41:14

Cancel Load

Ship date 27/10/95

Route?..

OR

Carrier?..

OR

Origin?..

Destination ..?..

OR

Load number H10

F3=Exit

F4=Prompt

F16=Select load

10-26

Sr

Mk

KS

IM

II

PLYM400A

PED171S1

Fields:

Ship Date

Ship date for which loads are to be reviewed.

Route

Enter the route for which loads are to be reviewed.

Carrier

Enter the carrier for which loads are to be reviewed.

Origin

Enter the origin or start point for which loads are to be reviewed.

Destination

Enter the destination or end point for which loads are to be reviewed

Load Number

Enter a particular load reference which is to be reviewed.

Functions:

F16

Select loads.

 *Note: Function key displays load headers that conform to the selection criteria irrespective of*

their status.



Note: If only one load is found, selection is bypassed and the load reference is returned to the Screen.



Press **Enter** to display the Cancel Load Details Screen.

Cancel Load Details Screen



This screen is accessed by entering a subset of details on the Cancel Load Selection Screen, displays load header information for review / confirmation.

TP470B	HW - Handy Wholesalers Ltd	User GALBRAIJ	26/10/95
	Handy Wholesaler Depot 001		16:50:52
Cancel Load			
Load number	H11	Load status	Pending
Bulk pick load ..	0 (0/1)		
Ship date	30/10/95	Ship time	1:30
Route	NHLT01	Northampton to Luton Route 01	
Carrier	MAERS	Maers Haulage	
Vehicle type	1TON	1 Ton with lifting Tailgate	
Origin	MIDC	Destination	MIDW
Vehicle		Seal number	
Driver		Crew	
Distance	.00	Skeleton load	0
Trip number		Agent contact	
Exclusive load ..	0	Payment method	
Confirmation	0	P & L override	
Bill required ...	1	Rating status	1 0
Bill format	01	Rate method	04
Copies	2	Rate code	JK9VT
F3=Exit F8=Update F12=Previous F20=Consignee details F21=Text 01-02 SP ML KS IM II PLYM400A PED171S1			

Functions:

F20

Display consignee details.

F21

Display load external text.



Press **F8=Update** to cancel load details. This displays the Cancel Load Cancellation Reason Window prior to update.

Cancel Load Cancellation Reason Window (F8)



If you have pressed **F8=Update** to cancel a load, the system will display this screen.

TP4708	HW - Handy Wholesalers Ltd	User GALBRAIJ	26/10/95
	Handy Wholesaler Depot 001		16:50:52
Cancel Load			
Load number	H11	Load status	Pending
Bulk pick load ..	0 (0/1)		
Ship date	30/10/95	Ship time	1:30
Route	NHLT01	Northampton to Luton Route 01	
Carrier	MAERS	Maers Haulage	
Vehicle type	1TON	1 Ton with lifting Tailgate	
Origin	MIDC	Destination	MIDW
Vehicle		Seal number	
Driver	Cancellation Reason		
Distance	Reason code.....?.. L		
Trip number			
Exclusive load ..			
Confirmation			
Bill required ...	F4=Prompt	F8=Update	F12=Previous
Bill format	01	Rate method	04
Copies	2	Rate code	JK9VT
F3=Exit F8=Update F12=Previous F20=Consignee details			
F21=Text			
16-46	Sr	Mk	KS IM II PLYM400A PED171S1

Fields:

Reason Code

Enter the reason for cancellation. Reason codes are defined to the Inventory descriptions file under a major type 'RSNC'.



Press **F8=Update** to cancel load details and place all orders back onto the Cancel Load Load Build Screen as outstanding requirements.