

-
-
-
-
-

Chapter 3

Inventory Stock Counting



Stock Counting Introduction

You can use Inventory Management for stock counting. Counts may be:

- Time based.
- Manually requested.

Time Based

For cycle counting or perpetual inventory the system can suggest WHAT to count and WHEN. The prime definition is an item classification of A, B, C or Z.

- A - High value and high usage or both.
- B - Medium value and medium usage or both.
- C - Low value and low usage both.
- Z - Ignore these items in a class/date control count.

Stockrooms have a count objective per year, per ABC classification. With the definition of a number of working days, the system calculates time intervals so that you can meet the count objectives.

Manual Request

You can select items for counting at any time, by using group ranges (for example Major, Minor, and so on).

Warehousing Stock Counting

The primary options of Warehousing are to record item locations and quantities and item movements. This incorporates a stock counting option which provides assistance with the control, documentation, reconciliation and adjustment of stock counting.

The Warehousing Stock Count options apply to the default warehouse only. You can change a user's default warehouse using the option Authorise Users To Warehouse.

Physical Warehouse Areas/Locations

You can request stock counts by a range of locations within a given area. In addition, you can select specific location types with the omission of void locations.

Stock Counting Steps

Count Creation

ABC classification or Manual range. The system provides a series of recommendations of what to count, but does not record details (lot/batch/serial). You can print count sheets at this stage but this will bypass the review stage and the count has an immediate status of outstanding.

Review Recommendations

If you have produced a stock count then you can review those recommendations.

Maintain the count

Once you have created a count. you can add to, or delete items from, the count list.

Print Count Sheets

The system records the computer stock figure. The count is now of outstanding status. The count sheets are produced, which may cover a number of action lists. A reprint option is also available.

Count Entry

Count figures are recorded. You can add new items to the count.

Reconciliation With Or Without Update

The system compares the counted figure with the recorded computer stock figure. Variances are reported by quantity and value, and designated as errors if outside defined tolerance limits.

With Update - Automatic adjustments can be made with appropriate Inventory movements created.



Note: If DRP or MRP are in use, net change triggers are written.

Count Profile Maintenance



1/INS
1/WH

Use this option to set up profiles that control the range of items you want to count, and when.

See the Company Profile - Stock Weeks Matrix Maintenance and Stockroom Details within Inventory Management to define additional information regarding the ABC classifications.

Count Profile Maintenance Stockroom Selection Screen

 Select Maintenance.

Use this screen to enter the selection criteria of Count Profile Maintenance.

IN106	Z1 - Demonstration Company	User SP1	26/08/94 9:23:46
Stock Count Profile Maintenance			
Stockroom?.. <u>01</u>			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter a stockroom code using up to two alphanumeric characters. You must define the stockroom to the Inventory company profile.

 Press **Enter** to display the Count Profile Maintenance Details screen

Count Profile Maintenance Details Screen



To display this screen select a stockroom on the Count Profile Maintenance Selection screen and press **Enter**.

Use this screen to enter counting criteria for the stockroom or warehouse.

IN106		NR - Neil Radford and Co. Ltd		User GBJBA1MS		22/07/96	
						11:37:49	
Stock Count Profile Maintenance							
Stockroom W1				Neil's Warehouse 1			
Last count number							
Overdue days 1							
Time fence days 1							
View quantity on count . 0				0=No 1=Print 2=Panel 3=Both			
Count by class 0				0=No,1=Yes			
Tolerances:							
Percentage (-ve)				_____			
Percentage (+ve)				_____			
Value (-ve)				_____			
Value (+ve)				_____			
F3=Exit		F8=Update		F12=Previous			
08-27		SF		MW		KS	
IM		II		KENB20A		PET087S1	

Fields:

Last Count Number

Last count number used within the stockroom or warehouse. This is automatically assigned during count creation.

Overdue Days

Specify the number of days after the due date of a count before the system will consider it overdue. When the count becomes overdue, the count initialisation date on the Recommended Count Selection screen is highlighted in red rather than yellow.

Time Fence Days

Specify the number of days of ABC cycle counting you wish to produce counts for. When you set the time fence days to zero then the count will only include items due to be counted on or before that day. When you set it to greater than zero then extra counts are created, one for each day into the future. These will only include items that are due to be counted on that day.

View Quantity On Count

This defines whether recorded or computer stock figures are visible to the user after printing of count sheets. Enter one of the following:

0 - No visibility.

- 1 - Printed. Computer stocks are printed on count sheets only.
- 2 - Screens. Computer stocks are displayed on count entry screens only.
- 3 - Both. Computer stocks are printed and displayed on screens.

Count By Class

Define whether you can count by class for the stockroom. Enter 1 to switch this on, you *must* define tolerances for each class, that is A, B and C.

You cannot switch Count By Class off whilst outstanding counts exist for the stockroom.

Tolerances:

Only shortfalls or excesses greater than the figures entered here are considered as count errors.

Percentage (-ve)

Maximum percentage tolerance for stock shortage. A shortfall greater than this tolerance is considered a count error at reconciliation.

Percentage error is calculated as follows:

$$\frac{\text{Counted Quantity} - \text{Computer Quantity} \times 100}{\text{Computer Quantity}}$$

Percentage (+ve)

Maximum percentage tolerance for stock excess. An excess greater than this tolerance is considered a count error at reconciliation.

Percentage error is calculated as follows:

$$\frac{\text{Counted Quantity} - \text{Computer Quantity} \times 100}{\text{Computer Quantity}}$$

Value (-ve)

Maximum value tolerance for stock shortage. A shortfall greater than this tolerance is considered a count error at reconciliation.

Value errors are calculated according to the costing method of the item as follows:

$$(\text{Counted Quantity} - \text{Computer Quantity}) \times \text{COST}$$

Where COST = Standard or Latest or Average according to costing method of item.

Discrepancies for FIFO costing items are valued at latest cost.

Value (+ve)

Maximum value tolerance for stock excess. An excess greater than this tolerance is considered a count error at reconciliation.

Value errors are calculated according to the costing method of the item as follows:

$$(\text{Counted Quantity} - \text{Computer Quantity}) \times \text{COST}$$

Where COST = Standard or Latest or Average according to costing method of item.

Discrepancies for FIFO costing items are valued at latest cost.



Press **Enter**. The system refreshes the screen and displays the following additional fields, for Class B and Class C.

Count Profile Maintenance Details Screen 2



To display this screen define the stock counting criteria on the first Count Profile Maintenance Details screen and press **Enter**.

Use this screen to view the details for the Count Profile Maintenance selection criteria previously entered.

IN106		NR - Neil Radford and Co. Ltd		User GBJBA1MS		22/07/96	
						11:45:44	
Stock Count Profile Maintenance							
Stockroom		W1		Neil's Warehouse 1			
Last count number							
Overdue days		2					
Time fence days		1					
View quantity on count ..		3					
Count by class		1					
Number of days/year		365					
		Class A		Class B		Class C	
Number of counts/year ..		_____		_____		_____	
Maximum items/count		_____		_____		_____	
Tolerances:							
Percentage (-ve)		_____		_____		_____	
Percentage (+ve)		_____		_____		_____	
Value (-ve)		.00		.00		.00	
Value (+ve)		.00		.00		.00	
F3=Exit		F8=Update		F12=Previous			
08-27		SF		MW		KS	
				IM		II	
				KENB20A		PET007S1	

Fields:

Number Of Days/Year

Number of days per year together with the count objective per class enables the calculation of next due count date for each item within the stockroom (based on the class of the item and the last counted date).

For example, if working days/year is 200 and the count objective for A class items is 20 (each item is required to have a stock check 20 times per working year) then each item should be counted every 200/20 - 10 working days.

Number Of Counts/Year

Count objective for A, B and C class items.

Maximum Items Count

Maximum items to count for A, B and C class items. This indicates the maximum number of items you want to include on an individual count sheet.

Tolerances:

Percentage Tolerance (-ve)

Maximum percentage tolerance for stock shortage. A shortfall greater than this tolerance is considered a count error at reconciliation.

Percentage error is calculated as follows:

Counted Quantity - Computer Quantity X 100

Computer Quantity

Percentage Tolerance (+ve)

Maximum percentage tolerance for stock excess. An excess greater than this tolerance is considered a count error at reconciliation.

Percentage error is calculated as follows:

Counted Quantity - Computer Quantity X 100

Computer Quantity

Value Tolerance (-ve)

Maximum value tolerance for stock shortage. A shortfall greater than this tolerance is considered a count error at reconciliation.

Value errors are calculated according to the costing method of the item as follows:

(Counted Quantity - Computer Quantity) X Cost.

Where Cost = Standard or Latest or Average according to costing method of item.

Discrepancies for FIFO costed items are valued at latest cost.

Value Tolerance (+ve)

Maximum value tolerance for stock excess. An excess greater than this tolerance is considered a count error at reconciliation.

Value errors are calculated according to the costing method of the item as follows:

(Counted Quantity - Computer Quantity) X Cost.

Where Cost = Standard or Latest or Average according to costing method of item.

Discrepancies for FIFO costed items are valued at latest cost.

Count Profile Enquiry



2/INS
2/WHS



Select Enquiry.

Use this option to view the stockroom count profile.



To display this screen enter a Stockroom on the Count Profile Enquiry Selection screen and press **Enter**.

IN107	Z1 - UK Demonstration Company	User GBJBAMSA	1/06/98 11:58:51
Stock Count Profile Enquiry			
Stockroom	01	Central Stockroom	
Last count number	10		
Overdue days	2		
Time fence days	1		
View quantity on count .	3	0=No 1=Print 2=Panel 3=Both	
Count by class	1	0=No,1=Yes	
Number of days/year	257		
Number of counts/year	Class A 6	Class B 4	Class C 2
Maximum items/count	100	80	40
Tolerances:			
Percentage (-ve)	5.00	10.00	20.00
Percentage (+ve)	5.00	10.00	20.00
Value (-ve)	.00	.00	.00
Value (+ve)	.00	.00	.00
F3=Exit F12=Previous			



Note: You cannot change anything at this point.

Regenerate ABC Classifications



11/INS
11/WHs

Use this option to reclassify items within a stockroom based on their average usage and cost in relation to the stockroom cost/usage matrix. Once reclassified, the next count date for each item in the stockroom is recalculated based on the last count date and the criteria defined for the stockroom count profile.

This option is prompted at Period End processing within Inventory when average usage for item/stockroom profiles are recalculated (Week or Month End depending on usage cycle of Inventory company). Alternatively, you can run it at any time by selecting Regenerate ABC Classifications.

Use this option to reassign classifications and next count dates to items. You may need to do this if a stockroom matrix or stockroom count profile has been changed.

You can view the ABC classification of items in the item/stockroom enquiry.



If you are not using Warehousing then select a stockroom and then **F8=Submit**.

Or, if you are using Warehousing, select **F8=Submit**. The system assumes that processing is within your default warehouse.

ABC Recommendations



21/INS
21/WHS

Use this option to create counts based on the next due for count date defined for each item within the stockroom or warehouse.

Counts are produced for all items due for count before or on the count recommendation date entered on the screen.

Additional counts are produced for each day after the entered date up to the number of time fence days specified. These counts contain items that are due for count on those days only and provide a forward looking view of future work loads.

Selection of items is also based on the maximum number of items to count per class as specified on the stockroom count profile.

You can print count sheets immediately, as a result they go straight to a status of outstanding. Alternatively, you can include a review stage.

The count sheet contains a list of items, the quantity of the items and the type. The type can be as follows:

- Type 1 - Class/Date Control. For more information see Create Count By Class/Date Control screen.
- Type 2 - Manual Range. For more information see Manual Range.
- Type 3 - Warehouse Location. For more information see Warehousing.
- Type 4 - Catchweight. This means the item has a zero primary value and a non-zero secondary value. You investigate this item to find out if any of this item is still available. As you can receive more of the item between printing of the count sheet and completing the stock take, it is strongly recommended that you investigate and correct these type 4 items first.



Note: Before creating an ABC count you should take the option to regenerate ABC classifications.

Create Count By Class/Date Selection Screen



Select ABC Recommendations.



Note: If you are doing a stock count for Warehousing, this screen is not displayed.

Fields:

Stockroom Code

Enter a stockroom code.



Press **Enter** to display the Create Count By Class/Date Control screen.

Create Count By Class/Date Control Screen



To display this screen select a stockroom on the Create Count By Class/Date Selection and press **Enter**.



Note: If you are doing a stock count for Warehousing, this screen is displayed when you select ABC Recommendations (Create Count).

IN116B	Z1 - Demonstration Company	User SP1	26/08/94 9:24:59
Create Count by Class/Date Control			
Stockroom	01	Central Stockroom	
Number of days	<u>2</u>	from	<u>26/08/94</u>
Print count sheets	<u>0</u>	0=No,1=Yes	
No of instructions/list	<u>0</u>		
F3=Exit F8=Submit F12=Previous			

Fields:

Number Of Days

This time fence defines the number of days after the date of recommendation (displayed to the right of the screens), which are reviewed separately for count creation. Where possible a daily count is produced detailing the items that are due for count on the specific day, thus giving a view of future counts and workloads.

From...Date

The start date from which count creation begins. The default is today's date.

Print Count Sheets

Enter one of the following:

0 - Review recommendations through Maintain Count Recommendations before printing.

1 - Print immediately after generating recommendations.



Note: If you select to print, the count becomes outstanding immediately and the option to review before printing is bypassed.

Number Of Instructions Per List

Enter the value of the maximum number of items or location you want to print on an action list. If Warehousing is attached then the value defaults to the value defined for the Warehouse List Profile for count lists. An entry of zero ensures that all instructions for the count appear on one list only.

Organise Count By

This field is only displayed for the Warehousing stockcount.

Enter one of the following:

1 - Warehouse. As the count only relates to your default warehouse, create a new list when the number of location or item details exceeds the value set for No of instructions/list.

2 - Area. Create a separate count list for each change of area code within the warehouse.

3 - Access to dimension 1. Create a separate count list for each change of access to dimension 1. If for example if you set up Aisle to be the first dimension in the warehouse, then one Action list per Aisle is produced.

For example, if Organise Count By is set to 2 (Area) then create a new list for each change in area code. There may be several lists per area if the number of location or item details to be checked exceeds the value set for Number Of Instructions/List.

Sequence Count By

This field is only displayed for the Warehousing stock count.

Enter one of the following:

1 - Item. The actions on the list are ordered by item.

2 - Location. The actions on the list are ordered by location code.

It is possible that after running the Create Count By ABC Recommendation option no counts are actually produced. This situation may arise for one of two reasons:

Firstly, on the Count Profile you specify how often each item classification (A, B or C) should be counted. If the Number Of Counts Per Year field is set to count items relatively infrequently and all items have recently been counted, then no items may be due to be counted, and hence no count recommendations are produced.

Secondly, items that are currently being counted cannot be included on other count lists, whether active or recommended. Hence any items appearing on manually requested counts lists, at either a summary or detail level, do not appear on a count list created by ABC Recommendation.



Select **F8=Submit** to submit count creation.

Manual Range



22/INS
22/WHs

You can select items for counting at any time. These are flagged as unplanned counts.

You can create counts for one or more stockrooms based on item range selection or item attribute selection.

You can enter a single stockroom or range of stockrooms in addition to a single selection or range of one of the following item attributes as defined for the item:

- Item number.
- Item group (major and minor).
- Item type.
- Item class.
- Count class (A, B, C or Z).

You can print counts immediately, or review them before printing.

Create Count by Manual Range Detail Screen



Select Manual Range.

Use this screen to select the items to be counted. You can use some or all the selection criteria.

For each search criterion, if you only enter a value in the From field, or if both the From and the To fields are the same, entries must exist on the item master file. However if you define a range, the From and To entries need not exist on the item master file. If you only enter the From value and leave the To value blank, the To fields default to the From field.

IN120	Z1 - GB Demonstration Company	User GBJBAMS	15/01/96 17:13:06
Create Count by Item Selection			
Selection criteria	Range from	Range to	
Stockroom?..	—	—	
AND			
Item?..	—	—	
OR			
Item group major/minor..?..	— —	— —	
OR			
Item type?..	—	—	
OR			
Item class?..	—	—	
OR			
Count class	—	—	
Count date	15/01/96		
Print count sheets	@ 0=No,1=Yes	No of instructions/list.... @	
F3=Exit F4=Prompt F5=Refresh F8=Submit			
07-30	SA	MA	KS IM II KENB20A PET166S2

Fields:

Stockroom

Enter the stockroom code whose items are to be selected for count.

If you enter a single stockroom, it must exist as a stockroom defined to the company. If, however, you enter a range, the From and To stockrooms which are used to define the range need not exist on the stockrooms master file, except when they are the same value.

If you are doing a stock count for Warehousing, this field does not display.

Item

This is the code which serves to uniquely identify an item.

If you enter a single item, then it must exist on the item master file. If, however, you enter a range, the From and To items which are used to define the range need not exist on the item master file, except when they are the same value.

Item Group Major

Enter an item group major code as defined to the descriptions file against the major type PGMJ.

If you enter a single major/minor combination, it must exist on the item master file. However, if you enter a range, the From and To major or minor groups which are used to define the range need not exist on the item master file, except when they are the same value.

Item Group Minor

This is the item group minor as defined to the descriptions file against the major type PGMN.

If you enter a single major/minor combination, it must exist on the item master file.

However, if you enter a range, the From and To major/minor groups which are used to define the range need not exist on the item master file, except when they are the same value.

Item Type

This is the item type as defined to the descriptions file against the major type PTYP.

If enter a single item type, then it must exist on the item master file. However, if you enter a range, the From and To item types which are used to define the range need not exist on the item master file, except when they are the same value.

Item Class

This is the item class as defined to the descriptions file against the major type PCLS.

If you enter a single item type, then it must exist on the item master file. However, if you enter a range, the From and To item classes which are used to define the range need not exist on the item master file, except when they are the same value.

Count Class

This is the classification of items within a given stockroom by a combination of their usage and value. They are then categorised by this into classes A, B and C. Items with the highest usage and value are normally classified as A and receive the most attention. Class B receives less attention, while class C with the lowest usage and value combination receive the least attention.

This means that effort is saved by relaxing controls on low value, low usage items which allows for more control of the higher value, higher usage items.

Valid classes are A, B, C and Z. The Z class excludes items From count requests by ABC classification.

Count Date

Every count is associated with a date. Enter the date in this field.

Print Count Sheets

Enter one of the following:

0 - Review recommendations through Maintain Count Recommendations before printing.

1 - Print immediately after generating recommendations.



Note: If you select to print, the count becomes outstanding immediately and the option to review

prior to printing is bypassed.

Number Of Instructions Per List

Determine the maximum number of item or location details to print on an action list.

If Warehousing is attached then the value defaults to the value defined for the Warehouse List Profile for count lists.

If you enter a zero all instructions for the count appear on one list only.

Organise Count By

This field is only displayed for the Warehousing stockcount.

Enter one of the following:

1 - Warehouse. As the count only relates to your default warehouse, create a new list when the number of location or item details exceeds the value set for No of instructions/list.

2 - Area. Create a separate count list for each change of area code within the warehouse.

3 - Access to dimension 1. Create a separate count list for each change of access to dimension 1. If for example Aisle is set up to be the first dimension in the warehouse, then one Action list per Aisle is produced.

For example, if Organise count by is set to 2, Area, then create a new list for each change in area code. There may be several lists per area if the number of location or item details to be checked exceeds the value set for No of instructions/list.

Sequence Count By

This field is only displayed for the Warehousing stock count.

Enter one of the following:

1 - Item. The actions on the list are ordered by item.

2 - Location. The actions on the list are ordered by location code.



Note: If you wish the to entry to be the same as the From entry, leave the to entry blank.



Note: A blank range selection for stockrooms defaults to all stockrooms.



Note: If no other selection criteria is specified, all items are selected within the specified stockroom range.

The count now follows exactly the same steps as the class/date count.



Select **F8=Submit** to submit the process.

Create Count by Warehouse Location



23/WH5



Note: This option is only available, if you have Warehousing attached.

You can create count for the default warehouse by location within a defined area.

Use a range of criteria to select the locations within the area:

- Range selected by dimension.
- Status. Only active locations or all locations.
- Location type.

You can set a maximum number of locations to be selected to ensure that the count lists do not become too large.

You can print counts or create recommended counts to review prior to print.

Create Count By Warehouse Location Area Selection Screen



Select Create Count By Warehouse

Use this screen to select the area containing the required locations, and specify the date associated with the count.

IN125	Z1 - Demonstration Company	User SP1	01/09/94
	Central Warehouse		12:00:00
Create Count by Warehouse Location			
Area	MS		
Count date	010994		
F3=Exit F4=Prompt			

Fields:

Area

Enter the warehouse area to be targeted for the count.

Count Date

Enter the date associated with the count recommendation.



Press **Enter** to display the Create Count by Warehouse Location Detail screen

Create Count By Warehouse Location Detail Screen



To display this screen select an area and count date on the Create Count by Warehouse Location Selection screen and press **Enter**.

Use this screen to select the locations within the chosen area for stock counting.

IN125	Z1 - Demonstration Company Central Warehouse	User SP1	01/09/94 12:00:00
Create Count by Warehouse Location			
Area	MS		
Count date	1/09/94		
Location Ranges :	From (?)	To (?)	
Aisle	A	B	
Bay			
Row			
Location status	1	0=All 1=Active only	
Location type	RA		
Maximum number of locns ..	300		
Print count sheets	0	0=No,1=Yes	
No of instructions/list ..	0		
Organise count by	1	1=Warehouse 2=Area 3=Access to dimension 1	
Sequence count by	2	1=Item 2=Location	
F3=Exit F4=Prompt F5=Refresh F8=Submit F12=Previous F16=No. of locns			

Fields:

Location Ranges:

You can leave both the From and To entry fields blank to select the entire range of dimension codes for the particular dimension.

Aisle

Enter the target range of dimension codes for count creation within the area.

Bay

Enter the target range of dimension codes for count creation within the area.

Row

Enter the target range of dimension codes for count creation within the area.

Location Status

Enter the location status:

0 - All. Select all locations defined by the dimension range.

1 - Active only. Ignore void locations (generated via the warehouse map), and select those locations defined as active from the dimension range.

Location Type

You can restrict the target locations for count by type. You must define the location type you enter to warehouse Location types.

If left blank, all location types found for the dimension range are selected.

Maximum Number Of Locns

Maximum number of target locations for the count.

This defaults to the entry held on the Inventory descriptions file under major type WHNL, minor type MAX.

It is strongly recommended that this value is maintained with a suitable to guard against the entry of dimension ranges that targets an inappropriately large number of locations.

Print Count Sheets

Enter one of the following:

0 - Review recommendations through Maintain Count Recommendations before printing.

1 - Print immediately after generating recommendations.



Note: If you select to print, the count becomes outstanding immediately and the option to review before printing is bypassed.

No Of Instructions/List

If you set Print count sheets to 1 this determines the maximum number of item or location details to print on an action list. This value defaults to the value defined in the Warehouse list profile for count lists.

Enter 0 to indicate that a new list should not be initiated based the number of item or location details. New lists can however be initiated by the Organise count by option.

Organise Count By

If you set Print count sheets to 1 this signals the start of a new list when the chosen option changes.

For example if Organise count by is set to 2, Area, a new list is initiated for each change in area code. There may be several lists per area if the number of location or item details to be checked exceeds the value set for No of instructions/list.

1 - Warehouse. As the count only relates to your default warehouse, a new list is only produced when the number of location or item details exceeds the value set for No of instructions/list.

2 - Area. A separate count list is initiated for each change of area code within the warehouse.

3 - Access to dimension 1. A separate count list is initiated for each change of access to dimension 1. The access points are set up in the Warehousing maintenance and are used for example to produce one action list per Aisle in the warehouse, if Aisle is set up to be the first dimension.

Sequence Count By

Determines the order of the stock count instructions on the action list.

1 - Item. The actions on the list are ordered by item.

2 - Location. The actions on the list are ordered by location code.

Functions:

F16

No. Of Locns. Review how many locations are targeted for count based on the entered dimension range.



*Note: It is recommended that **F16=No of Locations** is used to guard against producing counts over a large number of locations.*



Select **F8=Submit** to submit the count request.

Maintain Count

1... 31/INS
2... 31/WHs

You can review recommended counts before printing if you have not taken the option to print count sheets when you requested the count.

You can add or delete summary recommendations, that is, a request to count all balances for an item. In addition you can request detail recommendations, that is, specific lots, batches or serial numbers for count. You can delete counts entirely and all associated items taken off count.

Any additions are considered Unplanned requests, and you must enter a reason code for these.

Maintain Count Selection Screen



Select Maintain Count.

Use this screen to select the Stockroom and Stock Count that you want to maintain.

IN129A
Z1 - Demonstration Company
User SP1
5/09/94
12:30:26

Maintain Count

Stockroom?.. 01

Count number?.. 0

Recommended Count Selection

Sel	Central Warehouse Count number	Date and time count initialised	Items to count
	3	26/08/94 10:40:56	1
<u>I</u>	4	5/09/94 12:28:01	9

1=Select Position to

F12=Previous

F3=Exit
F4=Prompt

Fields:

Stockroom Code

Enter the stockroom code.



Note: This field does not display, if you are stock counting for Warehousing.

Count Number

Enter the count number.



Press **Enter** to display the Maintain Count Details screen.

Maintain Count Details Screen



To display this screen, select a stockroom and count on the Maintain Count Selection screen and press **Enter**.

Use this screen to add or delete summary or detail item recommendations. The stockroom, count number and the number of items or lots to count are displayed at the top of the screen. Detail recommendations are a request to count specific lot, batch or serial numbers. You can only review recommended counts.

IN129B	Z1 - Demonstration Company	User SP1	5/09/94 12:32:06
Maintain Count			
Stockroom	01	Item summaries to count	8
Count number	4	Item details to count	1
Create date/time	5/09/94 12:28:01	Item summaries cancelled	1
		More:	
Item	Lot	Reason	
- 5011		Planned Count	
- 5013	B002	Unplanned Request	
- 5014		Planned Count	
- 5015		Planned Count	
- 5016		Planned Count	
- 5017		Planned Count	
- 5018		Planned Count	
- 5019		Planned Count	
- 5020		Planned Count	
			Position to item .. _____
4=Delete			
F3=Exit F5=Refresh F8=Update F9=Add F11=Delete			
F12=Previous			

Fields:

Untitled

Select. Enter 4 to delete count recommendation for a particular line and select **F8=Update**. The count recommendation is no longer included in the count and the application immediately returns to the count selection screen.

Position To Item

If the list extends over a single screen, enter the item reference number or the first few characters of an item in order to position the count list to the required point.

Functions:

F9

Add. To add new items to the count.

Addition Window (F9)



To display this window select **F9=Add** on the Maintain Count Details screen.

Use this window to add a new item to the selected Count.

IN129B		Z1 - Demonstration Company		User SP1		5/09/94 12:31:54	
Maintain Count							
Stockroom		01		Item summaries to count		8	
Count number		4		Item details to count		0	
Create date/time		5/09/94 12:28:01		Item summaries cancelled		1	
				More:			
Item	Lot	Reason					
- 5011		Planned Count					
- 5014		Planned Count					
- 5015		Planned Count					
- 5016		Planned Count					
- 5017		Planned Count					
- 5018		P					
- 5019		P					
- 5020		P					
		Addition Item?.. 5013 Lot?.. B002 Reason code ?.. UN F4=Prompt F12=Previous					
		Position to item ..					
4=Delete F3=Exit F5=Refresh F8=Update F9=Add F11=Delete F12=Previous							

Fields:

Item

Item code. The item must exist on the Inventory item master file.

Location

Only displayed for Warehouse stock count. The location must exist within the current warehouse.



Note: You only need to enter the location (and any further detail for the item balance) if you are making a detail addition, in other words a specific warehouse balance for the item is being requested for count.

Lot

The lot, batch or serial number associated with a lot controlled item.

Rotation

Only displayed for Warehouse stock count. The rotation date associated with a balance for a date controlled item.

Pack

Only displayed for Warehouse stock count. The pack type associated with an item. You must define the pack Warehousing you must also associate the pack with the item in the item/warehouse profile.

Label

Only displayed for Warehouse stock count. The label number associated with a label-controlled pack type.

Reason Code

The reason code must be defined to the descriptions file against the major type CTRE and must be of an unplanned nature



Note: You cannot use the reserved code of #1 representing a Planned request for an item originating from an initial count request.



To delete the entire count, select **F11=Delete** twice.



Warning: You must delete summary recommendations before you can add a detail recommendation for an item.



Warning: Lot controlled items are only shown at summary level. You can specify individual lots by pressing F9=Add.



Note: If a count exists for a particular item at summary level, a detailed count recommendation cannot be generated for the same item, and vice versa.



Select **F8=Update** to update all item additions and deletions.

Location Based Count Recommendations Detail Screen



To display this screen select a warehouse and date on the Location Based Count Recommendations Selection screen and press **Enter**.



Note: This is only available, if you are doing a Warehousing stock count.

Use this screen to add location summary or detail recommendations to the count.

IN131	Z1 - Demonstration Company Central Warehouse	User SP1	01/09/94 12:00:00
Maintain Count			
Count number	4	Location summaries to count .	15
		Location details to count ...	0
Create date/time	01/09/94 11:00:00	Location summaries cancelled.	0
		More: +	
Location	Item	Lot	Rotation Pack Reason
- AA1			#1
- AA2			#1
- AA3			#1
- AA4			#1
- AA5			#1
- AB1			#1
- AB2			#1
- AB3			#1
- AB4			#1
- AB5			#1
		Position to location ...	
4=Delete			
F3=Exit	F5=Refresh	F8=Update	F9=Add
F12=Previous	F15=Labels		F11=Delete

Fields:

Untitled

Select. Enter 4 to delete a location recommendation.

This takes effect when you select **F8=Update**.

Position To Location

Position to location. Enter the first few characters of a location code to position the details to the required point.



Note: You must delete summary recommendations before you can add detailed recommendations for a location.

Functions:

F9

Add. To add recommendations.

F15

Labels. To display label numbers for label controlled pack types.

Count Size Warning Window

- ➡ This screen displays when the number of items specified for any of the classifications exceeds the maximum number of items per count sheet as maintained against the stockroom count profile on update for count request by ABC classification.

This situation can arise where you have added unplanned counts to the count list.

IN129B	Z1 - Demonstration Company	User SP1	05/09/94 12:36:13
Maintain Count			
Stockroom	01	Item summaries to count	8
Count number	4	Item details to count	1
Create date/time	5/09/94 12:28:01	Item summaries cancelled	1
		More:	
Item	Lot	Reason	Class
- 5011		Planned Count	B
- 5013	B002	Unplanned Request	B
- 5014			
- 5015			
- 5016			
- 5017			
- 5018			
- 5019			
- 5020			

Count Size Warning

Number of class A items in count 2

Maximum class A items specified 10

Number of class B items in count 6

Maximum class B items specified 5

Number of class C items in count 1

Maximum class C items specified 20

F12=Previous

4=Delete
F3=Exit F5=Refresh F8=Update F9=Add F11=Delete
F12=Previous

- ➡ Select **F12=Previous** to amend the current count.
- ➡ Press **Enter** to accept the count with the excess items.

Enter Count Details

1... 32/INS
2... 32/WHs

You enter counted details on a list by list basis. You can add, change or delete details until the list is recorded as complete. You can delete lists entirely and take all associated items off count (unless item details span a number of lists). You can only add item details if the item already exists as on count in this particular count. The system considers any additions Override details so you must enter an appropriate reason code.

It is recommended that you do not flag the list as complete until you have reviewed the reconciled details, as you cannot maintain a list recorded as complete.

Enter Count Selection Screen



Select Enter Count Details.

Use this screen to select the Stockroom, Count number and List number required to enter the count details.

IN133A		Z1 - Demonstration Company		User SP1		5/09/94 12:33:15	
Enter Count							
Stockroom		01					
Count number		4					
List number							

Select List Number

Central Warehouse

Count No..... 4

More:

S Number	S Number
1	4
-	5
-	6
-	7

1=Select
Position to...
F12=Previous

F3=Exit F4=Prompt

Fields:

Stockroom

Enter the stockroom code. This field is not displayed if you are doing a Warehousing stockcount.

Count Number

Enter the count number.

List Number

Enter the list number.



Press **Enter** to display the Enter Count Details screen.

Enter Count Details Screen



To display this screen select a Stockroom, Stock Count and List and press **Enter** on the Maintain Count Selection screen.

Use this screen to enter counted quantities.

IN133B		Z1 - Demonstration Company		User SPI		5/09/94 12:33:59	
Enter Count							
Stockroom		01		Item summaries to count		8	
Count number		4		Item details to count		1	
List number		4		Item summaries cancelled		1	
Create date/time		5/09/94 12:28:01		More:			
Item	Lot	Reason	Recorded qty	Entered qty			
- 5011		#1	512.000	512.000			
- 5013	B002	UN	719.000	.000			
- 5014	LP004	#1	138.000	138.000			
- 5014	L001	#1	575.000	575.000			
I 5015	LP054	#1	159.000	.000			
- 5015	L002	#1	625.000	.000			
			Position to item ..				
1=Select 2=Lot header 4=Delete							
F3=Exit		F5=Refresh		F8=Update		F9=Add	
F12=Previous						F11=Delete	

Fields:

Untitled

Select. Enter one of the following

- 1 - To enter or amend detail item count quantities. Press **Enter**, to display the Amendment Window that shows current information available for amendment.
- 2 - To display the Lot Header screen for a detail count line that appears on this Enter Count screen. See Lot, Grade, Potency for more details on the resulting window.
- 4 - Delete. To display the third Enter Count screen.

Entered Qty

Enter the counted quantity associated with the item record. Enter the in the issue unit of measure defined for the item within the Inventory.

Position To Item

Enter an item code you want displayed first.

Functions:

F9

Add. You can only add item details if the item already exists as on count in this particular count. Typically, this is where different lots of an item are found that were not on the original count sheets. If the item is lot controlled, the Lot Reference

Maintenance window is automatically presented and must be completed. Additions are considered as overrides and you must provide a reason code.



Select an option and press **Enter**.

Enter Count Amendment Window (Option 1)



To display this window select an item with option 1 on the Enter Count Details screen and press **Enter**.

The Amendment window displays current information available for amendment. You can enter the quantity directly into the column marked Entered Qty beside the appropriate item count line.

IN133B		Z1 - Demonstration Company		User SP1	5/09/94 12:33:59
Enter Count					
Stockroom	01	Item summaries to count	8		
Count number	4	Item details to count	1		
List number	4	Item summaries cancelled	1		
Create date/time	5/09/94 12:28:01	More:			
Item	Lot	Reason	Recorded qty	Entered qty	
- 5011		#1	512.000	512.000	
- 5013	B0 02	UN	719.000	.000	
- 5014	LP004	#1	138.000	138.000	
- 5014	L0 01				
- 5015	LP054				
- 5015	L0 02				

Amendment		
Item	5015	00
Lot	LP054	00
Reason	#1	
Recorded qty ...		159.000
Entered qty	160	
F12=Previous		

1=Select 2=Lot header 4=Delete
 F3=Exit F5=Refresh F8=Update F9=Add F11=Delete
 F12=Previous

Fields:

Item

Enter an item code.

Lot

Enter a lot number.

Reason

Enter a reason code.

Recorded Quantity

Enter a recorded quantity.

Entered Quantity

Enter the actual quantity for the item.



Press **F12=Previous** to return to the Enter Count Details screen with the details amended.

Enter Count Delete (Option 4)



To display this screen select an item with option 4 on the Enter Count Details screen and press **Enter**.

Use this screen to delete a selected item from the count.

```

IN133B      Distribution V3 -> V3 Financials      User GBJBAMV1      16/11/95
                                                    15:43:59

Enter Count

Stockroom ..... #P      Item summaries to count ..... 1
Count number ..... 5      Item details to count ..... 0
List number ..... 4      Item summaries cancelled ..... 0
Create date/time ..... 23/10/95 14:59:42      More:
Item      Lot      Reason      Recorded qty      Entered qty
4 ROB      Lot      #1      25000.000      .000

1=Select  2=Lot header  4=Delete
F3=Exit    F5=Refresh    F8=Update    F9=Add      F11=Delete
F12=Previous
          10-02      SA      MW      KS      IM      II  KENB20A  PET129S1
  
```

Fields:

Entered Quantity

Enter the counted quantity associated with the item record. You must detail the quantity in the issue unit of measure defined for the item within the stockroom.

Enter Count Addition Window (F9)



To display this window select **F9=Add** on the Enter Count Details screen.

Use this window to add an item to the count.

IN133B		Z1 - Demonstration Company		User SP1		5/09/94 12:34:11	
Enter Count							
Stockroom		01		Item summaries to count		8	
Count number		4		Item details to count		1	
List number		4		Item summaries cancelled		1	
Create date/time		5/09/94 12:28:01		More:			
Item	Lot	Reason	Recorded qty	Entered qty			
- 5011		#1	512.000	512.000			
- 5013	B0 02	UN	719.000	.000			
- 5014	LP004	#1	138.000	138.000			
- 5014	L0 01			00			
- 5015	LP054			00			
- 5015	L0 02			00			

Addition

Item?.. 5013

Lot?.. B009

Reason code .?.. UN

Entered qty 325

F4=Prompt F12=Previous

1=Select 2=Lot header 4=Delete
F3=Exit F5=Refresh F8=Update F9=Add F11=Delete
F12=Previous

Position to item ..

Fields:

Item

Enter an item number, that is defined to the current stockroom and is already on count in this count.

Location

Warehousing stock count only. Enter the location where you counted the additional stock.

Lot

Enter a lot, batch or serial number.

Rotation

Warehousing stock count only. If the stock counted is rotation date controlled enter the appropriate rotation date.

Pack

Warehousing stock count only. Enter the pack type associated with the stock counted.

Label

Warehousing stock count only. If the pack type associated with the stock is label controlled enter the appropriate label number.

Reason Code

Enter the reason code to be associated with the additional item details. The reason code must be defined to the descriptions file under major type CTRE and must be of an override nature.



Note: You cannot select the reserved code of #1 for a Planned request for an item originating from an initial count request.

Quantity

Enter the counted quantity in the issue unit of measure defined for the item within the stockroom.

When you press **Enter**, you return to the details screen, the system does not calculate stock balance for the additional item, and is not displayed in the Recorded qty column. You can delete the complete list with **F11=Delete**, and all associated items taken off count (unless the item details span a number of lists).



Select **F8=Update** to update the list. If no errors occur, the Update Confirmation window is displayed.

Update Confirmation Window



To display this window select **F8=Select** to update the entered quantities. You must complete all count details for the list, before hand.

Use this screen to confirm a completed list. You must complete all lists associated with a count before you can process a reconciliation with update.

IN133B		Z1 - Demonstration Company		User SP1	5/09/94 12:36:16
Enter Count					
Stockroom		01	Item summaries to count		8
Count number		4	Item details to count		1
List number		4	Item summaries cancelled		1
Create date/time		5/09/94 12:28:01		More:	
Item	Lot	Reason	Recorded qty	Entered qty	
- 5011		#1	512.000	512.000	
- 5013	B002	UN	719.000	720.000	
- 5014	LP004	#1	138.000	.000	
- 5014	L001	#1	575.000	.000	
- 5015	LP054	#1	159.000	.000	
- 5015				.00	
- 5013				.00	
Update Confirmation					
Complete list ? 0 1=Yes 0=No					
F12=Previous					
1=Select 2=Lot header 4=Delete			Position to item ..		
F3=Exit		F5=Refresh	F8=Update	F9=Add	F11=Delete
F12=Previous					

Fields:

Complete List

Enter one of the following:

0 - To not complete the list.

1 - To complete the list.



Tip: Once you have flagged a list as complete a list you cannot maintain it.



Note: JBA recommend that a list is not completed until after reconciliation, as a completed list can no longer be maintained.

Complete Count Lists



33/INS
33/WHs

As an alternative to flagging lists as complete through the count entry option, you can complete all lists associated with a count en masse, after details have been entered and the results of reconciliation reviewed and before the final update.

Lists cannot be complete if they contain detail records with lots referring to the special case of * Lot Error *. These lots are generated during the printing of count sheets if no lots exist for a batch, lot or serial controlled item.

Complete Count Lists Count Selection Screen



Select Complete Count Lists.

Use this screen to select a count number for completion.

IN182A	Z1 - Demonstration Company	User SP1	01/09/94
	Central Warehouse		12:00:00
Count Completion			
Count number?.. ____7			
F3=Exit F4=Prompt			

Fields:

Count Number

Enter the count number to be completed. This must be of an outstanding status, that is, printed.



Press **Enter** to display the Complete Count Lists
List Selection Window.

Complete Count Lists List Selection Window

 To display this window select a stockroom and count number and press **Enter**.

Use this window to select an action list associated with a chosen count for completion.

IN181A		Z1 - Demonstration Company		User SP1		5/09/94 12:38:07	
Count Completion							
Stockroom		01					
Count number		4					
				Select List Number			
				Central Warehouse			
				Count No..... 4			
				More:			
				S Number			
				1 4			
				- 5			
				- 6			
				- 7			
				1=Select			
				Position to....			
				F3=Exit F8=Update F12=Previous			
F3=Exit				F4=Prompt			

Fields:

S

Select. Enter 1 to select a list number associated with this count.

 Select **F8=Update** to update.

Print Count Sheets

1... 41/INS
2... 41/WHs

This option records the computer stock figure and summary recommendations are expanded to include lot/batch/serial level detail where relevant.

If a lot controlled item has no recorded lots or each lot is empty the system writes a record with the reference Lot error. You must delete this reference during count entry and count and add the actual lots of the item (if they exist), or you can delete the item from the count.

In addition, at time of print you can split the workload for the count across a number of lists based on the number of instructions on the count and the number of required instructions per list.

When you print the count sheet, it contains a list of items, the quantity of the items and the type. The type can be as follows:

- Type 1 - Class/Date Control. For more information see Create Count By Class/Date Control screen.
- Type 2 - Manual Range. For more information see Manual Range.
- Type 3 - Warehouse Location. For more information see Warehousing.
- Type 4 - Catchweight. This means the item has a zero primary value and a non-zero secondary value. You investigate this item to find out if any of this item is still available. As you can receive more of the item between printing off the count sheet and completing the stock take, it is strongly recommended that you investigate and correct these type 4 items first.

Print Count Sheets Count Selection Screen



Select Print Count Sheets.

Use this screen to enter the selection criteria for Print Count Sheets.

IN152	Z1 - Demonstration Company Central Warehouse	User SP1	01/09/94 12:00:00
Print count sheets			
Count number from?.. <u>4</u> to?.. <u>6</u>			
No of instructions/list <u>15</u>			
Organise count by <u>2</u> 1=Warehouse 2=Area 3=Access to dimension 1			
Sequence count by <u>2</u> 1=Item 2=Location			
F3=Exit F4=Prompt F8=Submit			

Fields:

Stockroom

This field is not displayed if you are doing a warehouse stock count.

Enter the stockroom code.

Count Number From/To

If you enter a single count, it must be outstanding. If you enter a range, these may act as limiters. If left blank, all recommendations are included.

No Of Instructions/List

Enter a number to create multiple lists. If you enter zero, all counts appear on one list.

Organise Count By

Only displayed for Warehouse stock count. This value signals the start of a new list when the chosen option changes.

1 - Warehouse. As the count only relates to your default warehouse, a new list is created when the number of location or item details exceeds the value set for No of instructions/list.

2 - Area. Create a separate count list for each change of area code within the warehouse.

3 - Access to dimension 1. Create a separate count list for each change of access to dimension 1. The access points are set up in Warehousing Maintenance and are

used for example to produce one action list per Aisle in the warehouse, if you set Aisle to be the first dimension.

For example if Organise count by is set to 2, Area, a new list is created for each change in area code. There may be several lists per area if the number of location or item details to be checked exceeds the value set for No of instructions/list.

Sequence Count By

Only displayed for Warehouse stock count. Enter one of the following:

- 1 - Item. The actions on the list are ordered by item.
- 2 - Location. The actions on the list are ordered by location code.



Select **F8=Submit** to submit count sheets to print.

Reprint Count Sheets

1... 42/INS
2... 42/WHs

Use this option to select count sheets you wish to re-print.

Reprint Count Sheets Count Selection Screen



Select Reprint Count Sheets.

Use this screen to reprint count sheets. You can print all, or selected lists for a count.

```

IN161                               Z1 - Demonstration Company       User SP1           5/09/94
                                           12:36:59

Reprint count sheets

Stockroom .....?.. 01

Count number from.....?.. 4      List number from...?.. 4

Count number to.....?.. 4      List number to.....?.. 5

```

Count Reconciliation

Reconciliation compares counted stock quantities with recorded computer stock quantities to assess stock count errors.

Stock errors are assessed on both a percentage quantity variance and a value variance basis as defined by the tolerances specified for the stockroom count profile.

For count profiles defined for count by classification, the appropriate classification tolerances are used for each item detail record, that is, A, B or C. Where you have not specified count by classification for the stockroom, the single default set of quantity percentage and value tolerance figures are used to assess count errors.

You can restrict Reconciliation (Without Update) to Complete lists within the count or to additionally include Open lists that are still available for modification. In addition you can restrict the report content such that it only includes items with quantity/value variances.

You can print full detail or summary information by item with selection by item range.

Detail or item summaries that are considered to be in error are flagged with an * at the right hand side of the report.

If an item summary is found to be in error but no errors have occurred for the detail lines, the summary is flagged for attention with a **. This situation normally arises due to a number of small positive (or negative) variances which in total constitute an error.

A similar situation arises with reconciliation (with update) where detail lines exist that are in error; however the summary is not flagged as in error. This situation normally arises due to a number of positive and negative variance errors at detail level that cancel each other out. If this arises the system assesses whether the item summary is placed in error or the adjusted detail lines are ignored for the summary totals. If they are in error, forced adjustments are made for all detail variances regardless of the extent of the variance, and the summary is flagged for attention with a **.

To assess whether variances are true count errors, you can print inventory movements that have occurred since the count sheets were printed, (and the computer stocks recorded), for those items that are in error.

Use Reconciliation (With Update) to make adjustments involving the update of the inventory stockroom balances according to the variances specified. Full movement audit and history updates are reflected in Inventory for any adjustments that take place.

Additionally, item count summaries are updated to reflect the type of count carried out for the item, together with the last count date and a recalculated next due count date. The stockroom period count history is updated to reflect the number and type of counts carried out for the stockroom.

If DRP and/or Production Planning are installed, net change triggers are written for any adjusted items in order to facilitate the selective replanning of items within the appropriate applications.

If Catchweight is used for this company, then the following occurs when reconciliation takes place.

For catchweight items or non-catchweight items with secondary units of measure, if the primary value is zero then the secondary value is also made zero. If the primary value is adjusted, the secondary value is automatically adjusted. The nominal secondary value of the quantity is also adjusted.

Reconciliation Without Update

1...
2...

51/INS
51/WHS



Select Without Update. To display this screen enter a stockroom code and count number on the Request Count Reconciliation (Without Update) Selection screen and press **Enter**.

Or: For Warehousing Stock Count. To display this screen enter a count number the On the first Request Count Reconciliation (Without Update) Selection screen and press **Enter**.

IN136B	Z1 - Demonstration Company	User SP1	5/09/94 12:37:32
Request Count Reconciliation (without update)			
Stockroom.....	01	Central Stockroom	
Count number.....	4		
Count lists.....	2	1=Completed 2=All	
Report content.....	1	1=Detail 2=Summary	
Print movements.....	1	0=No,1=Yes	
Items to be included....	2	0=None 1=Variance 2=All	
Range of items:			
From.....?	..	To.....?	..
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

Count Lists

Enter one of the following:

- 1 - Completed. Include completed lists on the report.
- 2 - All. Include both open and completed lists on the report.

Report Content

Enter one of the following:

- 1 - Detail. Include item detail, that is, lots, batches and serial numbers on the report.
- 2 - Summary. Include item totals on the report.

Print Movements

Enter one of the following:

1 - To print the movements: counted quantity, value of the count and recorded quantity of items. The items printed on the report depend on the entry in the field Items to be included.

0 - To exclude movements.

Items To Be Included

Enter one of the following:

0 - None. Do not include details on the report.

1 - Variance. Include those details with either a quantity or value variance on the report.

2 - All. Include all detail regardless of variance on the report.

Range Of Items From.. To..

Enter the valid item reference number required.

If you enter a single item it must exist on the item master file. If you enter a range, the From and To items used to define the range need not exist on the item master file except when they are the same value. If you leave the To item blank, it defaults to the From item. You can use range restriction to investigate specific item discrepancies.



Note: A blank range selection for items defaults to all items on the count.



Select **F8=Submit** to action batch job.

Reconciliation With Update

1...
2...

52/INS
52/WHS



Select With Update. To display this screen enter a stockroom code and count number on the Reconciliation With Update Selection screen and press **Enter**.

Or: for Warehousing Stock Count. To display this screen enter a count number on the Warehouse Stock Count Selection screen and press **Enter**.

IN136B	Z1 - Demonstration Company	User SP1	5/09/94 12:41:32
Request Count Reconciliation (With update)			
Stockroom.....	01	Central Stockroom	
Count number.....	4		
Report content.....	1	1=Detail 2=Summary	
Print movements.....	1	0=No,1=Yes	
Items to be included....	2	0=None 1=Variance 2=All	
Generate adjustments....	0	0=No 1=All 2=Outside tolerances	
Reason code.....?	—		
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

Report Content

Enter one of the following:

- 1 - Detail. Include item detail, that is, lots, batches and serial numbers on the report.
- 2 - Summary. Include item totals on the report.

Print Movements

Enter one of the following:

- 0 - No. Do not print movements.
- 1 - Yes. Print movements for all items that are in error.
- 2 - Warehousing. Print Warehousing movements for all items that are in error.
- 3 - Both. Print both Inventory and Warehousing movements for all items that are in error.

Options 2 and 3 are only available for Warehousing Stock Count.

Items To Be Included

Enter one of the following:

- 0 - None. Do not include details are on the report.
- 1 - Variance. Include details with either a quantity or value variance are the report.
- 2 - All. Include all detail regardless of variance on the report.

Generate Adjustments

Enter one of the following:

- 0 - None. Do not make stock adjustments.
- 1 - All. Adjust all quantity variances regardless of size within inventory.
- 2 - Outside tolerances. Adjust those variances which are flagged as errors (those with *) within Inventory.

Reason Code

You must enter a movement reason if adjustments are requested. Reason codes are defined to the descriptions file against the major type MOVR.



Select **F8=Update** to submit the batch job.

Reconciliation History Updates

If you request count reconciliation with update, the system performs the following count history updates:

Item Count History

- Count by Class. The number of recommended counts is incremented if the item was a planned summary recommendation. The number of unplanned counts is incremented if the item was an unplanned recommendation, that is, originating from an addition via recommendations maintenance
- Count by Manual Range. Number of unplanned counts is incremented.

Stockroom Count History

- Count by Class. Numbers of A, B and C items counted are incremented for all items that were planned via summary recommendations. In addition the numbers of A, B and C items that are in error are incremented for all items in error that were planned summary recommendations.
- Count by Manual Range. Number of other counts is incremented. In addition the numbers of other counts that are in error are incremented if any of the items on those counts are in error.



Note: If Warehousing is installed and you selected count by Warehouse location, the system performs other updates associated with these counts. For a full explanation, see Stock Counting in the Warehousing application.

Recommended Counts Enquiry



61/INS
61/WHs

Use this option to view the details of the Maintain Count option but without being able to do any maintenance.

Count Enquiry Selection Screen



Select Recommended Counts.

Use this screen to select the stockroom you wish to enquire upon.

```

IN142A          Z1 - UK Demonstration Company    User GJBAMSA    1/06/98
                                           13:38:44
Count Enquiry
Stockroom .....?.. 01
Count number .....?.. 0
  
```

Recommended Count Selection

Stockroom01

Central Stockroom

Count	Date and time	Items to
Sel number	count initialised	count
- 7	21/01/98 18:33:16	1

1=Select Position to
F12=Previous

F3=Exit F4=Prompt

Fields:

Stockroom

Enter a stockroom code using upto 2 characters.

Count Number

Enter a count number associated with the stockroom you have chosen.



Press **Enter** to display the Count Enquiry Details screen.

Count Enquiry Details Screen



To display this screen select a stockroom and count list combination on the Count Enquiry Selection screen and press **Enter**.

This screen displays the count details for the stockroom and count list combination you previously selected.

IN142B	Z1 - UK Demonstration Company	User GBJBAMSA	1/06/98 13:40:26
Count Enquiry			
Stockroom	01	Item summaries to count	1
		Item details to count	0
Count number	7	Item summaries cancelled	0
Create date/time	21/01/98 18:33:16	More:	
Item	Lot	Reason	
5001		Planned Count	
Position to item .. _____			
F3=Exit		F12=Previous	

Fields:

Position To Item

To view specific item details, enter the item reference number and press **Enter**.

Outstanding Counts Enquiry

1... 62/INS
2... 62/WHS

Use this option to enquire on outstanding counts for a stockroom. You can review open or complete lists for a count.

Count Enquiry Selection Screen



Select Outstanding Counts.

Use this screen to select the count that you wish to enquire on.

IN146A	Z1 - Demonstration Company	User SP1	5/09/94 12:36:35
Count Details Enquiry			
Stockroom	?	01	
Count number	?	4	
List number	?	4	
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter a stockroom code.

Count Number

Enter a count number.

List Number

Enter a list number.



Press **Enter** to display the Count Enquiry Detail screen.

Count Enquiry Detail Screen



To display this screen select a count on the Count Enquiry Selection screen and press **Enter**.

Use this screen to view the details of the count that you have selected to enquire on.

IN142B	Z1 - Demonstration Company	User SP1	5/09/94 12:32:37
Count Enquiry			
Stockroom	01	Item summaries to count	8
Count number	4	Item details to count	1
Create date/time	5/09/94 12:28:01	Item summaries cancelled	1
		More:	
Item	Lot	Reason	
5011		Planned Count	
5013	B002	Unplanned Request	
5014		Planned Count	
5015		Planned Count	
5016		Planned Count	
5017		Planned Count	
5018		Planned Count	
5019		Planned Count	
5020		Planned Count	
Position to item ..			
F3=Exit F12=Previous			

Fields:

Position To Item

Enter an item code to start the display.



Press **F3=Exit** to exit the enquiry.

Item Count Summary Enquiry



63/INS
63/WHs

Use this option to view yearly summary count information by item; that is, the number and type of counts carried out to date, with dates of the last count and the next count due.

Item Count Summary Enquiry Selection Screen

 Select Item Count Summary.

Use this screen to select the stockroom and item for the count summary information that you require to view.

IN174A	Z1 - Demonstration Company	User SP1	5/09/94 12:37:51
Item Count Summary Enquiry			
Stockroom?.. <u>01</u>			
Item?.. <u>5013</u>			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter a stockroom code.

Item

Enter an item code to display count details for a single item. Leave the field blank to display all item summaries associated with the specified stockroom.



Tip: If you enter a stockroom and leave the item field blank, the system displays a summary count information for all items in the specified stockroom.



Press **Enter** to display the Item Count Summary Enquiry Details screen.

Item Count Summary Enquiry Details Screen



To display this screen select the stockroom and optionally the item on the Item Count Summary Enquiry Details screen and press **Enter**.

Use this screen to view the count summary information for the selected stockroom and item combination.

IN174C		Z1 - Demonstration Company		User SPI		21/09/94 9:48:03	
Item Count Summary Enquiry							
Stockroom 01 Central Stockroom							
Item	Year	Counts recommended	Counts unplanned	Last count date	Last count time	Next count date	Next count time
- 5001	94	0	0	11/08/94		17/12/94	
- 5002	94	0	0	11/08/94		17/12/94	
- 5003	94	1	0	16/08/94		22/12/94	
- 5004	94	0	1	5/09/94		12/01/95	
- 5005	94	0	0	11/08/94		17/12/94	
- 5006	94	1	0	16/08/94		22/12/94	
- 5007	94	1	0	16/08/94		22/12/94	
- 5008	94	0	0	11/08/94		17/12/94	
- 5009	94	0	0	11/08/94		17/12/94	
- 5010	94	0	0	11/08/94		17/12/94	
- 5011	94	0	0	11/08/94		17/12/94	
- 5012	94	0	2	5/09/94		12/01/95	
Position to item							
F3=Exit				F12=Previous			

Fields:

Untitled

Select. Enter 1 to display count details for this item

Position To Item

If the list extends over a single screen, enter the item reference number or the first few characters of an item to reposition the count list.



Select an item and press **Enter** to view the Item Count Summary Enquiry Item Details screen

Item Count Summary Enquiry Item Details Screen



To display this screen select an item to view and press **Enter** on the Item Count Summary Enquiry Details screen

Use this screen to view summary information for the selected item and stockroom

IN174B	Z1 - Demonstration Company	User SP1	5/09/94 12:37:56
Item Count Summary Enquiry			
Stockroom	01	Central Stockroom	
Item	5013		
Year	94		
Date/time of last count	5/09/94	0:00:00	
Date/time of next count	12/01/95	0:00:00	
Recommended counts	0		
Unplanned counts	2		
Negative stock counts	0		
Low stock counts	0		
Zero stock counts	0		
Transaction frequency counts	0		
F3=Exit F12=Previous			

Fields:

Recommended Counts

The number of application recommended counts carried out this year.

Unplanned Counts

The number of unplanned, or manually requested, counts that carried out this year.



Note: Low Stock Counts, Zero Stock Counts, Transaction Frequency Counts are currently unsupported count methodologies, provided for recommending counts in the future.



Press **F3=Exit** to exit the enquiry.

Count History Enquiry



64/INS
64/WHs

Use this option to view stockroom summary count information by period. Counts are only included in this enquiry once you have run a reconciliation with update, even if no stock adjustments were actually generated.

At summary level the total number of counts is displayed, with information on the number of each ABC classified item counted with the number of items in error.

The number of other counts (those where you manually select the range) and other counts in error are displayed only at a detail level on an individual period basis.

Count History Enquiry Selection Screen



Select Count History.

Use this screen to select the stockroom and period for the count history information that you require to view.

IN177A	Z1 - Demonstration Company	User SP1	5/09/94 12:39:06
Count History Enquiry			
Stockroom?.. <u>01</u>			
Period _____			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code to review its count summaries.

Week/Period

Enter the week or period you want to review. Leave the period field blank to display all period summaries associated with stockroom. Summaries are displayed in descending period sequence by year.

If you want to view a specific period you must use the following format:

YYMM If usage cycle is Monthly

YYWW If usage cycle is Weekly

Where YY is the current year, MM is the current period and WW is the current week.



Tip: The usage cycle is defined to the Inventory company profile maintenance.



Press **Enter** to display the Count History Enquiry Summary screen.

Count History Enquiry Summary Screen



To display this screen select a stockroom and period on the Count History Enquiry Selection screen and press **Enter**.

Use this screen to view the count history information for the selected stockroom and period combination.

IN177C	Z1 - Demonstration Company	User SP1	5/09/94 12:39:09				
Count History Enquiry							
Stockroom 01 Central Stockroom							
Period	Counts	Class A counts	Class B counts	Class C counts	Count A errors	Class B errors	Class C errors
_ 08	2	0	0	0	0	0	0
Position to ____							
F3=Exit		F12=Previous					

Fields:

Untitled

Select. Enter 1 to display a more detailed count history.

Position To

If the summary count history extends over more than a single screen then enter the required period in the position to field to position the list at the selected period. You need to use the format YYMM or YYWW, in accordance with the usage cycle. (See the Company Profile Usage Profile.)



Press **Enter** to display the Count History Enquiry Stockroom Detail screen.

Count History Enquiry Stockroom Detail Screen (Option 1)



To display this screen select a period on the Count History Enquiry Summary screen and press **Enter**.

Use this screen to view the summary period information for the stockroom, including the number of ABC classified items counted and the number of items with errors.

IN177B	Z1 - Demonstration Company	User SP1	5/09/94 12:44:20
Count History Enquiry			
Stockroom 01 Central Stockroom			
Period 9408			
Number of counts 3			
Number of class A items counted ... 0			
Number of class B items counted ... 0			
Number of class C items counted ... 0			
Number of class A item errors 0			
Number of class B item errors 0			
Number of class C item errors 0			
Number of other counts 3			
Number of other count errors 1			
F3=Exit F12=Previous			



Press **F3=Exit** to exit the enquiry.