

-
-
-
-
-

Chapter 1

Maintenance



AFI Maintenance Functions

In order to use AFI you must set up at least one of each of the following:

- Journal conditions
 - These contain the rules used by AFI to select transactions in the source application.
 - Posting definitions
 - These tell AFI what information to pick up from the transactions selected.

Once the information has been extracted, AFI needs to know where to post it. You can let it post to the default accounts in GL or ABC, but to make full use of the analysis function provided via AFI you will want to use the extracted information itself to decide where to post.

If you wish to use the extracted information to create the codes to be posted to (these codes will be accounts within GL, or analysis codes within ABC), then the following options are required:

- Account code rules
 - Account code rules enable you to define how extracted information is to be mapped to create posting codes.
 - Data conversion codes
 - Data conversion codes are required if the input data is to be converted to alternative values when generating codes.
 - Template definitions
 - Templates are required if you wish to vary, for the purpose of AFI, the account level structure defined in your General Ledger.

Try to avoid maintaining this data if there are AFI transactions awaiting update (i.e. where automatic update is not being used).

Change Application



11/FIP

This option is used to select the application to be used while maintaining rules and definitions within AFI.



Take the *Change Application* option. A window enables you to select the source application.



Note: If you take a Maintenance option without having selected an application, the application selection window will be displayed automatically.

Journal Conditions



1/FIM

This facility enables you to define the source company from which the posting details are to be extracted, the parameters which govern when an extraction is to be made and the target application and company to which the posting is to be made.

Whether you decide to amend an existing condition or create a new condition, the Journal Definition Maintenance screen will be displayed.

Journal Condition Maintenance Screen

Whether you decide to amend an existing condition or create a new condition, the Journal Definition Maintenance screen will be displayed.



Take the *Journal Conditions* option. A window will display existing journal conditions available for amendment. Select one, or press **F18** to set up a new condition.

F1020		Advanced Financial Integrator		User TESTQA	18/09/96
Current Application.: Inventory					11:03:00
Journal Definition Maintenance					*Update
Journal Description <u>GLC IN/AFI Stock Movement-RM to WIP 2</u> ** LIVE **					
Target Application . GL		General Ledger			
Source Company . . ? <u>Z1</u>		Version 3 Demonstration Company			
Jrnl Condition Fld ? <u>PNUM96</u>		Item Code			
Test Type. <u>1</u>		(1=in range 0=not in range)			
Test against values		From . . . : <u>MAL001</u>			
		To . . . : <u>MAL003</u>			
Target company . . ? <u>Z1</u>		Version 3 Demonstration Company			
More Conditions. . . <u>0</u>		(1=Yes,0=No)			
F3=Exit		F4=Prompt	F11=Delete	F12=Previous	F15=Postings
Enter=Update					
05-26		<u>SP</u>	<u>ML</u>	KS	IM II KENB20A PET179S2

Fields:

Journal Description

Enter a meaningful description of the journal condition.

Unnamed Field (Journal Status)

0 - Inactive. This journal condition is set up on the system, but cannot be used.

1 - Under test. This journal condition can be used only when using the AFI test extract facility and will not make postings.

2 - Live. A fully active journal condition which makes postings.

Target Application

Enter the application to which postings are to be made.

GL - General Ledger

CG - Advanced Business Costing

Source Company

Enter the source company which will provide the data.

Jrnl Condition Field

Each journal condition includes a test it must make to determine when to create postings. Typically this test will be based on transaction type.

Enter here the data field to be tested. A prompt is available.

Only alphanumeric fields may be used in this test.

Test Type

The test type is used in conjunction with the journal condition field.

0 - Postings should occur if the tested data lies outside the given range (see 'Test Against Values').

1 - Postings should occur if the tested data lies within the given range.

Test Against Values Range

Enter the value range required. The values are compared to the data contained in the journal condition field, based on the test type. If the match is successful, postings occur. See also the 'More Conditions' field below.

The value you put in the 'From' field must be less than or equal to the value put in the 'To' field. If you want to test for a single value then put the same value in both the 'From' and 'To' fields.

Target Company

This is the code of the target company, i.e. the General Ledger or Advanced Business Costing company to which postings will be made if the match criteria are met.

More Conditions

If you want to specify more test conditions, enter 1 here and press Enter. A window will enable you to enter more conditions.



Press **Enter**.

If the 'More Conditions' field was set to 0, the entries or changes you have made will be updated, and you can exit the option, or enter another journal condition.

If the 'More Conditions' field was set to 1, the Journal Conditioning window will be displayed to enable you to enter more test conditions.

Functions:

F11

Delete an existing journal definition.

F15

This will take you into the first screen of the Posting Definitions option.

Journal Conditioning Window



If the 'More Conditions' field was set to 1, the Journal Condition window will be displayed to enable you to enter more test conditions.

FI020		Advanced Financial Integrator		User TESTQA	18/09/96
Current Application.: Inventory					11:03:00
Journal Definition Maintenance					*Update

Ln	Jrnl field	Tst	From test value	To test value
01	PNUM96	1	MAL001	MAL003
02				
03				
04				
05				
06				
07				
08				
09				
10				

F4=Prompt F8=Update F12=Previous

More Conditions. . . 1 (1=Yes,0=No)

F3=Exit	F4=Prompt	F11=Delete	F12=Previous	F15=Postings
Enter=Update	09-17	SA	MA	KS
			IM	II
				KENB20A
				PET179S2

Fields:

Jrnl Fld

Enter the data field to be tested. Only alphanumeric fields may be used in the test.

Tst

0 - Make the postings if the data lies outside the given range.

1 - Make the postings if the data lies within the given range.

Test Value Range

Enter the values the data is to be tested against. The value in the 'from' field must be less than or equal to the value in the 'to' field. To test for a single value, put that value in both fields.



Note: Multiple test conditions have an AND relationship; that is all the listed conditions must be satisfied by the input data for postings to be made by this journal.



When you have entered all the conditions, press **F8=Update** to update.

Posting Definitions



2/FIM

Posting definitions enable you to set the parameters for handling the data you wish to post. You can specify what values are to be posted, and how the account codes are to be composed.

The Posting Definition Browse and Select screen is reached either by:

- Taking the Postings Definitions option.
- Pressing **F15** from within the Journal Conditions option.

Posting Definition Browse and Select Screen

- ➡ Take the Postings Definitions option to display a window of existing journal conditions. Select the condition whose postings you wish to review or amend, and the Posting Definition Browse and Select screen will be displayed.

FI325 Advanced Financial Integrator User TESTQA 18/09/96
Current Application.: Inventory 11:24:00
Posting Definition Browse and Select

Journal 5 PLC IN/AFI Stock Movement-RM to WIP Src. Co. Z1 Trg.Co. Z1
Position list to Posting No. _____

	Posting Number	Posting Description
-	7	PLC INV/AFI-Movement Cost out of RM
-	8	PLC INV/AFI-Movement Cost into WIP

1=Select

F3=Exit F12=Previous F18=Add a record

12-15 SR MK KS IM II KENB20A PET179S2

Fields:

Position List To...

Enter the posting number to which you want to reposition the list.

Select

Enter 1 against the posting definition you want to maintain.

- ➡ When you have selected a definition, or pressed **F18=Add a record** to add a new one, the Posting Definition Maintenance screen will be displayed.

Posting Definition Maintenance Screen



When you have selected a definition, or pressed **F18=Add a record** to add a new one, the Posting Definition Maintenance screen will be displayed.

FI025	Advanced Financial Integrator	User TESTQA	18/09/96
Current Application.: Inventory			11:24:43
Posting Definition Maintenance			
Journal PLC IN/AFI Stock Movement-RM to WIP		Src. Co. Z1	
Target Application GL		Trg. Co. Z1	
Posting description		PLC INV/AFI-Movement Cost out of RM	*Update
Value field to post ?		MOV96	Total Movement Cost
Reverse sign of posting? (1/0)		1	
Consolidatable posting? (1/0)		0	
Consolidation control field . . . ?			
Default posting account . . . ?		310100	Raw Materials Transfers Control,
Account generation rule . . R/?		-	
Quantity field to post . . . ?			
F3=Exit	F4=Prompt	F10=Display Alternative Rule parameters	
F11=Delete	F12=Previous	Enter=Update	
00-34	SR	ML	KS IM II KENB20A PET179S2

Fields:

Posting Description

Enter a brief description of the posting to be created or maintained and could be, for example, a description of the account to which the posting will be made.

Value Field To Post

Enter the field containing the value to be posted. A prompt is available.

Reverse Sign Of Posting

0 - The value is to be posted with the same sign as that provided by the source application.

1 - Reverse the value's sign such that positive becomes negative, and negative positive.

Consolidatable Posting

Consolidation is when a number of transactions with common characteristics are posted as one transaction. The 'Consolidation Control Field' (see below) determines the characteristics for consolidation.

0 - Consolidation will not take place and individual postings will be made.

1 - Consolidation will take place if consolidation has been set to take place at the time of posting (either via Application Maintenance, or when a manual posting is

initiated). The consolidation will take place based on the contents of the 'Consolidation Control Field'.



Note: Consolidation does not apply to ABC.

Consolidation Control Field

This is the name of the field to be used to control consolidation before posting. A prompt is available. This field is only relevant if the 'Consolidatable Posting' field is set to 1.

All input transactions from the source application which have the same value in the 'Consolidation Control' field will have their posting values consolidated before posting.

Default Posting Account

This is the target account code to which the posting will be made if an account generation rule is not used.

If an account generation rule is used, this entry is the starting account which will be wholly or partly modified by the rule to generate the target account. It is also the default account code which will be used if the account generation rule fails to create a valid account number.

R/

This one character field is used only to delete an account generation rule which has already been entered for this posting. Enter R and press Enter to delete the rule.

Account Generation Rule

Enter the rule (which must have been previously defined in Account Rules) from which the account number is to be created for this posting.

An account generation rule is only necessary if the account code to be used for posting is to be generated by AFI.

Quantity Field To Post

Enter the field containing the quantity to be posted by this posting definition. This field is not mandatory entry.



Press **Enter** to update, or **F10=Display Alternative Rule Parameters** to see the alternative account rule parameters fields.

Functions:

F10

Display alternative rule parameters (see Alternative Account Rule Parameters (F10) screen.)

F11

Used to delete an existing posting definition

Alternative Account Rule Parameters (F10)

These optional parameters are used to specify an alternative rule to be used according to the contents of a specified data field in the source application. You can specify a data field to test and the range of values to test for. If the test is successful the alternative account generation rule is used, rather than the primary account generation rule.



This screen is displayed when you press F10
F10=Display Alternative Rule Parameters in
the Posting Definition Maintenance Screen.

F1025		Advanced Financial Integrator		User TESTQA	18/09/96
Current Application.: Inventory					11:24:43
Posting Definition Maintenance					
Journal PLC IN/AFI Stock Movement-RM to WIP		Src. Co. Z1			
Target Application GL		Trg. Co. Z1			
Posting description		PLC INV/AFI-Movement Cost out of RM		*Update	
Value field to post ?		MOV96		Total Movement Cost	
Reverse sign of posting? (1/0)		1			
Consolidatable posting? (1/0)		0			
Consolidation control field . ?					
Default posting account . . . ?		310100		Raw Materials Transfers Control,	
Account generation rule . . R/?		-			
Quantity field to post . . . ?					
----- Alternative Account Rule Parameters (optional) -----					
Data to test ?					
Test against values . . . from:				To: _____	
Use alternative if data is . . 1				(1=Inside range, 0=Outside range)	
Alternative account rule. . R/?		-			
F3=Exit		F4=Prompt		F10=Display Alternative Rule parameters	
F11=Delete		F12=Previous		Enter=Update	
00-34		SF		KS IM II KENB20A PET179S2	

Fields:

Data To Test

This enables you to define the data field in the source application you wish to test to determine whether an alternative account generation rule should be used. A prompt is available.

Test Against Values Range

Enter the value range required. The values are compared to the data contained in the 'Data To Test' field based on the 'Use Alternative If Data Is' field. If the match is successful a posting occurs using the alternative rule, otherwise the primary rule is used.

The value you put in the 'From' field must be less than or equal to the value put in the 'To' field. If you want to test for a single value then put the same value in both the 'From' and 'To' fields.

Use Alternative If Data Is

This field is used in conjunction with the 'Data To Test' and 'Test Against Values Range' fields.

0 - The alternative rule is to be used if the data from the 'Data To Test' field is outside the range of 'Test Against Values'.

1 - The alternative rule is to be used if the data from the 'Data To Test' field is inside the range of 'Test Against Values'.

If the specified test fails, then the primary account generation rule will be used in the posting.

R/

This one character field is used only to delete an alternative rule which has already been entered for this posting. Enter R and press Enter to delete the rule.

Alternative Account Rule

This field is used to specify the alternative account generation rule, which must have been previously defined in Account Rule Maintenance, from which the account code is to be created for this posting. A prompt is available.

For example, this could be used to attribute sales of one product category to one range of sales accounts, and other product categories to a different range.



Press **Enter** to update the data files when the required posting definition entries or amendments have been made.

Functions:

F11

Used to delete an existing posting definition.

Account Rules



3/FIM

Setting up an account rule is a means of converting posting data into an account in GL, or a code in ABC. The data string which constitutes the posting is analysed according to the details of the account rule, and each element of the data string becomes an element of the account or code.



Note: Any accounts or codes created must already be defined within the target application.

In this example, you wish to post invoices and create the GL account codes from the postings. Each posting consists of the following fields:

Field Name	Description	Valid Values	Portion of GL Code
TRAN 10	Transaction type	'70 - Invoice 75 - Credit	70 75
MARK 10	Market	HOM - Home EXP - Export INT - Intercompany	2 3 4
CTYP20	Customer type	A - Industry B - Retail	100 200
PCAL90	Posting value	Any	-

The final column shows the portion of the code which each field is to create. The code created by an export invoice to a type B customer, for example would be 703200.

You can see that the contents of the TRAN10 field transfer directly to become part of the account. The data, in other words, is not converted to another value.

The other two fields, however, MARK10 and CTYP20, do not send their contents to form part of the code. They are converted first. This is done by setting up conversion codes using the Data Conversion Codes.



Take the *Account Rules* option and a window of existing account rules is displayed. Select a rule for amendment, or press **F18** to add a new rule. The Account Rule Maintenance - Input screen is displayed.

Account Rule Maintenance Input Screen

This screen is used for entering the data fields from the source application which are to be used to build the code.

FI030		Advanced Financial Integrator		User TESTQA	18/09/96
Current Application.: Inventory					11:28:13
Account Rule Maintenance					*UPDATE
Account Generation Rule <u>PLC CG Stock movement rule one</u>				(RULE INPUT)	
Target Application . : CG Cost Accounting					
	Field name	Start Position	Length to use		
A	<u>DGLA35</u>	<u>1</u> for	<u> </u>	Default GL Account	
B	<u>STRC96</u>	<u>1</u> for	<u> </u>	Stockroom Code	
C	<u> </u>	<u> </u> for	<u> </u>		
D	<u> </u>	<u> </u> for	<u> </u>		
E	<u> </u>	<u> </u> for	<u> </u>		
F	<u> </u>	<u> </u> for	<u> </u>		
G	<u> </u>	<u> </u> for	<u> </u>		
H	<u> </u>	<u> </u> for	<u> </u>		
I	<u> </u>	<u> </u> for	<u> </u>		
F3=Exit F4=Prompt F12=Previous					
ENTER=Next screen (Rule Output data)					
05-29 <u>SF</u> <u>MM</u> KS IM II KENB20A PET179S2					

Fields:

Account Generation Rule

Enter a description for the rule.

Field Name

This is the data field from the source application, all or a part of which is used to build all or a part of the code to be created. A prompt is available.

Start Position

Enter the start position of the data you wish to use in the 'Field Name' defined above.

For example, if you want to ignore the first 2 characters of the field and commence building the code with the third character, enter a 3 here. Leave blank to start at position 1.

Length To Use

Enter the length of the data string from the data field name you wish to use. For example, for a 6 character data field with a start position of 3 defined above, you would enter a 4 here to indicate you were using four characters of the field (the data in positions 3, 4, 5 and 6). Leave blank if you want to use all data to the end of the field.

You may use up to 9 data fields in building up your string of input data, defined in positions A - I on this screen, each with a start position and length to use.

The data string built up from all or selected portions of the specified data fields will be used to modify all or part of the default posting account that this rule is attached to.



Press **Enter** to go to the Account Rule Maintenance Output for GL Screen, which specifies how to modify all or part of a default account code (defined in the posting definition), with the data selected, to create a final account code.

Functions:

F11

Used to delete an existing account code rule. This is only allowed, and the F11 function only appears, when the rule is not used in any posting definition. Confirmation of the deletion is required. Any associated conversion data is also deleted.

The screen you see will depend on the account rule application you are using. If you are posting to the General Ledger, you will see the Account Rule Maintenance - Output for GL screen.

The screen you see will depend on the account rule application you are using. If you are posting to Advanced Business Costing, you will see the Account Rule Maintenance - Output for ABC screen.

Account Rule Maintenance Output for GL Screen



This screen is displayed when you enter details in the Account Rule Maintenance Input Screen and press **Enter**.

```

FI030          Advanced Financial Integrator  User TESTQA      180996
Current Application.: Inventory                17:29:08
Account Rule Maintenance                      *ADD

Account generation rule Rule 002                                (RULE OUTPUT)

GL co. . . ? Z1  GL ledger. ? ___  OR  Template . ? ___

O/write      Portion of rule data to use  Convert?
Level        Start position      Length  (0/1)
  1          ___                ___      0
  2          ___                ___      0
  3          ___                ___      0
  4          ___                ___      0
                                           +
(RULE INPUT) Rule data format...: A.....
A Movement Reason Code                2 for length of 1

F3=Exit  F4=Prompt  F12=Previous

08-18  SF  MM  KS  IM  II  KENB20A  PET179S2
  
```

Fields:

GL Co

This specifies the target GL company for which this rule will generate an account code. An account code generated by this rule must exist in this company.

GL Ledger

This specifies the name of the actual ledger - the profit & loss ledger, for example, or the balance sheet - whose account level structure will be used as the template for this rule. The ledger must exist within the specified company.

This is an optional entry used to access the level code structure defined for the target structure. The alternatives are:

- To use a template to define a level code structure.
- To use neither a ledger nor a template to define the level structure. In this case the account must be retrieved directly from the data string, or the account generated by a single level data conversion.
- In either of these cases, this is only allowed if extension codes are inactive for the company.

Template

You may use a template to define the General Ledger level code structure you wish to use. This template must have previously been defined using the Templates option.

The code to enter here is the three-character template code assigned to the template you wish to use. This entry is optional, as explained above under 'General Ledger'.

O/Write Level

The overwrite level. This non-input field displays up to nine levels at which you may modify portions of the input data string to create or modify the code. Against each level to be used you may specify a start position, length, and whether the data is to be converted.

Portion Of Rule Data To Use - Start Position

This relates to the input data string shown in the lower portion of the screen. Select the start position within the string you wish to use to create the portion of the account code at this level.

Portion Of Rule Data To Use - Length

This relates to the input data string shown in the lower portion of the screen. Select the length of the input data string you wish to use, commencing at the start position, to create the portion of the account code at this level.

Convert?

0 - No data conversion will take place. The actual data contained in the portion of the input data string specified by start position and length will become part of the generated account code.

1 - Conversion is required. Providing that a data conversion code is attached to this account code rule, the input data will be converted to output data via the rule defined under the conversion code.

Conversion code rules are defined against account code rules and are detailed in section Data Conversion Codes.

If you are setting up this account code rule against a ledger (i.e. profit & loss, balance sheet) you may use up to nine levels to modify the input data string to create the account code. The levels used relate to the level structure defined for this ledger.

If you are setting up this account code rule against a template you may use the number of levels defined in the template specified, up to a maximum of nine levels. In this case the levels bear no relation to the level structure for the account code being generated.

If you are using neither ledger nor template you may use only Level 1 at which to modify your input data string to define your account code.

+

The + sign indicates that you may use Roll keys either to roll between overwrite levels, or to roll between elements of the input data string. To switch between the two 'roll' facilities place the cursor in the relevant portion of the screen.



Press **Enter** to update the data files when the required entries or amendments have been made.

Account Rule Maintenance Output for ABC Screen

```
FI030          Advanced Financial Integrator  User TESTQA      18/09/96
Current Application.: Inventory                11:29:28
Account Rule Maintenance                       *UPDATE

Account generation rule PLC CG Stock movement rule one      (RULE OUTPUT)

Target Company. . ? Z1
Entry key . . . . ? 107 Inventory Cost to COC

Level                Portion of rule data to use  Convert?
                   Start position  Length  (0/1)
1 (Line Number)      1           6        0
2 (Performing ALO)    1           6        0
3 (Receiving ALO)     13          2        1
4 (Line Number - Perform) 1           6        0

(RULE INPUT) Rule data format...: AAAAAAAAAAABB.....
A Default GL Account          1 for length of 12
B Stockroom Code              1 for length of  2

F3=Exit  F4=Prompt  F12=Previous

00-25  SF  MM  KS  IM  II  KENB20A  PET179S2
```

Fields:

Target Company

This specifies the target company for which this rule will generate a code. Any code generated by this rule must exist in this company.

Entry Key

Enter the key which determines how the data is to be formatted in Advanced Business Costing. This key is not used by AFI, but will be used to format the posting when it arrives in ABC.

Entry keys are set up as parameter 'K0' in ABC.

Only entry keys that apply to all relative fiscal years can be referenced, as it is not possible to select the fiscal year here.

Level

This non-input field displays the four levels at which you may modify portions of the input data string to create or modify the code. The four levels include two 'lines' (generally, a kind of revenue, expense, or a value such as a number of hours), and two 'ALOs' (allocation objects, usually a cost centre, department etc.).

Against each level to be used you may specify a start position, length, and whether the data is to be converted.

Portion Of Rule Data To Use - Start Position

This relates to the input data string shown in the lower portion of the screen. Select the start position within the string you wish to use to create the portion of the account code at this level.

Portion Of Rule Data To Use - Length

This relates to the input data string shown in the lower portion of the screen. Select the length of the input data string you wish to use, commencing at the start position, to create the portion of the account code at this level.

Convert?

0 - No data conversion will take place. The actual data contained in the portion of the input data string specified by start position and length will become part of the generated account code.

1 - Conversion is required. Providing that a data conversion code is attached to this account code rule, the input data will be converted to output data via the rule defined under the conversion code.

Conversion code rules are defined against account code rules and are detailed in section Data Conversion Codes.



Press **Enter** to update the data files when the required entries or amendments have been made.

Data Conversion Codes



4/FIM

A data conversion code is attached to an account code generation rule, and specifies how the input data from the source application will be converted to form all or part of the generated account code.



Take the *Data Conversion Codes* option to display a window of account rules for which data conversion codes can be defined. Select the rule you want to update.

The next screen you see depends on whether you are posting to the General Ledger or to Advanced Business Costing.

If you are maintaining conversion data for a General Ledger account rule, then you will see the Conversion Data Maintenance - GL screen.

If you are maintaining conversion data for an Advanced Business Costing account rule, then you will see the Conversion Data Maintenance - ABC screen.

Conversion Data Maintenance GL Screen

If you are maintaining conversion data for a General Ledger account rule, then you will see the Conversion Data Maintenance - GL screen.

You may now define the levels at which conversion is to take place, the input data string to be converted and the returned substring (i.e. output data).

```
FI041                      Advanced Financial Integrator  User TESTQA  19/09/96
Current Application.: Inventory                      9:50:05
Conversion Data Maintenance

Rule 13 Rule 002
Target Application . . . . : GL General Ledger
GL Co. Z1 GL Ledger P/L Template

Level Convert from      Convert to
  █ _____

(No translate strings exist for this rule)

2=Change  4=Delete

-----
F3=Exit  F4=Prompt  F5=Refresh  F12=previous

10-04  SF  MK  KS  IM  II  KENB20A  PET179S2
```

Fields:

Unnamed (Select)

2 - Change an entry.

4 - Delete an entry.

Level

This corresponds to the levels in use within the account code rule, up to a maximum of nine. However, if you are using neither a General Ledger nor a template to define your account level structure, then entries may only be made at Level 1. Other than this there is no restriction on the number of entries which may be made at each valid level.

Convert From

This defines the actual data contained in the input string at this level which is to be converted to the data shown in the 'Convert To' entry. The application will test for this data in the input string, and if a match occurs will convert it.

As the input string could contain a whole range of different values at this level, it may be necessary to specify a considerable number of data conversion operations, each with a 'Convert From' and a 'Convert To' entry.

If neither a ledger nor a template has been defined in the account code rule then there can only be Level 1 'Convert From' entries which are converted to the valid account codes defined in the 'Convert To' entries. In other words, without a ledger or

template specified on the account code rule, the results of data conversion can only be valid General Ledger account codes.

Convert To

This defines the actual data to which the input string will be converted, at this level, if a match occurs between the contents of the input data field from the source application and the 'convert from' data defined. The entry here can be of different length, larger or smaller, than the 'convert from' entry. For example A could be converted to '01', or 'BBBBB' to 2. However, the 'Convert To' entries must not exceed the maximum permitted length at this account level, as defined in the ledger or template specified on the account code rule.

If neither a ledger nor a template has been defined in the account code rule then the 'Convert To' entry must be a valid account code in the target General Ledger. A prompt is available.

This prompt is unavailable if either a ledger code or a template has been specified in the account code rule.



Press **Enter** to update the data files when the required entries or amendments have been made.

Functions:

F5

Refresh the contents of the screen after amendments have been made.

Conversion Data Maintenance ABC Screen

If you are maintaining conversion data for an Advanced Business Costing account rule, then you will see the Conversion Data Maintenance - ABC screen.

```
FI041          Advanced Financial Integrator  User TESTQA      18/09/96
Current Application.: Inventory                11:30:37
Conversion Data Maintenance

Rule      8 PLC CG Stock movement rule one
Target Application . . . . . : CG Cost Accounting
Target company. . . . . : Z1 Version 3 Demonstration Company
Entry Key . . . . . : 107 Inventory Cost to COC
Level Convert from      Convert to
  3 FG                  PURCH *****

2=Change  4=Delete
Level 1=Line No., 2=Performing ALO, 3=Receiving ALO, 4=Line No.(Perform)
F3=Exit   F5=Refresh  F12=Previous

10-04  SF  MK  KS  IM  II  KENB20A  PET179S2
```

You may now define the levels at which conversion is to take place, the input data string to be converted and the returned substring (i.e. output data).

Fields:

Unnamed (Select)

- 2 - Change an entry.
- 4 - Delete an entry.

Level

This corresponds to the levels in use within the account code rule:

- 1 - Line number
- 2 - Performing ALO (allocating object)
- 3 - Receiving ALO (allocating object)
- 4 - Line number (perform.)

There is no restriction on the number of entries which may be made at each valid level.

Convert From

This defines the actual data contained in the input string at this level which is to be converted to the data shown in the 'Convert To' entry. The application will test for this data in the input string, and if a match occurs will convert it.

As the input string could contain a whole range of different values at this level, it may be necessary to specify a considerable number of data conversion operations, each with a 'Convert From' and a 'Convert To' entry.

Convert To

This defines the actual data to which the input string will be converted, at this level, if a match occurs between the contents of the input data field from the source application and the 'convert from' data defined.

The entry here can be of different length, larger or smaller, than the 'convert from' entry. For example A could be converted to '01', or 'BBBBB' to 2. However, the 'Convert To' entries must not exceed the maximum permitted length at this level.



Press **Enter** to update the data files when the required entries or amendments have been made.

Functions:

F5

Used to refresh the contents of the screen after amendments have been made.

Templates

1... **2...** 5/FIM

This option is relevant only if you are posting to the General Ledger. It cannot be used for postings to Advanced Business Costing.


As an alternative to using account level definitions as set up within a ledger, you can define an account level template of your own with up to nine levels.

Using an account rule, as explained earlier, enables you to construct an account code using the elements of a data string. If the ledger associated with this account code provides account levels that you are happy to use, then specify that ledger when you create the account rule.

If that ledger's account levels are not satisfactory, then define the template here, and enter it when you create the definition.

The template enables you to subdivide the original account levels in any way you wish. You cannot change the order of the levels or omit sections, but you can amalgamate two levels, or divide a single level into two:

Original code: VEH - Company Vehicles



Take the *Templates* option to display a window listing the existing templates. If you wish to enter a new template, press **F18** to see the Account Template Maintenance screen.

Account Template Maintenance Screen (F18)

If you wish to enter a new template, press **F18** to see the Account Template Maintenance screen.

```
FI035          Advanced Financial Integrator  User TESTQA      18/09/96
Current Application.: Inventory              11:31:41
Account Template Maintenance

Please specify the ID of the template you wish to create, and press ENTER.

GL Company . . . . ? Z1
Template Code. . . . 004

F3=Exit  F4=Prompt  F12=Previous

08-25  SF  MK  KS  IM  II  KENB20A  PET179S2
```

Fields:

GL Company

Enter the company the template is to apply to.

Template Code

Enter a code for the new template.



When you press **Enter** you will see the Template Maintenance screen. This is also the screen which will be shown if you select a template from the initial list, without pressing **F18**.

Template Maintenance Screen

When you press **Enter** you will see the Template Maintenance screen. This is also the screen which will be shown if you select a template from the initial list, without pressing **F18**.

FI035		Advanced Financial Integrator		User TESTQA	18/09/96
Current Application.: Inventory					11:32:11
Template Maintenance					*ADD
Template code 004 <u>Change from 999-99 to 9-9-99-9</u> GL co. Z1					
Level	No.	Description	Level Length	Extension Code	
	1	Account prefix	1	0	
	2	Account group	1	0	
	3	Customer class	2	1	
	4	Item type	1	1	
	5				
	6				
	7				
	8				
	9				
F3=Exit F11=Delete F12=Previous					
16-18 SF MK KS IM II KENB20A PET179S2					

Fields:

Template Code

Enter a description for the template.

Description

A description can be maintained for the template as a whole and for each level within the template. The descriptions are for informational purposes only.

Level Length

Specify the length of the data field at each level. The sum of the lengths of data fields at each level defines the length of the account code and must not exceed 42 characters.

Extension Code

The extension code fields are displayed if you use extension codes in your chart of accounts.

0 - This source level is from the first 12 characters of the account. At least one level must be from the first 12 characters.

1 - This source level is from the extension of the account.

All the primary account code levels must come first.



Enter is used to update the data files when the required template definition entries or

amendments have been made.

Functions:

F11

Used to delete an existing template definition.

Relative Fiscal Year Periods



6/FIM

This option is relevant only if you are posting to Advanced Business Costing.

It enables you to define the linkage between an accounting period and a relative fiscal year period. This is necessary because the first period of a year may not be period 1 (it would be 4, for example, if the fiscal year starts in April).



Take the *Relative Fiscal Year Periods* option, and on the first screen select a company (leave blank to maintain the default). Press **Enter** to see the Period to Relative Fiscal Year Maintenance Screen.

Period to Relative Fiscal Year Maintenance Screen

Take the Relative Fiscal Year Periods option, and select a company. Press **Enter** to see the Period to Relative Fiscal Year Maintenance screen.

F1050

Advanced Financial Integrator

User TESTQA

18/09/96
11:35:18

Period to Relative Fiscal Year Maintenance

Cost Accounting company : Z1 Version 3 Demonstration Company

Source	Target
Period	RFY Period
9301	B 9301
9302	B 9302
9303	B 9303
9304	B 9304
9305	B 9305
9306	B 9306
9307	B 9307
9308	B 9308
9309	B 9309
9310	B 9310
9311	B 9311
9312	B 9312
9313	B 9313

More...

F3=Exit

09-03

SF

F12=Previous

ML

KS

IM

II

KENB20A

PET179S2

Fields:

Source Period

Enter the source periods for the relevant year.

Rfy

Enter the relative fiscal year. This is set up within the Advanced Costing application, and consists of a start and end date. The relative fiscal year has a one-character code.

Target Period

Enter the fiscal year period targeted by each source period.



Press **Enter** to update.