

-
-
-
-
-

Chapter 3

Output Formats



Output Formats Overview

Output formats define the way in which information is presented in reports. They indicate where the data dictionary fields should be positioned and what free-format text should appear on the finished report.

Formats may be specific to a report or common across several reports.

There are three types of format:

- Heading - used mainly for the report title and for column heading



Note: Detail - generally containing the values of General Ledger accounts or groups of accounts



Note: Total - used to display totals within a report




Note: Remember that a report is printed from an RPG program which is compiled from a report specification. Therefore, if you amend a format, you must also confirm the update, and generate a program source, for each report in which the format is used.

Heading, Detail and Total report formats are all entered in the same way, although they serve different purposes and require different data fields. Therefore, the only way of distinguishing between format types is from the name you give them. It is suggested you put an H in front or at the end of Heading formats, a D in front or at the end of Detail formats and a T in front or at the end of Total formats.

This section will begin by explaining the different types of field available for use within a report, then the paths you should take to maintain such fields, and finally an example of the maintenance of all three format types so as to create a report.

Paths to Format Definition

The following chart shows which paths you can take to create report formats.



Heading Format Maintenance

This procedure shows how you can set up a format which controls the headings you intend to have in the specific report and is usually used for the report title and column headings.

Maintain Output Formats Selection Screen

This screen enables you to enter the name of the Heading format, or enter or prompt on an existing format to maintain



Select the option to maintain Output Formats.

FM020	E1 - Demonstration Company	USER ED3	6/01/94 10:03:00
-------	----------------------------	----------	---------------------

Maintain Output Formats

Format name ? DEMOH _____

Based on format ? _____

Format for heading . . ? _____

F3=Return to menu F4=Prompt

Fields:

Format Name

Enter the name of the Heading format, or enter or prompt on an existing format to maintain.



Note: It is suggested you put an H as the first or last character of the heading format name so that you can identify heading formats. Remember, all three format types are created and maintained in the same way.

Based On Format

If you are creating a new format that is to be very similar to another existing format, you can enter the name of that other format and it will make a copy of it under the new name. You can then go on to modify it.

Format For Heading

Not normally used for creation of heading formats.



Having entered a format name, press **Enter** and you are taken to the Maintain Output Formats - Detail Screen.

Maintain Output Formats Detail Screen

This screen enables you to enter the details of the output format you wish to maintain.



This screen is displayed when you have entered a format name in the Maintain Output Formats Selection Screen and pressed **Enter**.

RW020	E1 - Demonstration Company	USER ED3	6/01/94 10:03:22
Maintain Output Formats			
Format name	DEMOH		
Description	Demonstration Header		
No. of lines in format	5		
Print on new page?	1 (1=Yes, 0/Blank=No)		
Characters per line	132 (198 maximum)		
Currency type	0 (0=Base, 1=Transaction)		
Currency	GBP (Leave blank for all currencies of type entered)		
F3=Return to menu F4=Prompt F12=Previous			

Fields:

Description

Enter a description for the format of up to 50 characters in length. This description is not used in any generated report.

No. Of Lines In Format

Enter the number of lines you want to make use of in order to define the format. 1 to 12 lines may be used.

Print On New Page?

This is used mainly on Heading formats.

Enter a 1:

- To print this format when a page change occurs as a result of a 'page overflow', i.e. when a page is full.

or:

- To force a page change when this format is specified in a report.

Characters Per Line

Enter the number of characters you want to have on a line in the report. Normally 132 for standard stationery. Use 70 - 80 for standard characters on A4 stationery. Use up to 198 for compressed print.



The following two entry fields only appear if General Ledger is maintaining prime period balances:

Currency Type

Enter 0 for the header format.

Currency

Leave blank for the header format.



Normally you would enter 5 - 10 lines to allow space for column headings.



Having entered the details, press **Enter** to proceed to the Create Format DEMOH Fields Screen.

Create Format DEMOH Fields Screen

On this screen you can enter literal fields and variable fields. A Heading format is likely to include:

- Literals for the title of the report, headings of columns, date, time, page number, etc.
- Variables for date, time, etc., from the data dictionary.



This screen is displayed when you have entered the details in the Maintain Output Formats - Detail Screen and pressed **Enter**.

```

Create Format.. DEMOH
.....10.....20.....30.....40.....50.....60.....70.....
Date ***** ** ***** Page ****
Period ****

Account No          Current          Previous          Variance
                   Month             Month

F3=Return to format entry  F5=Change window pos      F12=Previous
F14=Display fmt details   F17=Select dict fields    F23=Cancel changes
01 CMPNY_CODE 02 CMPNY_NAME 03 PAGE_NO 04 PST_PERIOD 05 RUN_DATE
  
```



Press one of the following function keys.

Functions:

F5

Allows you to move the format layout along to the position you want.

The edit screen normally displays the left-most 80 characters in the format. Press F5 and a Current Window Position field appears at the top left-hand corner. Enter a number in this field and press Enter. The window position number defines the position of the left-most edge of the screen. Thus, enter 53 and the screen will shift along to display positions 53 to 132 of the format.

F14

Allows you to view and modify fields you have set up within this format.

F17

Allows you to select data dictionary fields to use in the format.

F23

Allows you to cancel the changes you have made to the format by entering F23 twice.

Once you have finished maintaining the Heading format, press **F3** to return to the initial Maintain Output Formats screen to enter further formats.

Financial Manager provides field positioning techniques within the format. This is examined in 'Formatting and Examining Fields'.

Detail Format Maintenance

This procedure shows how you can set up a format for a detail line.

Detail formats are used to specify:

- The descriptive and value data to be printed for the accounts included in the report.
- The accumulation of totals.

Maintain Output Formats Screen

This screen enables you to create a new format or maintain an existing one.



Select the option to maintain Output formats.

FM020	E1 - Demonstration Company	USER ED3	6/01/94 10:14:25
Maintain Output Formats			
Format name ? DEMOD			
Based on format . . . ?			
Format for heading . . ? DEMOH			
F3=Return to menu F4=Prompt			

Fields:

Format Name

Enter the name of the detail format, or enter or prompt on an existing format to maintain.



Note: It is suggested you put a D as the first or last character of the detail format name so that you can identify detail formats at a glance. Remember, all three format types are created and maintained in the same way.

Based On Format

To create a format similar to an existing format, enter the name of that existing format and it will make a copy of it under the new name. You can then go on to modify it.

Format For Heading

Enter the name of a related Heading format if you want to use it to align fields and columns in this format to the headings within the heading format.

The format for heading will appear at the top of the edit screen so that you can work beneath it.



Note: The format for heading is only used as a guide to help you, and need not necessarily appear with the detail format you maintain.



Having entered a format name, press **Enter** and you are taken to the Maintain Output Formats Details Screen.

Maintain Output Formats Details Screen

This screen enables you to enter the details of the format.



This screen is displayed when you have entered a format name in the Maintain Output Formats - Formats Screen and pressed **Enter**.

RW020	E1 - Demonstration Company	USER ED3	6/01/94 10:14:46
Maintain Output Formats			
Format name	DEM0D		
Description	Demonstration Detail		
No. of lines in format	2		
Print on new page?	(1=Yes, 0/Blank=No)		
Characters per line	132 (198 maximum)		
Currency type	0 (0=Base, 1=Transaction)		
Currency	GBP (Leave blank for all currencies of type entered)		
F3=Return to menu F4=Prompt F12=Previous			

Fields:

Description

Enter a description for the format of up to 50 characters in length. This description is not used in any generated report.

No. Of Lines In Format

Enter the number of lines you want to make use of in order to define the format. Zero to 12 lines may be used. Zero lines are used for non-printing detail or total formats.

For example, a Detail format single spaced would require one line; a double spaced Detail format has two lines.

Print On New Page?

This is used mainly on Heading formats.

Enter a 1:

- To print this format when a page change occurs as a result of a 'page overflow', i.e. when a page is full.

or:

- To force a page change when this format is called in a report.

Characters Per Line

Enter the number of characters you want to have on a line in the report. Normally 132 for standard stationery. Use 70 - 80 for standard characters on A4 stationery. Use up to 198 for compressed print.



The two fields 'Currency Type' and 'Currency' will only appear if the General Ledger company profile field 'Maintain Prime Currency Balances' is set to 1.

Within format maintenance, the currency fields are relevant to balances in respect of prime currencies. Currency translation fields are maintained within report specification, or are input at runtime.

Provided prime currency balances are being maintained, data dictionary items 'PE.....' (Prime Equivalent) and 'PR.....' (Prime Currency) can be included in any format regardless of the setting of format currency fields.

Currency Type

Enter 0 to print the format only once for each account.

Enter 1 to print the format once for every prime period balance that accrues on each account.

Currency

Enter the code of the base currency if the 'Currency Type' is set to 0, otherwise enter the currency to be printed. The format will be printed once for an account for the currency (prime period balance) specified.



Having keyed in the details, press **Enter** to proceed to the Create Format - DEMOD - Literal and Variable Screen.

Create Format DEMOD Literal and Variable Screen

On this screen you can enter literal fields and variable fields. A detail format is likely to include:

- Data dictionary fields to appear as columns of figures or characters.
- Accumulators to print as sub-totals.

It will probably be used several times in the completed report.



This screen is displayed when you have entered the details of the format in the Maintain Output Formats - Details Screen and pressed **Enter**.

Create Format.. DEMOD			
.....10.....20.....30.....40.....50.....60.....70.....			
Date *****	** *****		Page ****
Period ****			
Account No	Current Month	Previous Month	Variance
*****	999999999999,99-	999999999999,99-	999999999999,99-

F3=Return to format entry	F5=Change window pos	F12=Previous
F14=Display fmt details	F17=Select dict fields	F23=Cancel changes
01 AC_COD_12	02 BS_NET_ACT	03 MONTH VAR



Press one of the following function keys.

Functions:

F5

Allows you to move the format layout along to the position you want.

The edit screen normally displays the left-most 80 characters in the format. Press F5 and a Current Window Position field appears at the top left-hand corner. Enter a number in this field and press Enter. The window position number defines the position of the left-most edge of the screen. Thus, enter 53 and the screen will shift along to display positions 53 to 132 of the format.

F14

Allows you to view and modify fields you have set up within this format, and to set up accumulators.

F17

Allows you to select data dictionary fields to use in the format.

F23

Allows you to cancel the changes you have made to the format by entering F23 twice.

Once you have finished maintaining the Detail format, press **F3** to return to the initial Maintain Output Formats screen to enter further formats.

Total Format Maintenance

This procedure shows how you can set up a format which controls the totals that will appear at the base of a report. They are positioned beneath and in line with the columns of values above them, which are calculated and displayed according to their definition in the detail format.

Maintain Output Formats Selection Screen

This screen enables you to create a new format or maintain an existing one.



Select the option to maintain Output Formats and the selection screen is displayed.

FM020	E1 - Demonstration Company	USER ED3	6/01/94 11:11:54
Maintain Output Formats			
Format name ? <u>DEMOT</u>			
Based on format . . . ? <u> </u>			
Format for heading . . ? <u>DEMOH</u>			
F3=Return to menu F4=Prompt			

Fields:

Format Name

Enter the name of the detail format, or enter or prompt on an existing format to maintain.



Note: It is suggested you put a T as the first or last character of the total format name so that you can identify total formats at a glance. Remember, all three format types are created and maintained in the same way.

Based On Format

If you are creating a new format that is to be very similar to another existing format, you can enter the name of that other format and it will make a copy of it under the new name. You can then go on to modify it.

Format For Heading

Enter the name of a related heading format if you want to use it to align fields and columns in this format to the headings within the heading format.

The format for heading will appear at the top of the edit screen so that you can work beneath it.



Note: The format for heading is only used as a guide to help you, and need not necessarily appear with the total format you maintain.



Having entered a format name, press **Enter** and you are taken to Maintain Output Formats Screen 2.

Maintain Output Formats Screen 2

This screen enables you to enter details about the format.



This screen is displayed when you have entered a format name in the Maintain Output Formats Selection Screen and pressed **Enter**.

RW020	E1 - Demonstration Company	USER ED3	6/01/94 11:12:03
Maintain Output Formats			
Format name DEMOT			
Description : <u>Demonstration Total</u>			
No. of lines in format : <u>5</u>			
Print on new page? . . . : (1=Yes, 0/Blank=No)			
Characters per line . . : <u>132</u> (198 maximum)			
Currency type : 0 (0=Base, 1=Transaction)			
Currency ? <u>GBP</u> (Leave blank for all currencies of type entered)			
F3=Return to menu F4=Prompt F12=Previous			

Fields:

Description

Enter a description for the format of up to 50 characters in length. This description is not used in any generated report.

No. Of Lines In Format

Enter the number of lines you want to make use of in order to define the format. Zero to 12 lines may be used. Zero lines are used for non-printing total formats.

For example, a total format single spaced would require one line; a double spaced total format has two lines.

Print On New Page?

This is used mainly on Heading formats.

Enter a 1:

- To print this format when a page change occurs as a result of a 'page overflow', i.e. when a page is full.

or:

- To force a page change when this format is called in a report.

Characters Per Line

Enter the number of characters you want to have on a line in the report. Normally 132 for standard stationery. Use 70 - 80 for standard characters on A4 stationery. Use up to 198 for compressed print.

-  The following two entry fields only appear if General Ledger is maintaining prime period balances.

Currency Type

This field is not relevant to total formats - enter 0.

Currency

This field is not relevant to total formats - leave blank.

-  Normally you would enter at least 3 lines in the format to allow for space between the detail and total on the report; you may also want to include underlines. Ensure the number of characters per line tallies with the heading or detail format.
-  Having keyed in the details, press **Enter** to proceed to Create Format Screen 3.

Create Format Screen 3

On this screen you can enter literal fields and dictionary items, or specify accumulators to be printed. A total format is likely to include:

- Literals such as underlines above and beneath the total figures, and a description, e.g. Grand Total
- Accumulators to take added values and display them as totals



This screen is displayed when you have entered details in the Maintain Output Formats Screen 2 and pressed **Enter**.

```

Create Format.. DEMOT
.....10.....20.....30.....40.....50.....60.....70.....
Date ***** ** ***** Page ****
Period ****

Account No          Current      Previous      Variance
                    Month         Month

-----
Grand Total  999999999999,99-  999999999999,99-  999999999999,99-
-----

```

F3=Return to format entry F5=Change window pos F12=Previous
F14=Display fmt details F17=Select dict fields F23=Cancel changes

Functions:

F5

Allows you to move the format layout along to the position you want.

The edit screen normally displays the left-most 80 characters in the format. Press F5 and a Current Window Position field appears at the top left-hand corner. Enter a number in this field and press Enter. The window position number defines the position of the left-most edge of the screen. Thus, enter 53 and the screen will shift along to display positions 53 to 132 of the format.

F14

Allows you to view and modify fields you have set up within this format, and to set up accumulators.

F17

Allows you to select data dictionary fields to use in the format.

F23

Allows you to cancel the changes you have made to the format by entering **F23=Cancel Charges** twice.



Once you have finished maintaining the total format, press **F3=Exit** to return to the initial Maintain Output Formats - Selection Screen to enter further formats.

Literal Fields

This procedure shows you how to enter, move and delete text which will appear on every report which uses that format.

You enter literals from the Create Format screen, which displays the report format.



To enter literal data on this screen, key in an apostrophe (') to open the field, then the characters of the literal, and finally a second apostrophe (') to end the field.

```
Create Format.. DEMOH
.....10.....20.....30.....40.....50.....60.....70.....
'Date'  *****  **  *****'Page' ****
'Period' ****

'Account No'      'Current'      'Previous'      'Variance'
                  'Month'        'Month'

F3=Return to format entry  F5=Change window pos      F12=Previous
F14=Display fmt details   F17=Select dict fields  F23=Cancel changes
01 CMPNY_CODE 02 CMPNY_NAME 03 PAGE_NO 04 PST_PERIOD 05 RUN_DATE
```



Note: Literal fields can only be entered line by line. A literal cannot extend to a second line.



Having keyed in the literals, press **Enter** and the apostrophes disappear to leave the literals as shown in the next screen.

To remove a literal once defined, enter D immediately to the left of the literal and press **Enter**.

Functions:

F14

Display the format in tabular form. This includes the position of each item in the format, and a relevant description for non-literal items.

Variable Fields

Variable fields access current system data such as balances, dates, times, etc. for the date/period span which you decide to specify.

Variable fields consist of four types of field:

- Data dictionary via **F17=Select Dict Fields**.
- Data dictionary via direct entry.
- Accumulators.
- Calculated fields.

The following sections show how these variable fields can be accessed and created.

Selecting Data Dictionary Fields (F17)

The data dictionary is used to feed data into those data dictionary fields you choose to use in a report.



To make use of the data dictionary fields, press
F17=Select Dict Fields from the Create Format
Screen 3 to display this screen.

RW040	E1 - Demonstration Company	USER ED3	6/01/94 10:04:28
Select Data Dictionary Fields.			
'1'	Field Name	Description	
-	BS_PCR_ACT	Base Currency Period Credits	
-	BS_PDB_ACT	Base Currency Period Debits	
-	BS_RBD_BD1	Base Currency Revised Budget 1	
-	BS_RBD_BD2	Base Currency Revised Budget 2	
-	BS_YCR_ACT	Base Currency Fiscal Year-to-date Credits	
-	BS_YDB_ACT	Base Currency Fiscal Year-to-date Debits	
-	BS_YNT_ACT	Base Currency Fiscal Year-to-Date	
-	BS_YNT_BD1	Base Currency Fiscal Year-to-date Net Budget 1	
-	BS_YNT_BD2	Base Currency Fiscal Year-to-date Net Budget 2	
I	CMPNY_CODE	Company Code	
I	CMPNY_NAME	Company Name	
-	LN_TXT_10	Line Text (10 Characters)	
-	LN_TXT_20	Line Text (20 Characters)	
-	LN_TXT_30	Line Text (30 Characters)	
-	LN_TXT_40	Line Text (40 Characters)	
-	LN_TXT_50	Line Text (50 Characters)	
1=Select field			
F12=Previous			

Fields:

Sel

1 - Select the data dictionary fields whose data you want to have access to so that it will appear in a generated report. You can choose as many fields as you like.

Roll Up or Down to view all the data dictionary fields.



Once you have selected the appropriate data
dictionary fields, press **F12=Previous** and you
are returned to the Create Format Screen 3.

```

Create Format.. DEMOH
.....10.....20.....30.....40.....50.....60.....70.....
'Date' &5          &1  &2          'Page'
'Period' &4
_____
_____
_____
_____

F3=Return to format entry  F5=Change window pos      F12=Previous
F14=Display fmt details    F17=Select dict fields    F23=Cancel changes
01 CMPNY_CODE 02 CMPNY_NAME 03 PAGE_NO    04 PST_PERIOD 05 RUN_DATE

```

The data dictionary fields you have selected are shown at the base of the Create Format - Screen 3, and have been allocated numbers. If you have selected more than five data dictionary fields, use the Roll Keys to see the remaining ones.

To insert one of the data dictionary fields into the format, key an ampersand (&) in the first position on the screen the field is to occupy, followed by the number allocated to the data dictionary field you want. Press **Enter** and the number of characters ready to accept variables in the field are displayed.

- If the variable field accesses an alphanumeric data dictionary field, the characters of the field are displayed as a series of asterisks (*s)
- If the variable field accesses a numeric data dictionary field, the characters of the field are displayed as a series of nines (9s). If the field is negative, a minus sign is displayed

An alphanumeric field would be displayed as asterisks.

Data Dictionary Variable Screen

RW050	E1 - Demonstration Company	USER ED3	6/01/94 11:14:34
-------	----------------------------	----------	---------------------

Data Dictionary Variable

Either enter the variable's name . . . : _____ Or select from below.

Opt	Type	Field name	Description
-	System	AC_COD_12	Account Code (12 Characters)
-	System	AC_COD_20	Account Code (20 Characters)
-	System	AC_COD_30	Account Code (30 Characters)
-	System	AC_COD_40	Account Code (40 Characters)
-	System	AC_COD_50	Account Code (50 Characters)
-	System	AC_DSC_20	Account Description (20 Characters)
-	System	AC_DSC_30	Account Description (30 Characters)
-	System	AC_DSC_40	Account Description (40 Characters)
-	System	AC_DSC_50	Account Description (50 Characters)
-	System	AC_DSC_60	Account Description (60 Characters)
-	System	AC_DSC_70	Account Description (70 Characters)
-	System	AC_DSC_79	Account Description (79 Characters)
-	System	AC_LCD_V1	Account Level Code for Position 1 in View
-	System	AC_LCD_V2	Account Level Code for Position 2 in View

1=Select field
F3=Cancel selection of field
F12=Previous

If you select a data dictionary field which is alphanumeric, and enter a 1 against it, you are taken back to the edit screen where the variable characters of the field appear as asterisks in the report format.

If you select a numeric data dictionary field, the next screen appears allowing you to enter further parameters.

RW050	E1 - Demonstration Company	USER ED3	11/10/94 14:36:54
-------	----------------------------	----------	----------------------

Data Dictionary Numeric Variable

Column number : 01
Variable name : ES_NET_ACT
Accumulate into : 001
Print commas? (0/1) : 0 Edit negatives with Blank, (, - or C . . : -
Print only if credit? (0/1) : 0 Print only if debit? (0/1) : 0
Print zero values? (0/1) : 1
Period modifier : 0 or Period . . : 00 & year modifier 0
Account modifier : ***** Budget code . ?
Company modifier : Currency . . ?

Type	Field name	Description
System	AC_COD_12	Account Code (12 Characters)
System	AC_COD_20	Account Code (20 Characters)
System	AC_COD_30	Account Code (30 Characters)
System	AC_COD_40	Account Code (40 Characters)
System	AC_COD_50	Account Code (50 Characters)
System	AC_DSC_20	Account Description (20 Characters)
System	AC_DSC_30	Account Description (30 Characters)

F3=Cancel field selection F4=Prompt F12=Previous F19=Sector Modifier

Fields:

Column Number

The column number, normally allocated automatically, is unique within a format. It is used when specifying accumulators and in calculations, and has no effect on the positioning of fields in the format.

It is suggested that columns 90 - 99 be used for 'work fields'.

Variable Name

This is the name of the data dictionary field used for this column. It is displayed if previously selected, or may be entered if this is a new field. A list of data dictionary fields is displayed at the foot of this screen.

Accumulate Into

Enter the accumulator number (01 - 99) into which the value of this field is to be accumulated. The value accumulated will be printed from another format ('Total') later in the report.

Print Commas

Enter 1 to print the value with commas separating the thousands, e.g. 1,426.65.

Enter 0 to print without separators, e.g. 1426.25.



Note that this decision will affect column spacing on the report.

Edit Negatives With Blank

This defines the editing of negative values. Assume a value of -156.23:

Blank prints with no sign:	156.23
(" with brackets:	(156.23)
- " trailing minus:	156.23-
C " trailing CR.:	156.23CR

Print Only If Credit

Leave as 0 if the value is to be printed as calculated. Enter 1 if the value is to be printed only if negative. If it is not negative, the field prints as a blank.

Print Only If Debit

Leave as 0 if the value is to be printed as calculated. Enter a 1 if the value is to be printed only if positive. If not positive, the field prints as a blank.

Print Zero Values?

Enter a 0 if you want to print a zero value as blank spaces, or leave as 1 if you do want to print zero values.

Period Modifier

If the values are to be obtained from a period earlier or later than the reporting period, enter the number of offset periods necessary to obtain those values. A trailing minus - indicates an earlier period, e.g. '13-'.

Period

The period from which values are to be retrieved, if not the reporting period. Enter the actual period number, e.g. '01' for the first period.

To use a period in another year, see the 'Year modifier' field. (See also 'Period modifier').

Year Modifier

If the period number is not in the current year, enter a 'year modifier'.

Enter the number of years offset, with a trailing minus for prior years.

For example:

'1-' is last year.

1 is next year.

So, period '12', modified '1-', is period 12 of last year.

Account Modifier

If the account from which the data is to be taken is different from that which will be associated with the format in the report, use an account modifier.

Financial Manager will generate an account from which the data is to be taken by replacing the asterisks of the account modifier with the characters in the levels of the account associated with the format.

For example, there may be two accounts in the General Ledger, 001456 and 002456; the first applies to cost centre 001, the second to cost centre 002.

Both these accounts may be printed on the same format by associating 001456 with the format in the report, and specifying an account modifier of 002***** in the column to print the value from account 002456.

Budget Code

If a budget item has been selected from the data dictionary, it is necessary to enter the budget code and type here.

If the budget code and type are not entered here, then the ones displayed or entered at runtime will be used.

Budget Type

Valid budget types are as follows:

0 - Forecast

1 - Budget

2 - Quantity forecast

3 - Quantity budget

4 - Currency forecast

5 - Currency budget

If a budget item has been selected from the data dictionary, it is necessary to enter the budget code and type here.

If the budget code and type are not entered here, then the ones displayed or entered at runtime will be used.

Company Modifier

If this is left blank, the values are taken from the company for which the report is run. If you enter a company code, the values are taken from the accounts or views in the specified company.

Currency

If the detail format specified a currency, that currency will be the default here. This may be changed if necessary.



Use the Roll Keys to view further data dictionary fields at the base of the screen.

Functions:

F19

Allows you to access views or X-ledger views



Having entered data into the parameter fields, press **Enter** and you are returned to the Create Format (or Maintain Format) screen where the numerics of the selected field are indicated by a row of nines beginning from the plus sign you entered.

Direct Entry Defining Accumulators

Accumulators are used to total detail lines, and for accumulating these totals into grand total. There are 999 accumulators available.

How the Accumulator works

If an accumulator is specified on a detail line, it takes the value in the detail field it is accumulating, and adds it to the value it already holds. This means that it holds a running total.

Values Posted	Value Posted Running Total
100.00	100.00
250.00	350.00
1250.00	1600.00
1500.00	3100.00
50.00	3150.00
520.00	3670.00

Each time a net posted value is accessed in order to have it displayed in the net posted field in the report, it is also added to the specified accumulator so that the running total of the net posted values can appear in the accumulator field in the report.

To make use of this facility you will have to:

- Specify an accumulator against the item.
 - Specify the numerator as an item in the format.
-  From the Create Format (or Maintain Format) screen, enter a plus sign (+) in the first position the accumulator field is to occupy and press **Enter**. The Include Variable in Format screen is displayed.

Include Variable in Format Screen

RW050	E1 - Demonstration Company	USER ED3	6/01/94 11:14:37
-------	----------------------------	----------	---------------------

Include Variable in Format

Type of variable to include . . . : 2 (1=Data dictionary field,
2=Accumulator,
3=Calculated field)

F12=Previous



2 - Select the Accumulator option by entering a 2 and press **Enter**. The Accumulated Variable screen is displayed.



Note: You can go straight to the next screen from the Maintain Format screen by entering a '+2' at the position you want the field to appear.

RW050	E1 - Demonstration Company	USER ED3	6/01/94 11:14:40
-------	----------------------------	----------	---------------------

Accumulated Variable

Column number : 02
Accumulator number : 100
Length to print : 15
Decimals to print : 2

Accumulate into accumulator . . : 1
Clear after printing? : 1 (0=No, 1=Yes)
Print only if credit? : 0 (0=No, 1=Yes)
Print only if debit? : 0 (0=No, 1=Yes)
Print zero values? : 1 (0=No, 1=Yes)

Print commas? : 0 (0=No, 1=Yes)
How to edit negatives : - (Blank, (, -, C)

F3=Cancel definition of field F12=Previous

Fields:

Column Number

The column number is unique within a format. They are used in accumulators and in calculations, and have no effect on the positioning of fields in the format. It is suggested that columns 90 - 99 be used for 'work fields'.

Accumulator Number

The number of the accumulator that is to be printed. The value held in this accumulator is determined by the value of the various fields accumulated into it in previous formats.

Length To Print

The number of digits to be printed, excluding the decimal point. The accumulator is held to an accuracy of 15 digits, 4 of these being decimal places.

Decimals To Print

The number of decimal positions in the value to be printed.

Accumulate Into Accumulator

The accumulator number (01 - 99) into which the value of this field is to be accumulated. The value accumulated will be printed from another format ('Total') later in the report.

Clear After Printing

If the accumulator is to be cleared after it has been printed, leave 1. If it is not to be cleared - for example, it is used as a running total - enter 0.

Print Only If Credit

Leave 0 if the value is to be printed as calculated. Enter a 1 if the value is to be printed only if negative. If not negative, the field prints a blank.

Print Only If Debit

Leave 0 if the value is to be printed as calculated. Enter a 1 if the value is to be printed only if positive. If not positive, the field prints a blank.

Print Zero Values?

Leave 1 if zero values are to be printed. Enter a 0 to print a zero value as blank (spaces).

Print Commas

1 - Print the value with commas separating the thousands, e.g. 1,426.65.

0 - Print without separators, e.g. 1426.25.



Note that this decision will affect the spacing of columns on the report.

How To Edit Negatives

This defines the editing of negative values. Assume a value of -156.23:

Blank prints with no sign: 156.23

(" with brackets: (156.23)

- " trailing minus: 156.23-

C " trailing CR: 156.23CR



Enter an accumulator number and press **Enter**.
You are returned to the Create Format - Screen
3 (or Maintain Format) screen where the
numerics of the field are listed as a row of nines
beginning from the position at which you entered
the plus sign.

Direct Entry Defining Calculated Fields

This procedure allows you to enter user-defined fields which perform calculations on values within data dictionary fields so as to display the results on the report.



From the Create Format Screen 3 (or Maintain Format) screen, enter a plus sign (+) in the first position the field is to occupy and press **Enter**. The next screen is displayed.

RW050	E1 - Demonstration Company	USER ED3	6/01/94 11:34:54
-------	----------------------------	----------	---------------------

Include Variable in Format

Type of variable to include . . . : 3 (1=Data dictionary field,
2=Accumulator,
3=Calculated field)

F12=Previous

Fields:

Sel

3 - Select a Calculated Field.



Note: You can go straight to the next screen from the Create Format (or Maintain Format) screen by entering a '+3' at the position you want the field to appear.



Press **Enter** and you are taken to the next screen, which displays the parameters necessary for the specification of a calculated variable.

Calculated Variable Screen

RM050		E1 - Demonstration Company		USER ED3	6/01/94 11:34:57
Calculated Variable					
Calculation	Op.	Column Number	OR	Numeric Literal	Valid Operations:
Column 03	=	01		.00	+ PLUS, - MINUS,
	-	02		.00	* TIMES, / DIVIDE BY,
				.00	% PERCENTAGE OF,
OR Column equals line total?(0/1): 0					
Accumulate into accumulator . . . : 200					
Format					
Length to print : 15 Decimals to print : 2					
Print only if credit?(0/1): 0 Only if debit?(0/1): 0 Print if zero?(0/1): 1					
Print dots? (0/1): 0 Edit negatives . . . : - (Blank, (, -, C)					
Column	Field	Description			
01	BS_NET_ACT	Base Currency Net			
02	BS_NET_ACT	Base Currency Net			
1=Select field					
F3=Cancel selection of field			F12=Previous		

Fields:

Column

The column number is unique within a format. They are used in accumulators and in calculations, and have no effect on the positioning of fields in the format. It is suggested that columns 90 - 99 be used for 'work fields'.

Calculation Number

The value of this column is used in the calculation. The column must already be defined. (It may of course be a work column).

Numeric Literal

The calculation may use a numeric constant, instead of data obtained from another column. If a constant is used, a column reference cannot be specified on the same line. For example, to inflate a value by 15%, multiply by 1.15.

Op

The arithmetic operators you can use are as displayed on the screen as +, -, /, *, %.

Calculations are performed from left to right; for example: ab - cd * ef is calculated (ab - cd) * ef.

Column Equals Line Total

If the value to be printed is the sum of all columns in the format, rather than a combination of nominated columns, enter 1. Otherwise, leave 0.

If 1 is entered, no calculations may be specified. Only one line total column can be specified in any output format.

Accumulate Into Accumulator

Enter the accumulator number (01 - 99) into which the value of this field is to be accumulated. The value accumulated will be printed from another format ('Total') later in the report.

Length To Print

Enter the number of digits to be printed, excluding the decimal point. The accumulator is held to an accuracy of 15 digits, 4 of these being decimal places.

Decimals To Print

Enter the number of decimal positions in the value to be printed.

Print Only If Credit?

Leave 0 if the value is to be printed as calculated. Enter 1 if the value is to be printed only if negative. If not negative, the field prints a blank.

Only If Debit?

Leave 0 if the value is to be printed as calculated. Enter a 1 if the value is to be printed only if it is positive. If it is not positive, the field prints as a blank.

Print If Zero?

Leave a 1 if zero values are to be printed. Enter a 0 to print a zero value as blank (spaces).

Print Commas

Enter 1 to print the value with commas separating the thousands, e.g. 1,426.65.

Enter 0 to print without separators, e.g. 1426.25.



Note that this decision will affect the spacing of columns on the report.

Edit Negatives

This defines the editing of negative values. Assume a value of minus 156.23:

Blank prints with no sign: 156.23

(" with brackets: (156.23)

- " trailing minus: 156.23-

C " trailing CR: 156.23CR



A calculated variable relies on the fields you are making use of in the report format. You can choose only these fields and they are displayed at the base of the screen.



Having entered data into the parameter fields, press **Enter** and you are returned to the Create Format (or Maintain Format) screen where the numerics of the selected field are indicated by a row of nines from the position at which you entered the plus sign.



Press **Enter**. If you have entered ?, a description is displayed at the bottom of the screen. If you entered *, a field specification is displayed.

Maintain Format DEMOD Screen 2

Maintain Format DEMOD		Demonstration Detail	
.....10.....20.....30.....40.....50.....60.....70.....	Date	*****	Page ****
Period	****		
Account No	Current Month	Previous Month	Variance
*****	999999999999,99-	999999999999,99-	?999999999999,99-
Calculated - Column 01 - Column 02			
Press ENTER to continue...			

The field type and a brief description is displayed.



Press **Enter** again and the description and question mark disappear from the screen.

Existing Field Maintenance

This procedure allows you to modify any data fields which already exist on a format. You might use this for the allocation of accumulators to numeric fields which were set up before their related accumulators were created.

You can maintain existing fields from the edit format screen in two ways:

- Directly from the edit screen
- From a list of fields in the report format



This screen is displayed when you press **F14=Display Fmt Details** from the Maintain Format screen.

```

RW060                      EI - Demonstration Company      USER ED3      6/01/94
                                           11:31:57

Maintain Fields In Format DEMOD

Opt Clm Acc Posn.  Field ID.  Field Definition
-   01   1  02/005 AC_COD_12  Account Code (12 Characters)
-   02  100 02/023 BS_NET_ACT  Base Currency Net
-   03  200 02/043 BS_NET_ACT  Base Currency Net
-   03  200 02/063 MONTH VAR   Monthly Variance

Enter '+' to add a work column. _ Type.. _ 1. Dictionary field. 2. Accumulator.
1=Modify. 4=Delete                      3. Calculated field.
F3=End format maintenance      F12=Previous
  
```

There are a number of columns containing the following fields which cannot be entered:

- Clm - The column number unique within the format which is allocated to a calculated field. No column number is given to an alphanumeric data dictionary field
- Acc - The accumulator into which values from this field will be fed
- Posn. - The position of this field on the format: line/position in line
- Field ID. - The name given to the field as its identification
- Field Definition - The descriptive name given to the field

Options

- Option 1 - Modify - Allows you to enter a 1 against any field you want to expand or make changes to
- Option 4 - Delete - Allows you to delete any field by entering a 4 against it

To proceed, enter a 1 against a field and you will be taken to the appropriate screen for the modification of that field and its field type. Therefore:

- For an alphanumeric data dictionary field you are taken to the list of all data dictionary fields for you to make another selection since you cannot modify alphanumeric fields
- For a numeric data dictionary field you are taken to the Data Dictionary Numeric Variable screen
- For an accumulator you are taken to the Accumulated Variable screen
- For a calculated field you are taken to the Calculated Variable screen



*Note: You cannot update a text field from this screen. If you enter a 1 against a field whose Field ID is Literal and press **Enter**, nothing will happen.*

Work Fields

A work field is used to perform calculations or accumulations for a report, which you do not want to see printed. As such, they can take the form of a calculated field or an accumulator field and be defined in the same way as you would define a normal calculated field or accumulator. However, since the field is not intended to occupy space on a report format, it is not allocated a line and column number but is flagged with the title 'Work' instead.

For example, you might want to produce a summary report detailing the total sales and total cost of sales of a range of divisions within your company, without printing details of the individual divisional sales figures. To do this, you would need an accumulator to accumulate divisional sales figures and divisional cost of sales figures. Because you do not intend to print the accumulated divisional details, you would use a work field as the accumulator.

Once the respective figures have been accumulated and two totals arrived at, the totals would be fed into another format - a detail format - which will print on the report.

Maintaining Work Fields

Work fields are defined from the Maintain Fields in Format screen.



To access this screen press **F14=Display Fmt Details** from the Create Format (or Maintain Format) screen.

RW060		E1 - Demonstration Company		USER ED3	6/01/94 11:37:24
Maintain Fields In Format DEMOD					
Opt	Cln	Acc	Posn.	Field ID.	Field Definition
-				02/005 AC_COD_12	Account Code (12 Characters)
-	01	1	02/023	BS_NET_ACT	Base Currency Net
-	02	100	02/043	BS_NET_ACT	Base Currency Net
-	03	200	02/062	Calculated	Column 01 - Column 02
Enter '+' to add a work column. ± Type.. 3 1. Dictionary field. 2. Accumulator. 3. Calculated field. 1=Modify, 4=Delete F3=End format maintenance F12=Previous					

Fields:

Add Work Column

A work column is a field which will be used in a calculation and is not printed. Enter a + in the first field and the number appropriate to the type of field you want to define in the following Type field.



Select one of the field types and press **Enter**. You are taken to the field definition screen for either a data dictionary numeric variable, a calculated variable or an accumulated variable where you can define the work field.

Having defined the work field, press **Enter** and the system returns you to the Maintain Fields in Format screen.

Maintain Fields In Format Screen Work Field

RW060	E1 - Demonstration Company	USER ED3	6/01/94 11:39:23
-------	----------------------------	----------	---------------------

Maintain Fields In Format DEMOD

Opt	Clm	Acc	Posn.	Field ID.	Field Definition
-				02/005 AC_COD_12	Account Code (12 Characters)
-	01	1	02/023	BS_NET_ACT	Base Currency Net
-	02	100	02/043	BS_NET_ACT	Base Currency Net
-	03	200	02/062	Calculated	Column 01 - Column 02
-	04		Work	Calculated	Column 03 % Column 02

Enter '+' to add a work column. _ Type.. _ 1. Dictionary field. 2. Accumulator.
3. Calculated field.
1=Modify. 4=Delete
F3=End format maintenance F12=Previous

The work field has been added to the list and is easily identifiable by the title 'Work' which has replaced the position number, since the field will not hold a position in a report.

Modifiers Maintenance

Modifiers are used to generate columns of values within a report for the purpose of comparison.

While creating a report structure, or at the time of running a report, you have the opportunity of modifying a set range of specified delimiters to produce separate columns in a report, or separate reports, with modified ranges.

When you modify a report's range of delimiters, you have a choice of the following modifiers:

- Period modifier - Allows you to offset the set period back by a specified number of periods

or

- Period & Year modifier - Allows you to modify the set period to a different specific period and offset the set year back by a specified number of years
- Account modifier - Allows you to change level codes or portions of level codes existing in the accounts of the set account range
- Company modifier - Allows you to change the company from the set company
- Sector modifier - Allows you to change level codes or portions of level codes existing in the views of the set view range. You can also modify level codes belonging to X-ledger views

The following example demonstrates how and why you might use the Account Modifier.

Setting an Account Modifier

You have three cost centres whose codes form a level within your company's account code structure. Your aim is to produce a report which has three columns of values. The first with net profit values pertaining to cost centre 01, the second to cost centre 02 and the third to cost centre 03

To do this you should use account modifiers, and should take the following steps

- 1. Maintain the Header format of the report and enter the headings for three columns of cost centre values.
- 2. Maintain the Detail format and specify the data dictionary field for *net profit* in three columns beneath the aforementioned headings.
- 3. While maintaining the Detail format fields, enter the parameter values for each *net profit* column.
 - *cost centre 1* has its **Account modifier** field left untouched as a line of asterisks representing the account levels: *****.
 - *cost centre 2* has the account level in the account code which denotes the cost centre modified to 02, ***02*****.
 - *cost centre 3* has the account level in the account code which denotes the cost centre modified to 03, ***03*****.

- 4. Run the report and specify the range of accounts you want to be printed. The range should only include *cost centre 01*. i.e. **From 01 To 01**.
- 5. When generating the report, the program will:
 - first pick up all net profit values for the range of accounts with cost centre 01 to be printed.
 - then substitute the cost centre level code of 01 for 02 and pick up all valid accounts for cost centre 02 to be printed.
 - then substitute the cost centre level code of 01 for 03 and pick up all valid accounts for cost centre 03 to be printed.
 - The report will then make it easy for you to compare net profit values across the three cost centres on one report.

Multiple Modifiers

Any single data dictionary field can hold a combination of the above modifiers with the exception of the Period Modifier or the Period & Year Modifier, which cannot both be selected.

If account modifiers and run time modifiers are used in the same report, the account modifier will take precedence.

Run Time Modifiers

The above example demonstrated how and why you would set up modifiers before generating the report. However, you can specify modifiers at the time you run the report. The modifiers are entered in a similar way, but will not, of course, be printed on the same report as the set delimiting parameters on which they are based, since output fields will not be available. Instead, the modified values will be printed on subsequent reports.



Note: This is a temporary modification valid only for the time the report is run.



Note: You can only modify accounts and views at run time; you cannot modify any of the other modifier options.

RW050	E1 - Demonstration Company	USER ED3	11/10/94 14:39:25
-------	----------------------------	----------	----------------------

Data Dictionary Numeric Variable

Column number : 01
Variable name : BS NET ACT
Accumulate into : 001
Print commas? (0/1) : 0 Edit negatives with Blank, (, - or C . : -
Print only if credit? (0/1) : 0 Print only if debit? (0/1) : 0
Print zero values? . (0/1) : 1
Period modifier : -1 or Period . . : 00 & year modifier 0
Account modifier : ***** Budget code . ?
Company modifier : Currency . . ?

Type	Field name	Description
System	AC_COD_12	Account Code (12 Characters)
System	AC_COD_20	Account Code (20 Characters)
System	AC_COD_30	Account Code (30 Characters)
System	AC_COD_40	Account Code (40 Characters)
System	AC_COD_50	Account Code (50 Characters)
System	AC_DSC_20	Account Description (20 Characters)
System	AC_DSC_30	Account Description (30 Characters)

F3=Cancel field selection F4=Prompt F12=Previous F19=Sector Modifier

In the Period Modifier field enter the number of periods you want to have offset from the period of the 'standard' column. The system allows you to enter a negative number so that you can compare current period values to previous period values.

Maintaining a Period and Year Modifier

When setting up modifiers it is assumed the report should contain two or more columns of details dependent upon the number of modifications you intend to make. When you create the Header format of the report, ensure you include the appropriate headings for the columns. In this case you would require a Header format for a report comparing years and periods.

One of the columns in the report will be the 'standard' column, the other the 'modified' column.

First define the field for the standard column in the normal way. It must be a numeric data dictionary field.

When defining the field for the 'modified' column, select the same data dictionary field as with the standard column and you are taken to the screen of data dictionary numeric variable parameters.

RW050	E1 - Demonstration Company	USER ED3	11/10/94 14:40:04
Data Dictionary Numeric Variable			
Column number	: 01		
Variable name	: BS_NET_ACT		
Accumulate into	: 001		
Print commas? (0/1) :	0	Edit negatives with Blank, (, - or C . . . :	-
Print only if credit? (0/1) :	0	Print only if debit? (0/1) :	0
Print zero values? (0/1) :	1		
Period modifier	0	or Period . . . :	02 & year modifier -2
Account modifier	*****	Budget code . ?	
Company modifier		Currency . . ?	
Type	Field name	Description	
System	AC_COD_12	Account Code (12 Characters)	
System	AC_COD_20	Account Code (20 Characters)	
System	AC_COD_30	Account Code (30 Characters)	
System	AC_COD_40	Account Code (40 Characters)	
System	AC_COD_50	Account Code (50 Characters)	
System	AC_DSC_20	Account Description (20 Characters)	
System	AC_DSC_30	Account Description (30 Characters)	+
F3=Cancel field selection F4=Prompt F12=Previous F19=Sector Modifier			

In the Period field enter, the specific period number of the period.

In the Year Modifier field, enter the number of years you want to have offset from the year of the standard column. The system allows you to enter a negative number so that you can compare current year values to previous year values.



Note: You must leave the Period Modifier field blank.

Maintaining an Account Modifier

When setting up modifiers it is assumed the report should contain two or more columns of details dependent upon the number of modifications you intend to make. When you are creating the Header format of the report, ensure you include the appropriate headings for the columns.

First define the field for the standard column in the normal way. It must be a numeric data dictionary field.

When defining the field for the 'modified' column, select the same data dictionary field as with the first and you are taken to the next screen of data dictionary numeric variable parameters.

RM050	EI - Demonstration Company	USER ED3	11/10/94 14:40:04
Data Dictionary Numeric Variable			
Column number	01		
Variable name	BS_NET_ACT		
Accumulate into	001		
Print commas? (0/1) :	0	Edit negatives with Blank, (, - or C . . . :	-
Print only if credit? (0/1) :	0	Print only if debit? (0/1) :	0
Print zero values? . . (0/1) :	1		
Period modifier	0	or Period . . . :	00 & year modifier 0
Account modifier	002*****	Budget code . ?	
Company modifier		Currency . . ?	
Type	Field name	Description	
System	AC_COD_12	Account Code (12 Characters)	
System	AC_COD_20	Account Code (20 Characters)	
System	AC_COD_30	Account Code (30 Characters)	
System	AC_COD_40	Account Code (40 Characters)	
System	AC_COD_50	Account Code (50 Characters)	
System	AC_DSC_20	Account Description (20 Characters)	
System	AC_DSC_30	Account Description (30 Characters)	+
F3=Cancel field selection F4=Prompt F12=Previous F19=Sector Modifier			

The Account Modifier field is already filled with 12 asterisks for the possible 12 characters an account code can have. Identify the position and number of asterisks for the account level you want to modify and overwrite them with the appropriate code.

For example, you may want to compare values from two accounts: account 001456 and account 002456. The first applies to cost centre 001, the second to cost centre 002. Both these accounts can be printed in the same format by taking account 001456 as a 'standard' and specifying the account modifier as 002*****, which will then print the value from account 002456.



Warning: It is advisable to ensure that the structure and number of your 'standard' accounts is the same as that of your modified accounts. If there are modified accounts which do not exist in the standard account code's structure, they will not be printed.

Standard Accounts	Modified Accounts
-------------------	-------------------

001456	002456
001457	002457
001459	002458
	002459

Account 002458 will not be printed because it cannot be modified from a standard account 001458, since the latter does not exist.



Note: You can enter partial level modifiers, whereby you can modify one or more of the characters in a specific level while leaving the other characters as asterisks.



Note: You can enter modifications to more than one level.

Maintaining a Company Modifier

When setting up modifiers it is assumed the report should contain two or more columns of details dependent upon the number of modifications you intend to make. When creating the Header format of the report, ensure you include the appropriate headings for the columns.

First define the field for the standard column in the normal way. It must be a numeric data dictionary field.

When defining the field for the 'modified' column, select the same data dictionary field as with the first and you are taken to the next screen of data dictionary numeric variable parameters.

```

RW050                                E1 - Demonstration Company  USER ED3          11/10/94
                                           14:40:04

Data Dictionary Numeric Variable

Column number . . . . . : 01
Variable name . . . . . : BS NET ACT
Accumulate into . . . . . : 001
Print commas? . . . . . (0/1) : 0      Edit negatives with Blank, (, - or C . . : -
Print only if credit? (0/1) : 0      Print only if debit? . . . . . (0/1) : 0
Print zero values? . . . . . (0/1) : 1
Period modifier . . . . . : 0      or Period . . . : 00 & year modifier 0
Account modifier . . . . . : *****      Budget code . ? ____
Company modifier . . . . . : E2      Currency . . ? ____

Type      Field name      Description
System AC_COD_12      Account Code (12 Characters)
System AC_COD_20      Account Code (20 Characters)
System AC_COD_30      Account Code (30 Characters)
System AC_COD_40      Account Code (40 Characters)
System AC_COD_50      Account Code (50 Characters)
System AC_DSC_20      Account Description (20 Characters)
System AC_DSC_30      Account Description (30 Characters)      +

F3=Cancel field selection  F4=Prompt  F12=Previous  F19=Sector Modifier
  
```



Enter the company code of another company in the Company Modifier field.

For a meaningful comparison to work, it is assumed the 'standard' and 'modified' companies have a similar Chart of Accounts structure set up.

Maintaining a User-defined View Modifier

When setting up modifiers it is assumed the report should contain two or more columns of details dependent upon the number of modifications you intend to make. When defining the Header format of the report, ensure you include the appropriate headings for the columns.

The next stage is to maintain the Detail format. For example, you might want to maintain two columns; one will be the 'standard' column, the other the 'modified' column.

First define the field for the standard column in the normal way. It must be a numeric data dictionary field.

When defining the field for the 'modified' column, select the same data dictionary field as with the first and you are taken to the next screen of data dictionary numeric variable parameters.

RW050 E1 - Demonstration Company USER ED3 6/01/94 11:22:45

Data Dictionary Numeric Variable

Enter Ledger

Ledger.....? P/L (Leave blank for cross ledger)

F4=Prompt 12=Previous

Print commas? (0/1) : 0 Edit negatives with Blank, (> - or C) : -

Print only if credit? (0/1) : 0 Print only if debit? (0/1) : 0

Print zero values? (0/1) : 1

Period modifier : 0 or Period : 00 & year modifier 0

Account modifier : *****

Company modifier : Currency : ?

Type	Field name	Description
System	AC_COD_12	Account Code (12 Characters)
System	AC_COD_20	Account Code (20 Characters)
System	AC_COD_30	Account Code (30 Characters)
System	AC_COD_40	Account Code (40 Characters)
System	AC_COD_50	Account Code (50 Characters)
System	AC_DSC_20	Account Description (20 Characters)
System	AC_DSC_30	Account Description (30 Characters)

F3=Cancel field selection F4=Prompt F19=Sector Modifier

In order to modify a view, press **F19=Sector Modifier** and a window enabling you to enter a ledger code is displayed as shown above. For a view held within a ledger, enter a valid ledger code and press **Enter** (note that the ledger code may also be left blank). The next window for view selection is displayed on top of the previous window.

Data Dictionary Numeric Variable Select User Defined key

```

RW050                      E1 - Demonstration Company      USER ED3      6/01/94
                                                                11:22:45

Data Dictionary Numeric Variable
Enter Ledger
Select User Defined key
Ledger..... P/L      PROFIT & LOSS LEDGER

Pri      Key                      More                      : -
Pri      123456789  Key description                      : 0
Pri      1--- -- Standard key description
Per      1--- 32-- Account/Cost Centre/Division
Acc      --- 1 -- Division
Com      --- 12-- Division/Cost Centre
T        I 3--- 12-- Division/Cost Centre/Account
S        --- 1-- Cost Centre
S        --- 21-- Cost Centre/Division
S
S
S
S
S
S
S
F12=Previous
System AC_DSC_30      Account Description (30 Characters)      +
  
```

The name and description of the ledger you entered are displayed at the top of the window, and a list of all the views belonging to that ledger beneath.

- The level codes of each view currently set up for the ledger are displayed as numbers within the Key column
- The sequence of the levels is displayed, starting from 1 and descending to a possible 9 if there are 9 available levels in a ledger
- A - in the Key column indicates that the level has not been set up within the ledger's structure
- A blank space in the Key column indicates that there is a level in the ledger's structure but it has not been selected for the view



Note: If no views exist for the ledger the system will take you into the screen where level code range input is defined.



Select a view by entering a 1 against the appropriate view. The system automatically calls up the Specify Sector Modifier window.

Specify Sector Modifier Window

RW050		E1 - Demonstration Company		USER ED3	6/01/94 11:22:45
Data Dictionary Numeric Variable					
Specify Sector Modifier					
Ledger.... P/L PROFIT & LOSS LEDGER					
View..... 3--- 12-- Division/Cost Centre/Account					
Level	Description	Modifier			
6	Division.....?	***			C : -
7	Cost Centre.....?	***			/1) : 0
1	Account Type.....?	*****			0
F4=Prompt F8=Confirm F12=Previous					
System	AC_COD_50	Account Code (50 Characters)			
System	AC_DSC_20	Account Description (20 Characters)			
System	AC_DSC_30	Account Description (30 Characters)			
F3=Cancel field selection F4=Prompt F19=Sector Modifier					

The window displays a list of the levels belonging to the view, the descriptions given to each of those levels and input fields tailored to the particular length of each level.

Enter a modification value in one or more of the level fields and press **Enter**, and then **F8** to confirm your entry. The system takes you back to the initial Data Dictionary Numeric Variable parameter screen where the function key **F19=Sector Modifier** is highlighted to indicate that a view has been modified.



Warning: It is advisable to ensure that the structure and number of your 'standard' accounts is the same as that of your modified accounts. If there are modified accounts which do not exist in the standard account code's structure, they will not be printed.



Note: You can enter partial level modifiers, whereby you can modify one or more of the characters in a specific level while leaving the other characters as asterisks.



Note: You can enter modifications to more than one level.



Note: You can go back and maintain a view modifier at any time. The modified levels will still retain the changes you have made.

Maintaining a X-ledger User-defined View Modifier

When setting up modifiers it is assumed the report should contain two or more columns of details dependent upon the number of modifications you intend to make, so that when defining the Header format of the report, ensure you include the appropriate headings for the columns.

The next stage is to maintain the Detail format. For example, you might want to maintain two columns. One will be the 'standard' column, the other the 'modified' column.

First define the field for the standard column in the normal way. It must be a numeric data dictionary field.

When defining the field for the 'modified' column, select the same data dictionary field as with the standard and you are taken to the next screen of data dictionary numeric variable parameters.

```
RW050                      E1 - Demonstration Company      USER ED3      6/01/94
                                                                11:27:11

Data Dictionary Numeric Variable
Enter Ledger
Ledger.....? (Leave blank for cross ledger)
F4=Prompt  12=Previous

Print dots? . . . . . (0/1) : 0      Edit negatives with Blank, ( , - or C . : -
Print only if credit? (0/1) : 0      Print only if debit? . . . . . (0/1) : 0
Print zero values? . . (0/1) : 1
Period modifier . . . . . : 0      or Period . . : 00 & year modifier 0
Account modifier . . . . . : *****
Company modifier . . . . . : _____ Currency . . ? _____

Type      Field name      Description
System AC_COD_12      Account Code (12 Characters)
System AC_COD_20      Account Code (20 Characters)
System AC_COD_30      Account Code (30 Characters)
System AC_COD_40      Account Code (40 Characters)
System AC_COD_50      Account Code (50 Characters)
System AC_DSC_20      Account Description (20 Characters)
System AC_DSC_30      Account Description (30 Characters)      +

F3=Cancel field selection  F4=Prompt                      F19=Sector Modifier
```

In order to modify a X-ledger view, press **F19=Sector Modifier** and a window requiring you to enter a ledger code is displayed as shown above. For a X-ledger view leave the field blank and press **Enter**. The next window for view selection is displayed on top of the previous window.

Select Cross-Ledger User-Defined Key Window

```

RW050                                E1 - Demonstration Company    USER ED3        6/01/94
                                           11:22:45

Data Dictionary Numeric Variable

Enter Ledger
Select Cross-ledger User-defined key.

Key                                     More
123456789   Key description
-----
-----   Standard key description
-----   Trial Balance by State
-----   Cost of Sales by Rep/Type
-----   Account/Type/Rep
-----   Division/Account
-----   Cost Centre
-----   Cost Centre/Division

F12=Previous
System AC_DSC_30      Account Description (30 Characters)

```

The window displays the X-ledger views which have been set up on the General Ledger Chart of Accounts. Each X-ledger view is comprised of X-ledger levels. As such, the views cannot belong to a particular ledger and do not have specific level code numbers 1 to 9 against them because the codes might be used at different levels across different ledgers.

Select a X-ledger view by entering a 1 against the one you want to use. The system automatically displays the Specify Sector Modifier window where you can specify level code modifications.

Specify Sector Modifier Window

RW050		E1 - Demonstration Company		USER ED3	6/01/94 11:22:45
Data Dictionary Numeric Variable					
Specify Sector Modifier					
View..... ----- Account/Type/Rep					C. : -
Level	Description	Modifier		/1) : 0	
	Account.....?	002			
	Type.....?	***			0
	Rep.....?	*****			
F4=Prompt F8=Confirm F12=Previous					
System	AC_COD_50	Account Code (50 Characters)			
System	AC_DSC_20	Account Description (20 Characters)			
System	AC_DSC_30	Account Description (30 Characters)			
F3=Cancel field selection F4=Prompt F19=Sector Modifier					

The window displays a list of the levels belonging to the X-ledger view, the descriptions given to each of those levels and input fields tailored to the particular length of each level.

Enter a modification value in one of the level fields and press **Enter**, and then **F8=Confirm** to confirm your entry. The system takes you back to the initial Data Dictionary Numeric Variable parameter screen where the function key **F19=Sector Modifier** is highlighted to indicate that a view has been modified.



Warning: It is advisable to ensure that the structure and number of your 'standard' accounts is the same as that of your modified accounts. If there are modified accounts which do not exist in the standard account code's structure, they will not be printed.



Note: You can enter partial level modifiers, whereby you can modify one or more of the characters in a specific level while leaving the other characters as asterisks.



Note: You can enter modifications to more than one level.

You can go back and maintain a X-ledger view modifier at any time. The modified levels will still retain the changes you have made.