

-
-
-
-
-

Chapter 3

Chart Of Accounts Maintenance



Introduction To Chart Of Accounts Maintenance

To access the facilities to set up and maintain your Chart Of Accounts select the GL Chart Of Accounts Maintenance options.

The Chart Of Accounts forms the basis of the General Ledger structure. The accounts and their respective ledgers are all defined here. Hierarchies and reports relating to Chart Of Accounts ledgers are also provided.


Ledger Structure Explanation

The General Ledger is made up of two high level ledgers, the profit and loss ledger and the balance sheet. Below these two ledgers build a structure of Sub Ledgers down to lower level Sub Ledgers. Postings are made at the lowest level - feeding upwards to the highest level for reporting and analysis.

The structure of the P&L and Balance sheet account codes may be different.

The major benefit of Sub Ledgers is the ability to define an alternative account code structure for a specific group of accounts.

Ledger Structure Example




The structure of ledgers can be as simple or as sophisticated as necessary, depending on the size of the business or the complexity of detail required for data analysis.

The creation of Sub Ledgers allows extra cross-ledger levels to be defined.

Posting is always made to the lowest Sub Ledger in the structure. The Sub Ledger posting accounts must be unique across the ledgers. The transaction is recorded with the account code for the lowest Sub Ledger only. Each Sub Ledger has a control account in the ledger immediately above it. Such control accounts are automatically updated by the system.

This approach progresses upwards until the balance sheet or profit and loss ledgers are reached.

Sub Ledgers/Accounts Example



A Sub Ledger gives more detailed analysis of an account in a ledger above it.

Account Structure Explanation

The structure of any account is dictated by the structure you created in the ledger in which it resides.

An account can be up to 42 characters long, is alphanumeric, and is structured by the use of level codes.

There is a logical split in the 42 characters - the first 12 characters are referred to as the account code while the last 30 characters are called the extension code.

There are two types of posting account, fiscal and memorandum.

Fiscal And Memorandum Accounts

Fiscal accounts are the financial posting accounts. The fiscal accounts form the high level balance sheet and profit and loss ledgers form the trial balance.

Example: Use the first 12 characters for fiscal codes and the last 30 for analysis.

It is possible to specify any combination of level codes to form an account code or view.


Memorandum accounts are used for statistical purposes and do not appear in the trial balance.

The low level posting accounts from the Sub Ledgers do not appear in the trial balance. The postings to these accounts are summarised in the Sub Ledger control accounts. Control account summaries are high level and therefore appear in the trial balance.

Level Codes

The structure of the levels directly affects the level of analysis and should, therefore, be examined before the account code structures are decided. It is not necessary to use all of the first 12 characters before moving on to the use of the last 30.

The account code has up to four possible level codes, which are defined by its ledger structure:



The maximum length of each individual code is nine characters. The total length of all the level codes can not exceed twelve characters.

Account level code 1 must be specified for each ledger.


level code 1	region	4 characters
level code 2	expense	2 characters



Note: The system maintains period balances for the account code and ensures that transactions are correct, in that debits must always equal credits.

Extension Level Codes

For further analysis extend the account level code. This extension code has up to five possible levels, which are defined by its ledger structure.



Depending on the structure of the ledger, an account can have an extension code defined to it. The maximum length of any extension code is fifteen characters. The total length of the extension codes cannot exceed thirty characters.

The extension level codes are optional and have several uses:

- For more detailed analysis of, for example, cost centre, activity or product group. If defined, they are entered at the time of the posting. They are part of the transaction record and are used to update user-defined views.
- For ease of use when inputting account codes; a window will be automatically displayed with prompts for the required extension level codes. In addition to this, partial or complete default extension codes can be set up for each account.
- You can specify links (between levels of the code) to ensure that the correct combination of extension codes are entered when posting. Codes from the first four levels are linked to codes from levels 5 to 9. Or, extension levels (5 to 9) are linked with other extension level codes (5 to 9).

Other points to remember:

- You do not have to use all of the first four account code levels before creating extension level codes. You can specify additional extension codes at a later date, but not account code levels.
- All levels must be used in sequence; you cannot specify level 7 before level 5.
- Actual extension codes can be created on an ad hoc basis if the option to have this facility is chosen on the company profile.

Global Levels And Global Codes

A global level is an extension level which is created to cover every ledger in your company.

To activate the global level the following conditions must be set up:

- At your company profile screen 2, level code 5 should have a length and description added. If required, levels 6-9 may be added at the same screen.
- At your company profile screen 1, Use Account Code Extensions? must be set to 1.
- At Maintain Ledger Descriptions screen the Req'd flag must be set to 1 against the global level. (For more information see Maintain Ledger Descriptions Screen.)



Note: If you do not select to use the global code, the level will be posted as blank for transactions within that ledger.

The following attributes apply to the global level and the global code:

- Set global levels when your company profile is being defined. Once specified, they are permanently in the system and may not be deleted.
- A global level set for extension level 5 (and its designated description) would appear within the account level structure of every ledger at level 5.
- A global level is only created for extension levels.
- A global level must occupy the first extension levels available. The first global level set up should be 5, a second, level 6 and so on.
- A global level must cross over all ledgers. When creating account level codes you can create a list of global account level codes. This list can then be selected to be used in any ledger or Sub Ledger where global levels are in operation.
- In addition to this list of global codes, you are also able to create account level codes that can be used at the designated global level(s), but these will effectively be specific to an individual ledger or Sub Ledger.
- Global level codes can be deactivated (before being posted to) in any ledger.



Warning: Once a global attribute is set for a level, it may not be removed. It effectively locks that level.

X-Ledger Levels And X-Ledger Codes


Use cross-ledger levels to set up level codes that span two or more ledgers. Balances held against accounts and specified levels of accounts can then be analysed and compared across ledgers.

Cross-ledger codes may be analysed at a different level in each ledger. The analysis element must be the same length in each ledger.

These cross-ledger codes can also be used to build user-defined views.

For example, if an area code is used in several ledgers, and you are required to construct totals (period balances) by area, it would follow that whenever area is defined in a ledger structure, it is defined as cross-ledger (X-Ledger). It does not need to be in the same physical position in all ledgers, but its length must always be the same.

X-Ledger Example



A window of all extension levels of the same specified length display for selection when you define your X-Ledger levels. You must then select an appropriate X-Ledger level or create a new one.

The system builds internal links for X-Ledger levels which control this function.




Warning: You can only have thirty-six X-Ledger levels on the system, so it is advisable not to give X-Ledger status to a level unless you are sure it is absolutely necessary. X-Ledger levels should not be employed merely as a way of setting up account codes more quickly.

Linked Levels And Their Codes

Link Level codes to selected account codes. The system will then only allow transactions of the correct combination of account codes to be entered.

One or more levels of the code used are automatically linked when the posting account is created.

Linked Levels Example



In this example, a link has been set up between the level 2 Dept and the level 5 Salaries. Clerks, Engineers and Tech Authors salaries would be combined for Department 2.

Should the operator attempt to post accounts with the extension codes for directors' or managers' salaries in department 2, the transaction will not be allowed. Department 1 would be set up to accept salary codes 002 and 004.



Note: Once you have defined a link, you can only use valid combinations within that ledger.

User-Defined Views

A view is a defined number of account levels arranged in a sequence. You can define any number of views within the Chart Of Accounts, each time specifying a different sequence and/or different number of account levels.

Every time a transaction occurs which affects one of these views, the view will be updated. Transactions and budgets can then be examined via these user-defined views (as well as simply by account throughout the Enquiries facility).

Views may be within a single ledger or across ledgers:

- Single ledger views - Used to compare balances held against different ranges of accounts and combinations of account levels (both levels 1 to 4 and for extension levels) within the same specified ledger. They access ledger levels set up for individual ledgers in the Chart Of Accounts.
- X-Ledger views - Used to compare balances held against different ranges of accounts and combinations of account levels across two or more ledgers. They use the X-Ledger levels set up in your Chart Of Accounts.

Report Level Codes

Report level codes are optional and are used solely for reporting purposes. Report level codes can group together like accounts to compare and analyse under specified report headings.

Report Control Codes

Specify up to five further codes lettered A to E when you set up your ledger account structure. A - E are report control codes. Give Descriptions to A - E to be used in accounts maintenance to allocate accounts.

Report control codes are applied to accounts. Then specify the sequence of display used on reports.

Report level A is used by the system to generate the standard financial reports. Level A is used by the system to sort the GL posting accounts into common groups to prepare the trial balance and other financial reports. You should define report control codes and assign these against GL posting codes during their creation.

Once total codes are assigned against specific report control codes, sub totals can be generated for the standard financial reports. Secondary sort criteria can also be specified for the standard financial reports.



Note: Report level codes are a good way of selecting a group of accounts when creating Financial Manager report definitions.

Report Levels Examples

1 - Set up account level codes:

Level 1 (EXPENSE)	Level 2 (COST CENTRE)
1001	99
1002	98
1003	97

2 - Set up a number of accounts with report control codes:

Account	Level A (REGION)
1001 99	100
1001 98	090
1001 97	080
1002 99	070
1002 98	060
1002 97	050
1003 99	040
1003 98	030
1003 97	020

3 - Make the following postings within the ledger

Account	Value
1001 99	10
1001 98	15
1001 97	12
1002 99	8
1002 98	20
1002 97	16

4 - Make the following postings within the ledger:

Account	Value
1001 97	12
1001 98	15
1001 99	10
1002 97	16
1002 98	20
1002 99	8
1003 97	0
1003 98	0
1003 99	0

5 - Run the report in level A order, followed by level 2 and you will see the following:

Account	Value
1003 97	0
1003 98	0
1003 99	0
1002 97	16
1002 98	20
1002 99	8
1001 97	12
1001 98	15
1001 99	10

Memo Accounts

Memo accounts are for aggregating balances from other accounts, or statistical information, and will be excluded from trial balance calculations as they are not financial (or fiscal) posting codes. They can hold both values and quantities, and can be incorporated within views.

Memo accounts are set up in the same way as fiscal accounts, but are flagged with M for memo.

Their primary use is as hierarchy control accounts.

Hierarchy Structure

Hierarchies are structures of memorandum accounts which summarise values from fiscal and/or memo accounts. Typically, they are used to accumulate top level accounts as management summaries.

Forecasts

Because forecasts can be created at this level, hierarchies can also be used to assess the effect of, say, a 10% increase in cost of sales. Such accounts are known as hierarchy accounts.

Period Values

Hierarchy accounts can accumulate values from prior periods and/or a percentage only of the designated accounts.

Inter-Company Consolidation

A hierarchy can also incorporate accounts from another company; such hierarchies could be used for simple company consolidation where the full consolidation and translation features are not required.

Number of Levels

You can have up to nine levels to a hierarchy. Thus, when a transaction is posted to an account, the system identifies that it has been specified in one or more hierarchies.

Control Account

The hierarchy control account balance is updated according to the hierarchy specification. No transactions are held against hierarchy control accounts, and you cannot post to them.

Enquiry

The General Ledger account enquiry allows online review of hierarchy control account totals and component accounts.


New Account

If a hierarchy is selected using a rule selecting a range of accounts, and you subsequently create a new account which falls within the range specified on the hierarchy, then, at the end of Chart Of Accounts creation, a batch job is submitted, and the account will be inserted into the hierarchy.



Warning: In order to create hierarchies you must have a memorandum account to summarise the hierarchy data.

Hierarchy Simple Example



Accounts Maintenance



1/GLM

Use this procedure to create accounts for each of your existing ledgers for this company. This option may then be used to maintain accounts.

Update Chart Of Accounts Screen

Once the ledger is entered this screen displays to allow you to select the account levels.



Select the chart of accounts maintenance option
Accounts, enter the relevant ledger, and press
Enter.

```

GL102                Version 3 Demonstration Company    USER GBJBANB1    8/12/97
                                           15:26:52
Maintain Chart of Accounts      Structure XX-XXXX-XXX
Ledger . . . . . : TRC Travelling Costs

Level 1 Expense . . . . . ? 62
Level 2 Cost type . . . . . ? 5101
Level 3 Contract Manag . . . . . ? 013

Sequence
Accounts
(Optional)
1
2
3

F3=Exit      F4=Prompt      F12=Previous

12-38      *      KS CL IM DM II      MARVIN      KB      PKH312S1
  
```

The fields to display depend on how you created your level codes.

Level 1

For the first level displayed enter an existing account level code.



*Note: Levels used are entered at the Ledgers
maintenance option.*

Level 2

Enter level 2 (if set up) and any subsequent levels to display - up to level 4. See
Example Account Sequence for more information.

Sequence Accounts (Optional)



*Note: Sequence Accounts only displays if set up.
Use Account Sequencing is set to 1 on Company
Profile Screen 1.*

Sequence the account levels in the order in which you wish to have them created.

Account Sequence Example

Ledger	TRV Travel Sub Ledger	Sequence Accounts (Optional)
Level 1 Expense type	62 (Travel Costs)	1

Level 2 Travel cost	5101 (Hotels)	2
Level 3 Employee	012 (M Jones)	3

All the Employees will be run through against the first Travel code. Once they are exhausted, the system will run through the Employees again against the next Travel code, and so on. Creation of accounts will only stop when all Travel codes with their respective Employees have been exhausted.

Accounts can now be created semi-automatically. Press **Enter** to accept the details and to redisplay. Only the first four account level codes are displayed on the Selection Screen; the reason being that many combinations of extension level codes may be set up for one account, whereas only one combination of account codes is permitted.



Note: The structure of the account is displayed at the top of the screen.



Press **Enter** to call up a window containing the extension levels of the account (if used).

Select Default Extension Code Window

Extension codes selected at this window will be created as default for the account levels entered on the previous screen. Default codes may then be accepted or changed when the account is being processed. The correct length of each extension level displays. Select only those extension codes appropriate for the account. The default can be partial, meaning that you do not need to set up all extension codes as defaults.



Press **Enter** at the Update Chart Of Accounts Screen to display this window (if you are using extension codes).

GL102	Version 3 Demonstration Company	USER GBJBANB1	8/12/97
Maintain Chart of Accounts	Structure XX-XXXX-XXX		13:47:42
Ledger	Select default extension code		
Last account code updated . . .	Ledger..... TAC		
	Fiscal Account..... 625101012		
	Corporate.....? 83021		
	Cost Centre.....? 001		
	F4=Prompt F12=Previous		
F3=Exit F4=Prompt F12=Previous			
9-55	▪	KS CL DM II	MARVIN KB PKH312S1

Fields:

Extension level codes

Your level codes display as you defined them in Ledger Maintenance.



Note: Extension level codes are created at levels 5 to 9 in the Maintaining A Ledger Screen.



Enter to validate your extension codes and to display the Maintain Chart Of Accounts screen.

Maintain Chart Of Accounts Screen

This is the main screen for entering the details of your General Ledger accounts.

GL102	Z1 - UK Demonstration Company	USER GBJBA1MS	9/06/98 15:06:56
Maintain Chart of Accounts			*UPDATE
Ledger : COS Cost of Sales			
Account : 603000			
Default extension code : 66601/100/210/0001/			
Report control codes . ? _ _ _ _ _			
Account description . . <u>Stock Inwards,</u>			
Short description . . . <u>Stock Inwards</u>			
Memo account (M=Memo)			
Post inhibit? (U=Inhibited by user)			
Maintain prime balances? <u>1</u> (0/1)			
Summarise postings . . . <u>0</u> (0/1/2)			
Transfer jnl. details? . <u>0</u> (0/1)			
Translation method . . . <u>1</u> (0=Current, 1=Historical)			
VAT Code ? <u>001</u>		Input/Output . . . <u>1</u> (blank/1/2)	
Account type -			
B/M Worksheet			
F4=Prompt		F12=Previous	
MA	a	MW	20/027

Fields:

Report Control Codes

Enter the relevant report control codes for the account. They must be valid codes as set up in Chart Of Accounts. Five sections are available to select control codes for Level A to level E.

These codes are used to group accounts for reporting purposes.



Note: As a reminder, report level 5 is used to format and sequence the standard profit and loss and balance sheet reports.

Account Description

The account description is derived from the account level codes, but can be changed by overtyping a new description of up to 50 characters in length.

Short Description

Enter an abbreviated description of the account of up to 20 characters in length. The description will default to the prime account level description as specified for the ledger for which the account is defined.

Memo Account

The General Ledger may also hold memorandum accounts which can be used for statistical purposes. Such accounts do not appear in the trial balance.

Enter M to indicate a memorandum account. Otherwise, leave blank for fiscal accounts.

Posting Inhibit

Enter U to prevent direct posting of journals to this account.

The flag may also be set automatically to one of the following values. If it is, the flag cannot be changed.

A - The account is a Cash Management bank suspense account.

B - The account is a Cash Management bank account.

C - The account is a control account for another module such as Accounts Receivable or Accounts Payable.

D - The account is a Cash Management collection document control account.

G - The account is used to hold the value of unrealised currency gains and losses.

S - The account is a hierarchy control account.

Y - The account is a Sub Ledger control account.

Maintain Prime Balances

Enter 1 if this account is to build prime value balances. The default for this account is taken from the ledger profile, which in turn comes from the company profile.

Summarise Postings

0 - Print all transaction details in reports.

1 - Print only summary details in reports.

2 - Print the transactions summarised by document reference (one line per journal). This setting is relevant if you are using French statutory reports, and the setting in France should be 2.

Transfer Jnl Details

0 - To transfer period values only (separately for debits and credits).

1 - If details of individual transactions are to be transferred to the target company by company consolidation.

Translation Method

The method by which values on this account are translated into a different currency. See company profile for a definition of all the available methods.

VAT Code



Note: This field displays only if Country Specific Parameter 031, VAT Rec(onciliation) By GL Account, is set to 1 or 2.

Select a VAT code if you wish to specify a VAT code against the account. You must then specify whether the VAT is for inputs or outputs. This will enable you to produce a VAT reconciliation report.

Input/Output



Note: This field displays only if Country Specific Parameter 031, VAT Rec(onciliation) By GL Account is set to 1 or 2.

Blank - Purchase or Sales. The VAT Code selected will be validated in the posting options to ensure that only the VAT code entered above is used. No check will be made on the VAT type.



Note: The blank option only displays if Country Specific Parameter 031 is set to 2.

1 - Purchase only. The VAT Code selected will be validated in the posting options to ensure that only the VAT code entered above is used. The VAT type must be Purchase (Input).

2 - Sales only. The VAT Code selected will be validated in the posting options to ensure that only the VAT code entered above is used. The VAT type must be Sales (Output).

Account Type

This two character field may be used for any appropriate classification of the account. Note however that the code 01 is used by certain VAT procedures to indicate an Asset account, and should therefore be reserved for that purpose.

B/M Worksheet

This field is provided in order to enable an interface to the Business Modeller Financial Planning product. Any entries made are not validated.

Row

This field is provided in order to enable an interface to the Business Modeller Financial Planning product. Any entries made are not validated.



Note: If one has been set up, a default extension code will be displayed on the screen beneath the account.

If an existing account code is being maintained, the screen will display the data held for the account which can be altered.



Enter or amend the data for this account and press **Enter** to accept and you are returned to the initial screen. If the company profile is set to check new accounts against hierarchies, the system finds any hierarchies and displays them. Enter details if the account is to form part of a hierarchy structure.

Account Level Codes



2/GLM

If the company profile Level Codes Active? flag has been set to 1, then valid level codes must be defined for each ledger. This procedure enables you to define these level codes.

Maintain Account Level Codes Screen 1



Select the chart of accounts maintenance option
Account Level Codes to display the first Maintain
Account Level Codes screen.

Select the level code or ledger or account whose level codes you wish to maintain.

GL098	Y9 - Education Company - Y9	User FFV9	21/06/95 16:06:28
Maintain Account Level Codes			
Global?.....:	☐	(0/1)	
Or Cross-ledger?.....:	0	(0/1)	
Or Ledger?.....:	TRV		
Or Account?.....:			
F3=Exit F4=Prompt			
05-26 SF MK KS IM II EDN400A PCET02S3			

Fields:

Global

0 - You do not wish to maintain a global level code.

1 - You do wish to maintain a global level code.

Global level codes are set up for those reserve levels which cover every ledger within the company's Chart Of Accounts.

Cross-Ledger

0 - You do not wish to maintain a X-Ledger code.

1 - You do wish to maintain a X-Ledger code.

X-Ledger level codes are set up primarily in order to create X-Ledger user-defined views. When setting up such a view, you are presented with the lists of X-Ledger level codes, combinations of which you can choose to make up the structure of your views. Thus, you are able to compare values held in like account level codes across ledgers for enquiry and reporting purposes.

Ledger

Enter a valid ledger code for the ledger for which level codes are to be set up/maintained.

Ledger level codes are set up for levels within a specified ledger, and enable both level codes from the first twelve characters of the account code structure, and

extension codes to be defined. This is the most common method of defining level codes.

Account

Enter the name of the account whose extension levels you wish to maintain.

You can only enter an account which has extension codes.

Since this option is designed to set up level codes for chosen individual accounts, only extension levels within the account's ledger are displayed. Enter values in the normal way.



Make your selection to display the second
Maintain Account Level Codes screen.

Maintain Account Level Codes Screen 2

This screen will vary depending on the selection you made on the first screen, but will in all cases be a simple selection screen. The screen displays the structure of the levels belonging to the selected ledger.



To display this screen select the level code or ledger or account at the Maintain Account Level Codes Screen 1 and press **Enter**.

GL098	Z1 - GB Demonstration Company	USER GBJBA1MS	19/01/98 15:07:54
Maintain Ledger Level Codes			
Ledger code :	BNK	Bank Accounts	
Level :	5	Corporate	
Ref	Code	Description	
1		prior period suspens	
Reference	_____ (Change/Delete)	Start from . _____	
Code	_____	Status . . . 1 (0/1)	
Description	_____		
F3=Exit		F12=Previous	
20-24	SA	MW	KS CL IM DM II STUD140 KB PKH312S1

Fields:

(Asterisks)

* beside an account level indicates that it has been set up as a global level.

** beside an account level indicates that it has been set up as a X-Ledger level.

Enter Level Number

Enter the level number of the level code you wish to maintain.



Press **Enter** to see the Maintain Level Codes screen. This will be titled according to the selection you made on the first screen. If you are maintaining a ledger, it is called the Maintain Ledger Level Codes screen, and so on.

Maintain Ledger Level Codes Screen

This screen will be titled according to the selection you made on the first screen. If you are maintaining a ledger, it is called the Maintain Ledger Level Codes screen, and so on.



Press **Enter** at the Maintain Account Level Codes Screen to display this Level Codes maintenance screen.

GL098	Z1 - GB Demonstration Company	USER GBJBA1MS	19/01/98 15:07:54
Maintain Ledger Level Codes			
Ledger code : BNK		Bank Accounts	
Level : 5		Corporate	
Ref	Code	Description	
1		prior period suspens	
Reference		(Change/Delete)	Start from
Code			
Description		Status . . . 1	(0/1)
F3=Exit		F12=Previous	
20-24	SA	MW	KS CL IM DM II STUD140 KB PKH312S1

Fields:

Reference

This reference number is generated sequentially. Where a level code is being amended or deleted the code is selected by this reference.

Start From

Enter a valid code which has already been set up for this level and press Enter.

The list of codes displayed on the screen will position itself so that it begins with the code you specify here.

Code

Enter a valid code whose length has already been determined from the Ledger description.

Description

Enter a description of the account level code you are maintaining of up to 20 characters in length.

Status

0 - The account code will set up but cannot be posted to. Enter 0 for a level no longer required for posting purposes, but still required for reporting - for example, comparative year basis. The account level code will be highlighted on screen.

1 - The level code will be taken as normal and may be input as part of the account within the system. Setting a status of 1 creates the level code as a global level code.

If a level code is set to inactive after it has been posted to, you may not make further use of it. A typical example is a level code set up for a department that no longer exists.



Note: The status flag may only be set for extension level codes, and not normal level codes.



Accept the details by pressing **Enter** and the new level code and its description will be displayed on the screen along with a system generated number.

Report Control Codes



3/GLM

Report control codes are used during account creation to group accounts together using a specific key. Level A is used to sequence the accounts to generate the standard financial reports.

Reports are set up using three stages:

- Define the report control codes required within the ledger structure. This is done via the option Ledgers (General Ledger Chart Of Accounts Maintenance) The third screen enables you to enter report control codes.
- Select Report Control Codes, and enter the ledger code for the ledger whose report control codes you want to maintain.
- Select the option to maintain Accounts (Chart Of Accounts). Having selected the appropriate ledger and account and having reached the screen requiring input of report control codes, prompt on the report control codes you have set up. A screen then appears with the selected code number inserted for the specified control code: If specified within the format of the account's ledger, further report control codes may be input.

Report Control Codes Maintenance Screen 1

This screen displays report levels available to be selected for maintenance.



Select the option to maintain Report Control Codes, and enter the ledger code for the ledger whose report control codes you want to maintain. The code must be a valid ledger code as set up in Chart Of Accounts.



Press **Enter** to proceed to the first Report Control Codes Maintenance screen.

```

GL094          Y9 - Education Company - Y9      USER FFV9      21/06/95
                                                    16:48:56

Maintain Report Control Codes

Ledger..... P/L  PROFIT & LOSS LEDGER

Select report level:-

      Description
A.  ACCOUNTS SEQ.NO
B.
C.
D.
E.

Level..... A

Note: only levels in high intensity may be selected.

-----
F3=Exit  F12=Previous
17-22   SF      MW      KS      IM      II  EDN400A  PCET0283
  
```

Fields:

Level

Enter the letter of the report control level you wish to maintain.



You can enter only those report control code levels which are highlighted, reflecting the level code structure of the ledger.



Press **Enter** to display the second Report Control Codes Maintenance screen.

Report Control Codes Maintenance Screen 2

Select by reference to amend or delete report control accounts, or, enter a new code to create a new report control code.



To display this screen press **Enter** at the first Report Control Codes Maintenance screen.

GL094		Y9 - Education Company - Y9		USER FFV9	21/06/95 16:49:11
Maintain Report Control Codes					
Ledger.....	P/L	PROFIT & LOSS LEDGER			
Level.....	A	ACCOUNTS SEQ.NO			
Ref	Code	Description			
1	010	Turnover			
2	020	Cost of Sales			
3	050	GROSS PROFIT			
4	060	Payroll			
5	070	Travel/Entertaining			
6	080	Property			
7	090	Utilities			
8	100	Transport			
		+			
Ref.....	0000 (Change/Delete)				
Code.....					
Description					
F3=Exit 18-27 SF F12=Previous MK KS IM II EDN400A PCET02S3					

Fields:

Reference Number

This reference number is generated sequentially. Where a level code is being amended or deleted the code is selected by this reference. A code cannot be deleted if it is used for a total description.

Code

Enter a code for this report control code of three characters in length. It must be unique for this level.

Description

Enter a description for the report level code. It can be up to 20 characters in length.



The descriptions of the report codes will appear as in the generated reports.

Ledgers Maintenance

1... **2...** 4/GLM

The high level ledgers for each company must be set up before accounts can be created. This procedure defines the structure of each ledger.

Sequence Of Entry Checklist

- Create company profile. (1/ASCO)
- Assign global levels. (4/GLM)
- Create high level Balance Sheet and Profit and Loss ledgers. (4/GLM)
- Create level codes for Balance Sheet and P&L ledgers. (2/GLM)
- Create report control codes & total codes. (3/GLM)
- Create Balance Sheet and P&L accounts. (1/GLM)
- Create VAT Control Codes. (1/GLM)
- Maintain company profile. (1/ASCO)
- Maintain company Sub Ledgers. (4/GLM)
- Maintain company Sub Ledger levels. (2/GLM)
- Maintain company Sub Ledger accounts. (1/GLM)
- Create hierarchies. (31/GLM)
- Create views. (21/GLM)

Maintain Ledger Descriptions Screen

Enter ledgers as profit and loss, balance sheet or as Sub Ledger types. This screen includes creation of the structure of the ledger accounts; account description; extension codes; set up cross-ledgers; links; a global level and add the Sub Ledger control account.



Select the maintenance option Ledgers (Chart Of Accounts), and enter a ledger code in the selection screen, either to maintain an existing ledger or to set up a new one.



Press **Enter** to see the Maintain Ledger Descriptions screen.



Note: Details of extension codes are displayed only if the Account Code Extensions field is 1 on the company profile.

```

GL090          Y9 - Education Company - Y9          USER FFV9          21/06/95
                                           15:55:20

Maintain Ledger Descriptions

Ledger code . . . EXP
Description . . : Expenses Sub Ledger
Type . . . . . 4
Control account ? 628000
Default translation method . . . . . : 0 (0=Current, 1=Historical)
Default to maintain prime balances? . . : 0 (0=No, 1=Yes)
Extension codes active?.....: 1 (0=No, 1=Yes)

      Description      Length  X-lgr  Link
Account code  1 Employee      2      1      0
              2 Expense      4      -      0
              3              0      -      0
              4              0      -      0
Extension code 5 Corporate    5      1      0
              6 Division     3      1      0
              7 Cost Centre   3      1      0
              8              -      -      0
              9              -      -      0
Account desc level _

F3=Exit  F4=Prompt  F12=Previous
06-22    SF        MK        KS        IM        II  EDN400A  PCET02S3
  
```

Fields:

Description

Enter a description for the ledger of up to 30 characters in length.

Type

The following ledger types are valid:

- 1 - Balance sheet.
- 2 - Profit & loss.
- 3 - Balance sheet Sub Ledger.
- 4 - Profit & loss Sub Ledger.

The General Ledger of each company must have

- one type 1 ledger (the balance sheet) and
- one type 2 ledger (profit and loss).

This is the minimum ledger set for each company. You may set up as many type 3 and 4 ledgers as you wish since they are optional and operate as Sub Ledgers to the main ledgers.

Control Account

Enter a valid account code of up to 12 characters in length, to act as the control account for this Sub Ledger. This is for ledger types 3 and 4 only. It indicates an account in a higher level ledger, which must not already have been specified as a control account to another Sub Ledger.

The control account cannot be used if it has already had transactions posted to it.

It should be a fiscal account and you cannot post memo accounts into a memo control account.

Postings to an individual account in a Sub Ledger are automatically added to the control account specified for that Sub Ledger.

Company Profile Multi-Currency Options

The following two fields will appear only if the company has been flagged as a multi-currency company on the company profile:

Default Translation Method

This is the default translation method that will be passed down to the accounts set up within this ledger.

0 - Translate cumulative values as at the end-of-period rate for the translation period.

1 - Will do one of the following:

Translate posted values for the translation period at the mid-period rate.

Transfer the actual values in the target currency (if historical translation details for this company are being maintained).

Default To Maintain Prime Balances

This is the default used when you create a new Sub Ledger in a multi-currency environment to identify whether you are maintaining prime currency balances for the Sub Ledger.

Company Profile Ledger Level Structure



Enter the following details all relevant to the level structure of the ledger.

Extension Codes Active

0 - You do not want extension codes to be used for accounts within this ledger.

1 - You want to set extension codes as active, in which case extension codes will be maintained and used for accounts within this ledger. You must set this flag to 1 if you want to use global codes.

Account Code Description

Enter a description for the account level of up to 15 characters in length.

You can maintain up to four account levels.

Length

Enter the length of the account code. It can be up to 9 characters in length, but the total length of all the account codes set together must not exceed 12.

X-Lgr

Enter 1 against any level codes you wish to act as X-Ledger level codes. As such, they can be used in X-Ledger views for enquiry, report, budgeting and detailed analysis purposes.



Note: Only 36 X-Ledger level codes can be set up for a company.

If you specify X-Ledger levels a small window is displayed for you to select or create and select one. It lists all the X-Ledger levels already set up and of the same length. You can:

Select an existing X-Ledger level. In which case the system will build a link for this level to enable you to maintain X-Ledger views.

Create a new X-Ledger level by selecting **F10=Add**.

Link

0 - You do not want the level to be linked to another level within the ledger.

1 - You want the level to be linked to another level.

If you use links, you must link an account level 1-4 with an extension level 5-9.

The linking of level codes forces you to input the correct combination of codes when entering an account belonging to this ledger.

Obviously, links will include an extension level because account levels are already linked.

Secure

1 - Create this level as a security object.

You cannot secure levels 1-4 retrospectively.

This field displays only if you have elected to use security in the company profile.



Note: See the section entitled Level Code Security Options for more information.

Description (Extension Code Level)

Enter a description for the extension level - up to 15 characters in length.

You can maintain up to five extension levels.

Length

Enter the length of the extension code. It can be up to 15 characters in length, but the total length of all the extension codes together must not exceed 30 characters.

Reqd

0 - You do not want to make use of the global code already existing in the ledger structure. The level will be locked and you may not use it.

1 - You wish to use the global code set up for this level as part of the ledger's extension code structure.

Account Description Level

Indicates the account level code description which best describes the account. This will be used as a default for the short (abbreviated) account description.



Press **Enter**. If you entered 1 in any of the fields in the X-lgr column, you will now see a list of cross-ledger levels to choose from.

Select Cross-Ledger Level Window

This window displays a list of your available cross-ledger levels to select for maintenance.



Enter 1 in any of the fields in the X-lgr column on the Maintain Ledger Descriptions Screen and press **Enter** to display this window.

GL090 Y9 - Education Company - Y9 USER FFV9 21/06/95 15:55:20

Maintain Ledger Descriptions

Ledger code . . . EXP
Description . . : Expenses Sub Ledger
Type 4
Control account ? 628000
Default translation method
Default to maintain prime balances? . . :
Extension codes active?.....

Account code	Description	Le
1	Employee	
2	Expense	
3		
4		
5	Corporate	5
6	Division	3
7	Cost Centre	3
8		
9		

Account desc level 2

Select Cross-Ledger Level

Level: 6 More:

Opt	Description	Length
1	Asset Type	3
2	Division	3
3	Cost Centre	3
4	Product Group	3
5	Employee	3

1=Select, 2=Amend, 4=Delete
F10=Add F12=Previous

08-47 SF MW KS IM II EDN400A PCET02S3

Fields:

Opt

- 1 - Select the level.
- 2 - Amend the level.
- 4 - Delete the level.

Functions:

F10

Add. Use this function to set up a new cross-ledger level. A window enables you to enter a description for the new ledger level.



Note: The X-Ledger level description defaults to the level description entered in the ledger definition screen.



Press **F8=Update** from this new window to add the new cross-ledger level to the list.



Select the cross-ledger level as appropriate, then press **Enter** to see the report control codes screen.

Ledger Descriptions Maintenance Screen

This screen enables you to add descriptions for your report control codes. The report level codes, together with the account level codes may be used in management reporting and the profit and loss ledger to produce the desired sequence and sorting of reports.



Select the cross-ledger level at the Select Cross-Ledger Level Window and press **Enter** to see this screen.

GL090	Y9 - Education Company - Y9	USER FFV9	21/06/95 16:48:32
Maintain Ledger Descriptions			
Ledger code	P/L		
Description . . . :	PROFIT & LOSS LEDGER		
Type	2		
Control account .			
Report control			
A Desc	ACCOUNTS SEQ.NO		
B Desc	_____		
C Desc	_____		
D Desc	_____		
E Desc	_____		
F3=Exit 14-28 SF MW KS IM II EDN400A PCET02S3			

Fields:

Unnamed (Description)

You have a choice of five report control codes to use for the ledger. Descriptions for the control codes should be entered in descending order of A to E.

It is particularly important that level code A be defined as it is used as the primary sequence for the trial balance, profit & loss and balance sheet reports. (Level A is also used to define total descriptions).

Level A appears as a default for the profit & loss and balance sheet ledgers, and is allocated the title Accounts Seq. No.



Select the option to maintain Report Control Codes to continue with the setting up of these codes.

Linked Levels Account Maintenance



5/GLM

This procedure allows you to set up relationships between level codes in order to have greater control on the input and processing of accounts and their extension codes. Links can be made between account codes and extension codes, or between extension codes and extension codes, but cannot be maintained for account codes exclusively.

When postings are made, those level codes defined on the ledger structure as linked will have the entered combination validated against the valid combinations maintained through this option.



Select the option to maintain Linked Levels (Chart Of Accounts Maintenance), and enter the ledger code of the ledger containing the level codes to be maintained. The code must be a valid ledger code as set up in Chart Of Accounts.



Press **Enter** to proceed to the Maintain Level Code Linkages screen, which lists any existing linked levels.

Maintain Level Code Linkages Screen

Use this screen to link different extension codes or to link account codes and extension codes.



Select the chart of accounts option to maintain Linked Levels, enter the ledger code then the level codes to be maintained and press **Enter**.

GL111	Y9 - Education Company - Y9	USER FFV9	21/06/95 16:21:31
Maintain Level Code Linkages			
Ledger..... SLS - Sales Sub-Ledger			
Opt	Account Code	Extension Code	
-		6 8	
-		000/000	
-		100/210	
-		100/211	
-		100/212	
-		110/230	
-		110/231	
-		110/232	
-		120/250	+
1. Account Type		5. Corporate	
2.		6. Division.....?	☐
3.		7. Cost Centre	
4.		8. Product Group..?	
9.			
4=Delete			
F3=Exit F4=Prompt F12=Previous F21=Position to			
19-56 SF ML KS IM II EDN400A PCET02S3			

Fields:

Opt

4 - Delete a linked level.

Unnamed (Level Codes)

A list of the account level code numbers and their descriptions making up the structure of the accounts within the ledger appears at the base. The linked levels are highlighted with an input line to their right. Only these level codes may be maintained.



Enter a combination of valid level codes to be linked and press **Enter**. The link you have just maintained displays.

Left To Right Accounts Mass Maintenance

Use this option to copy whole sections of the Chart Of Accounts (for a ledger) and so quickly create new accounts (in the same ledger). This facility allows flexibility in copying ranges of accounts at selected levels. This procedure can reduce the amount of time needed to define the whole Chart Of Accounts.

For example, expense accounts linked to a new branch or department can be created by copying accounts linked to an existing branch or department.



Note: This facility can only be used if you are using level codes. That is, Use Level Codes? is set to 1 in your company profile.

Ensure that all valid level codes needed have been created prior to copying.

Example Left To Right Accounts Copy

The two examples which follow are based on a set of accounts within a ledger which uses four account level codes:

Level Code 1	001 (Cost Centre)
Level Code 2	D1 (Department)
Level Code 3	EXP (Expense)
Level Code 4	0123 (Product)

Example 1

The New Accounts column shows a new cost centre 002 copied from all accounts within the existing cost centre 001. To do this, specify all accounts beginning with level code 001 to be duplicated into a new set of accounts with level code 002:

Existing Accounts	New Accounts
001D1EX11005	002D1EX11005
001D1EX11006	002D1EX11006
001D1EX11007	002D1EX11007
001D1EX21005	002D1EX21005
001D1EX21006	002D1EX21006
001D2EX11006	002D2EX11006
001D2EX31005	002D2EX31005

Example 2

This example limits the copy from 001D2 to 002D3. So only accounts existing for department 2 of cost centre 001 are copied.

Existing Accounts	New Accounts
001D2EX11006	002D3EX11006
001D2EX31005	002D3EX31005

Left To Right Accounts Copy



11/GLM

See Left To Right Accounts Mass Maintenance for an explanation, with examples, of this copying option.

An audit listing showing the new accounts and the number of accounts created will be produced automatically from this copy job.



Note: This copy option is only available within ledgers. For example, copy P/L accounts to P/L accounts or B/S accounts to B/S accounts.



Select the chart of accounts mass maintenance option Left To Right Accounts to display the following fields:

Fields:

Ledger

Enter the ledger code of the ledger whose accounts are to be copied. The code must be a valid ledger code as set up in Chart Of Accounts.

Wildcard Add

0 - Do not use the wildcard option of accounts selection.

1 - Enables you to use the wildcard character * when you specify the account levels to be copied on the next screen.

This means that each level does not have to be copied individually, but can instead be submitted as one job.

Example:

From: **1.....To:.....**2 (Copies all codes ending in 1 to new codes ending in 2).

From: ***.....To:.....**2 (Copies all codes to a new set of codes ending in 2).



Press **Enter** to proceed to the Copy Chart Of Accounts screen.

Copy Chart Of Accounts Screen

Use this screen for a mass copy of account levels.



Press **Enter** at the Left To Right Accounts (Mass Maintenance) to proceed to the Copy Chart Of Accounts screen.

GL215	Y9 - Education Company - Y9	USER FFV9	22/06/95 10:51:09
Copy Chart of Accounts (Left to Right)			
Ledger Code..... B/S BALANCE SHEET LEDGER			
Account Level 1.....?		Copied From	To
Copy report control codes?..... 1 (0/1)			
F3=Exit 10-39	F4=Prompt SF	F12=Previous MK	ENTER=Continue KS IM II EDN400A PCET02S3

Fields:

Account Level Copied Range

Enter the account level code range to be copied.



*Note: Asterisks * may be used as a wildcard to enter partial codes. See the Wildcard Add item for more information. The wildcard option field on the previous screen must be set to 1.*

Copy Report Control Codes

0 - You do not want to copy across any report control codes.

1 - You do want to copy across the report control codes.

Copy Default Extension Codes

0 - You do not want to copy across the default extension codes set up against accounts.

1 - You do want to copy across those default extension codes.



Note: This field only displays if extension codes are used in this ledger.



Press **Enter=Continue** to submit your job for processing.

Right To Left Accounts Mass Maintenance

12/GLM

Use this procedure to copy whole sections of the Chart Of Accounts and so create new accounts. For example, add accounts for a new branch or department, based on an existing branch or department.

This procedure can reduce the amount of time needed to define the whole Chart Of Accounts.



Note: This facility can only be used if you are using Level code checking



Note: See the previous section on Left To Right Accounts Mass Maintenance for more information.

The Right To Left Accounts option copies across accounts beginning with the higher numbered account codes and works its way back to the lower numbered account codes.

Example

A ledger has four account level codes:

Level code 1	Division
Level code 2	Cost Centre
Level code 3	Expense
Level code 4	Department

Several accounts are already set up for Department P01. A new department P03 is formed within a company and requires identical accounts to those of department P01. The Department is the right hand level of the code.

Copy From P01 ToP03.

The result of the copy would be:

Existing Accounts	New Accounts
D01C01E01P01	D01C01E01P03
D01C01E02P01	D01C01E02P03
D01C02E01P01	D01C02E01P03

Copy Chart Of Accounts Right To Left Selection Screen

Select the ledger to copy accounts from right to left.



Select the Right To Left Accounts (Mass Maintenance) option.

Fields:

Ledger

Enter the ledger code of the ledger whose accounts you wish to copy. The code must be a valid ledger code as set up in Chart Of Accounts.

Wildcard Add

0 - Do not use the wildcard option of selection accounts.

1 - Enables you to use the wildcard character * when you specify the account levels to be copied on the next screen.

Example:

From: **1.....To:.....**2 (Copies all codes ending 1 to new codes ending in 2.

From ***.....To:.....**2 (Copies all codes to a new set of codes ending in 2.

This means that the copying of each account level, where appropriate, can be submitted as one job.



Press **Enter** to proceed to the next screen.

Copy Chart Of Accounts Right To Left Screen

See Left To Right Accounts Mass Maintenance for an explanation with examples of this copying option.

Use this screen for a mass copy of account levels.



Enter a valid ledger (leaving blank for all ledgers) at the selection screen to display this copy screen.

```

GL216                      Version 3 Demonstration Company    USER GBJBANB1    9/12/97
                                           14:54:09

Copy Chart of Accounts  (Right to Left)

Ledger . . . . . : TRC Travelling Costs

Wildcard characters allowed

                                From      To
Level 3 . . . . . ?  010      014
Level 2 . . . . . ?  5101     5104

Copy report control codes? . . 1  (0/1)
Copy default extension codes? . 1  (0/1)

-----
F3=Exit          F4=Prompt          F12=Previous

11-35      *          KS  CL      DM  II      MARVIN      KB      PKH312S1
  
```

Account Level Copied Range

Enter the range of account level codes (right hand level of the code) to be copied.



*Note: Asterisks * may be used as a wildcard to enter partial codes. See the Wildcard Add item for more information. The wildcard option field on the previous screen must be set to 1.*

Copy Report Control Codes

0 - You do not want to copy across the report control codes.

1 - You do want to copy across the report control codes.

Copy Default Extension Codes

0 - You do not want to copy across the default extension codes set up against accounts.

1 - You do want to copy across those default extension codes.



Note: The detail screen will hold parameters similar to the previous copy routine with the exception that levels are listed starting from the higher level codes and working backwards.



Press **Enter** to submit the amendments for processing.

Sub Ledger Mass Maintenance

1... **2...** 13/GLM

This procedure enables you to create a new Sub Ledger based on an existing one. You may create a new level code for the target Sub Ledger during Sub Ledger copying.

Copy Subledger Screen 1

Select subledger and control accounts to be copied and enter subledger code and description for new subledgers.



Select the chart of accounts Right To Left option.
The Copy Subledger screen displays.

GL500	Y9 - Education Company - Y9	USER FFY9	22/06/95 10:54:39
Copy Subledger			
Existing Subledger to use as a base. ?	TRV		
New Subledger. ?	TR2		
Description for new Subledger.	COPIED SUB LEDGER		
Control account for new Subledger. . ?	624700		
F3=Exit F4=Prompt			
05-43 SF MW KS IM II EDN400A PCET02S3			

Fields:

Existing Sub Ledger To Use As A Base

Enter the ledger code of the sub ledger you want to use as the base for the Sub Ledger copy. The code must be a valid ledger code as set up in Chart Of Accounts.

Do not specify a top-level ledger.

New Sub Ledger

Enter the ledger code for a new sub ledger.

The new sub ledger need not exist on the system. If it does, make sure its structure is of the same length as that of the base ledger.

Description For New Sub Ledger

Enter a suitable description for the new sub ledger of up to 30 characters in length.

Control Account For New Sub Ledger

Enter the control account to receive values from the new sub ledger you are creating.

If the ledger is type 3 you should enter an account in a Balance Sheet ledger of type 1 or 3.

If the ledger is type 4 you should enter an account in a Profit and Loss ledger of type 2 or 4.

The account must be a valid account set up in the Chart Of Accounts and may not be a control account of another sub ledger of a hierarchy summary account.



You may have to accept extension codes for the control account if they have been set up. Press **Enter** to go to the next step.

Copy Subledger Screen 2

Use this screen to enter details of the mass copy and to submit the copy for processing.

- 
- Enter the subledgers to be copied and press **Enter** to display the second Copy Subledger Screen.

GL500

Y9 - Education Company - Y9

USER FFY9

22/06/95
10:54:39

Copy Subledger

Based-on Subledger . TRV Travel Sub-Ledger

New Subledger. . . . TR2 COPIED SUB LEDGER

Control Account. . . 624700 00020/000/000

** ADDITION **

Overriding Value

Overriding Description

Level 1.

Level 2.

Level 3.

Level 4.

Extension codes to be copied? . 1 (0/1)

Memo accounts to be copied? . . 1 (0/1)

Report codes to be copied? . . . 1 (0/1)

Linkages to be copied? 1 (0/1)

F3=Exit F12=Previous

12-24 SF ML KS IM II EDN400A PCET02S3

Fields:

Overriding Value

Enter the overriding level code you want to use for the new sub ledger.

The copy procedure will pick up every account it finds in the base sub ledger and copy it to the new sub ledger, transferring the base sub ledger level code with the new one you enter here.

You must enter at least one overriding level code for the copy to work. This avoids a total duplication of data.

Overriding Description

Enter the overriding description for the corresponding overriding level code you have entered. A new level code will be created in the new sub ledger with this description given it.

Extension Codes To Be Copied

- 0 - You do not want to copy extension codes across to the new sub ledger.
- 1 - You do want to copy across the extension codes.

Memo Accounts To Be Copied

- 0 - You do not want to copy memo accounts across to the new sub ledger.

1 - You do want to copy memo accounts across.

Report Codes To Be Copied

0 - You do not want to copy report codes across to the new sub- ledger.

1 - You do want to copy report codes across.

Linkages To Be Copied

0 - You do not want linked levels, which have been applied to level codes in the base sub ledger to be copied across to the new sub ledger.

1 - You do want to copy the linkages across.



The sub ledger to which you are copying may already exist. In which case a window will display asking for confirmation that the sub ledger you have selected is correct.

- If you are happy with your selection, the module will request the overriding level codes and descriptions, and will create accounts only if they do not exist - effectively adding to the selected sub ledger.
- If you are not, a warning message will be printed and no change will be made to existing accounts.

This facility may be used, therefore, for copying accounts which have been added to the base ledger subsequent to the initial set up of the individual ledgers.



Press **Enter**. A batch job is submitted to generate the new accounts and an audit report generated of those accounts which are created.



Note: If bank accounts are contained within the copied sub ledger, they will not be created as bank accounts in the new ledger.

Report Control Codes Mass Maintenance



14/GLM

This procedure enables you to change the report control codes to any other report control code existing in the same ledger. Report control codes are held against a range of accounts (or all accounts in a ledger).

Maintain Account Report Control Codes Screen 1

At this screen select a particular set of report level codes by ledger, report level, and values. The report level code will be applied to the selected range of accounts which you specify on the next screen.



Select the chart of accounts option Report Control Codes (Mass Maintenance). The selection screen displays.

```

GL884          Version 3 Demonstration Company  USER GBJBANB1  25/11/97
                                           14:10:07
Maintain Account Report Control Codes

Ledger . . . . . ? 2/L
Report level code . . . A
Change value from . ? 100 (** for all)
                  to . ? 110

F3=Exit      F4=Prompt

6-25      *      KS  CL      DM  II      MARVIN      KB      PKH312S1
  
```

Fields:

Ledger

Enter the ledger in which the control codes to be maintained reside. The code must be a valid ledger code as set up in Chart Of Accounts.

Report Level Code

Where the ledger selected has a reporting level set up, enter (or select) the appropriate code (A - E).

Change Value From ..

Enter the report code to be changed.

Or, enter From *** to select all codes at the report level entered.

Change Value To.

Enter the report code to be applied. This must be a valid report code defined for this ledger.



Press **Enter** to validate your selection and to display the Maintain Account Report Control

Codes.

Maintain Account Report Control Codes Screen 2

Use this screen to select the range of accounts for which the report control code change (entered at the previous screen) is to be applied.



Press **Enter** to validate your selection at Maintain Account Report Control Codes Screen 1 to display screen 2.

GL884	Version 3 Demonstration Company	USER GBJBANB1	25/11/97
			14:10:07
Maintain Account Report Control Codes			
Ledger : P/L Profit & Loss			
Select Account Codes From To			
Expense . . ? 300000 606130			
F3=Exit F4=Prompt F12=Previous			
10-30 * KS CL DM II MARVIN KB PKH312S1			

From ... To

Select a range of existing accounts at the level displayed.



Press **Enter** to validate your selection and to submit the job for processing.

User-Defined Keys Maintenance



21/GLM

At this procedure define and maintain your views. A view is a combination of account levels and/or extension levels defined by the user in any sequence. They are used to report balances held against accounts within the same ledger or across ledgers.

The following two sections demonstrate how to maintain ledger-specific user-defined views, and X-Ledger user-defined views.

Maintain User-Defined Views Selection Screen

A list of the views already defined to the system displays. All views in the list belong to a ledger or are X-Ledger (listed as ledger=blank). The extreme right-hand column shows year-end cleardown status.



Select the chart of accounts user-defined keys option Maintenance.

```

GL382                Version 3 Demonstration Company      USER GBJBANB1    10/12/97
                                                           11:15:48
Maintain User-defined Views

                                                           More:  +
                                                           < View>      C
                                                           <-Account level->
1  Lgr View description      1 2 3 4 5 6 7 8 9
-   Location                 - - - - - - - - 1
-   Registration number      - - - - - - - - 1
-   Cost Centre              - - - - - - - - 1
-   Project                  - - - - - - - - 0
-   Product                  - - - - - - - - 1
-   B/S Balance Sheet        1 - - - 2 - - - 0
-   COS Cost of Sales         1 - - - 2 3 4 5 - 1
-   COS Cost of Sales by product 4 - - - 5 3 1 2 - 1
-   P/L Profit & Loss         1 - - - 2 3 - - - 1
-   P/L Corporate Expense / Corporate Department - - - 1 2 - - - 1
-   REP Repairs by PCG/Account/Asset Type/Registration No. 1 - - - 2 3 4 - - 1

Position to ledger . . . . ? █
0=De-select 1=Build 2=Change 4=Delete-view 5=Enquire(X-ledger only)
6=Delete balances 7=Delete transaction X-references
F3=Exit F4=Prompt          F10=Add view F15=Build all F16=De-select all

21-32      *              KS CL IM DM II      MARVIN      KB      PKH312S1
  
```

Fields:

1 (Selection)

0 - De-select - Any views which you have previously selected to build (or to delete balances or transaction), may be de-selected by entering 0 in the option column.

1 - Build - Select the view to build by entering 1 in the option column. Or use the **F15=Build All** option to select all views. After selection use **F8=Confirm** to build the user-defined balances.

2 - Change. Make amendments to cross-ledger reference periods. Or select to keep links until an archive option is taken.

4 - Delete. A window displays with a warning about the balance/view deletion. Use **F11=Delete** to confirm the deletion or **Enter** to retain the view.

5 - Enquire. A window displays details of the cross-ledger level accounts for the view. Only cross-ledger views can be enquired on here.

6 - Delete Balances. Balances built for the view will be deleted. Budget balances, may also be deleted. The view itself will not be deleted. A window displays with a warning about the balance/view deletion. Use **F11=Delete** to confirm the deletion.

7 - Delete Transactions. A window displays with a warning that if you delete you will delete all transactions underlying the view balances: you will not be able to drill down from the period balances to those supporting transactions. Use **F11=Delete** to confirm the deletion, or **Enter** to cancel the deletion request.

Functions:

F10

Add Key. Allows you to add a new view.

F15

Build All. Selects all the views for building.

F16

De-select All. Removes the flag 1 against any views which have been selected for build.



To create a new user-defined view, press **F10=Add**. The Add A User-Defined View Selection window displays.

Change A User-Defined View Window (Option 2)

Use this option to set or amend the number of periods for which the balance-to-transactions links should be held. You may set to keep links until an archive is run.



To display this window enter 2 against a line in the Maintain User-Defined Views screen.

```

3L382                               Version 3 Demonstration Company          USER GBJBANB1    10/12/97
                                         14:46:55

Maintain User-defined Views

Change a User-defined View
Ledger . . . . . : P/L Profit & Loss
View description : Profit & Loss
Year end clear-down? 1 (0/1)
X reference periods.. 0 (99=Keep links until archive)  - - - - -
Level . . . . . Seq(1-9)
1 Expense..... 1
5 Corporate..... 2
6 Cost Centre..... 3

F3=Exit F8=Confirm F12=Previous
Position to ledger . . . . . ?
0=De-select 1=Build 2=Change 4=Delete-view 5=Enquire(X-ledger only)
6=Delete balances 7=Delete transaction X-references
F3=Exit F4=Prompt F8=Confirm F10=Add view F15=Build all F16=De-select all

1-1      *      KS CL IM DM II      MARVIN      KB      PKH312S1

```

The year end cleardown status displays. This was selected when the view was created.

Fields:

X-Reference Periods

1-98 - Enter the number of periods to retain your balance to transaction links (for the cross-ledger view).

99 - Keep links until archive. Cross referenced links will be retained for this user view until an archive option is run.



*Note: User-Views are archived at the GL utilities
Reorganise User View options and the
Reorganise Transaction X Reference option.*



Press **F8=Confirm** to update the amended user view.

Display A User-Defined View (Option 5)



Note: This option is available for Cross-Ledger Views only.

This enquiry screen displays details of the selected user-defined view. Details include year end clear-down status, X-Ledger periods, and code lengths - from which the selection was made. X-Ledger levels as selected for the view display.



This window displays when 5 is entered against a (cross-ledger) view in the Maintain User Defined Views screen.

```

GL382                Version 3 Demonstration Company        USER GBJBANB1    10/12/97
Display a User-Defined View
Mai  Ledger . . . . . : *ANY
      View description : Project
      Year end clear-down: 0 (0/1)
      X reference periods.. (99=Keep links until archive)
      X-Ledger level      Length (1-9)      X-Ledger level      Length (1-9)
1     Fiscal account      12                Corporate          6
-     Location            2                Asset Type           3
-     Registration no      7                Cost Centre          3
-     Country              2                Month               4
-     Contract Managr      3                Cost Type            1
-     Project Codes        4      1          Division           3
-     Product              3
-
-     F3=Exit  F12=Previous
-     REP Repairs by PCG/Account/Asset Type/Registration No. 1 - - - 2 3 4 - - 1
-
Position to ledger . . . . . ?
0=De-select 1=Build 2=Change 4=Delete-view 5=Enquire(X-ledger only)
6=Delete balances 7=Delete transaction X-references
F3=Exit F4=Prompt F8=Confirm F10=Add view F15=Build all F16=De-select all

1-1      *                KS CL IM DM II      MARVIN      KB      PKH312S1
  
```



Press **F12=Previous** to return to the selection screen or **F3=Exit** to leave the option. If build or delete requests are outstanding you will be asked to confirm exit or proceed with the build process.

Balance Deletion Requested Window (Option 6)

This window displays details of the selected ledger key (view). All balances for the view will be deleted although the view definition is retained.

The options available after deletion are:

- New balances could be built for transactions posted in the future.
- Balances could be rebuilt from historical transaction information (use option 1).

The option to delete budgets held for the view is also available.



Note: Budgets for a budget entry level view cannot be rebuilt after deletion.



To display this window select a line with 6 at the Maintain User-Defined Views selection screen.

```

GL382                Version 3 Demonstration Company      USER GBJBANB1    15/01/98
                                                              12:09:13
Maintain User-defined Views

                                                              More: -
                                                              < View> C
                                                              <-Account level->
1  Balance deletion requested                                7 8 9
2  Ledger . . . . REP                                       3 - - 1
3  Key . . . . Repairs By Registration No.                 1 - - 1
4  <- Level ->                                           4 5 - 1
5  1 2 3 4                                                1 3 - 1
6  - - - - - 1 - -
7
8  Delete budgets.. 0 (0/1)
9
10 Press F11 to confirm the request for deletion.
11 Press ENTER to retain the balances
12 F11=Delete
13
14 Position to ledger . . . . ?
15 0=De-select 1=Build 2=Change 4=Delete-view 5=Enquire(X-ledger only)
16 6=Delete balances 7=Delete transaction X=references
17 F3=Exit F4=Prompt F10=Add view F15=Build all F16=De-select all
18
19 15-24      *                K5 CL IM DM II      MARVIN    KB    PKH31251
  
```

Fields:

Delete Budgets

0 - Retain budgets held against the selected view.

1 - Delete any budgets held against the view.



Note: Entry Level budgets cannot be rebuilt after deletion.



Press **F11=Delete** to confirm deletion of your selection and to return to the previous screen. At exit from the option you may, again, be prompted to confirm outstanding deletions.

Transaction Link Deletion Requested Window (Option 7)

Use this option if you do not need to enquire on user-view data at the transaction level. It deletes all user-view balance-to-transaction links for the displayed ledger key (view). Enquiry on current balances for the view is still available.

A window displays, warning that if you delete you will not be able to drill down from the period balances to the supporting transactions. Otherwise confirm the deletion.



*Note: These links may be rebuilt if required.
Select the line with 1 at the Maintain User-Defined Views selection screen, and then press **F15=Rebuild All**.*



To display this window select a line with 7 at the Maintain User-Defined Views selection screen.

```

GL382                Version 3 Demonstration Company      USER GBJBANB1    15/01/98
                                                           13:00:06
Maintain User-defined Views                                More:  +
                                                           < View>          C
                                                           <-Account level-> 9
1  Transaction link deletion requested
- Ledger . . . . COS - - - 1
- Key . . . . Cost of Sales by product - - - 1
- <----- Account level -----> - - - 1
-   1 2 3 4 5 6 7 8 9 - 0 - 1
-   4 - - - 5 3 1 2 - - 0 - 1
-                                     - 1
- You have requested deletion of transaction cross references links. - 1
Z This means you will not be able to drill from the period balances - 1
- in this view to the supporting transactions - 1
- Press F11 to confirm the request for deletion. - 1
- Press ENTER to retain the key. - 1
- F11=Delete
Position to ledger . . . . ?
0=De-select 1=Build 2=Change 4=Delete-view 5=Enquire(X-ledger only)
6=Delete balances 7=Delete transaction X-references
F3=Exit F4=Prompt F10=Add view F15=Build all F16=De-select all

1-1      *                KS CL      DM II      MARVIN      KB      PKH31251
  
```



Press **F11=Delete** to continue or **Enter** to cancel the deletion request and exit the window.

Add A User-Defined View Selection Window (F10)

This window enables you to create a new user-defined view.



To display this window, press **F10=Add** at the User-Defined Views Maintenance screen.

Fields:

Ledger

Enter the ledger code of the ledger for which you want to define a view. The code must be a valid ledger code as set up in Chart Of Accounts.

Leave this field blank if you want to define a X-Ledger view.

View Description

Enter a description for the user-defined view of up to 45 characters in length.



Tip: The description should follow the order of level codes included and sequenced within the view.



Press **Enter** to accept. The levels defined for the specified ledger display.

Add A User-Defined Key Window

This window displays the levels belonging to the ledger specified on the previous screen.



This second window displays when **Enter** is pressed at the first Add A User-Defined View Selection Window (F10).

```

GL382                Y9 - Education Company - Y9                User FFY9                21/06/95
Add a User-defined Key
Mai
Ledger . . . . . P/L PROFIT & LOSS LEDGER
Key description . . Account/Cost Centre/Division
Clear down at year end.....:      1 (0/1)
                                   Sequence
                                   (1-9)
1  Account level 1  EXPENSE CODE.....:      1
-
-
-
Account level 5  Corporate.....:
Account level 6  Division.....:      3
Account level 7  Cost Centre.....:
-
-
-
F3=Exit              F12=Previous
P/L Division/Cost Centre/Account Type                3 - - - 1 2 - - 1

Position to ledger . . . . ?  _

0=De-select    1=Build    4=Delete    5=Enquire(X-Ledger Only)
F3=Exit  F4=Prompt    F10=Add key  F15=Build all  F16=De-select all
14-55    SP          MW          KS          IM          II  EDN400A  PCET02S3
  
```

Fields:

Clear down At Year End

0 - Do not clear down view balance at year end.

1 - Balances in the user-defined view should be cleared down at the end of the year.

Sequence

The structure of the ledger displays on the screen. Select the required levels to form the view, specifying the order in which they should appear. One or more levels may be chosen. Allocate the appropriate number in sequence. (1 = highest and 9 = lowest sequence level.)



Note: You may wish the sequence to match any sequence indicated in your view description.



Press **Enter** to accept the details and then **F8=Update** to confirm. You are then returned to the previous screen, where the view you have just defined is listed in order.

Maintain User-Defined Views Listing Screen

Select your ledger views to enquire on, build or delete.



This selection screen is returned to when other functions have been processed.

```

GL382          Y9 - Education Company - Y9          User FFY9          21/06/95
                                           17:15:06

Maintain User-defined Views

                                           More: -

                                           <-----Key-----> C
                                           <-Account level->
1  Lgr View description                    1 2 3 4 5 6 7 8 9
- 1 P/L Account/Cost Centre/Division      1 - - - 3 2 - - 1
- P/L Division                          - - - 1 - - - 1
- P/L Division/Cost Centre                - - - 1 2 - - 1
- P/L Division/Cost Centre/Account Type   3 - - - 1 2 - - 1

Position to ledger . . . . ? ____

0=De-select   1=Build   4=Delete   5=Enquire(X-Ledger Only)
F3=Exit  F4=Prompt  F8=Confirm  F10=Add key  F15=Build all  F16=De-select all
10-02    SF      MK      KS      IM      II  EDN400A  PCET02S3
  
```

Fields:

1 (Select)

1 - Build the view so that data applicable to its specified levels may be accessed.



Enter 1 against the view and press **Enter**.



Press **F8=Confirm** to update your choice for the build, and a window is displayed asking you for the period range for which balances are to be built for that view.

Build User-Defined Balances Window

The window displays when you have selected views for rebuild and have opted to exit or update. One or more views must have been selected to build with option 1, or you may have selected all views for rebuild with the **F15=Build All** option.

The system will build period balances for all views displaying 1 on the Maintain User-Defined Views Selection Screen.

 *Note: Enquiries and reports on user-defined views may be carried out or printed once the views have been built.*

 This window displays when views have been selected for rebuild and you have pressed **F8=Confirm** or **F3=Exit** at the Maintain User-Defined Views screen.

GL382 Y9 - Education Company - Y9 User FFY9 21/06/95
17:15:06

Maintain User-defined Views

Build User-Defined Balances
From period : 9401
To period : 9413
Please press ENTER

More: -
Key-----> C
unt level->

1	Lgr View description	1	2	3	4	5	6	7	8	9
-	1 P/L Account/Cost Centre/Division	1	-	-	-	3	2	-	-	1
-	P/L Division	-	-	-	-	1	-	-	-	1
-	P/L Division/Cost Centre	-	-	-	-	1	2	-	-	1
-	P/L Division/Cost Centre/Account Type	3	-	-	-	1	2	-	-	1

Position to ledger ? __

Q=De-select 1=Build 4=Delete 5=Enquire(X-Ledger Only)
F3=Exit F4=Prompt F8=Confirm F10=Add key F15=Build all F16=De-select all
05-60 SF MK KS IM II EDN400A PCET02S3

Fields:

From Period ..To Period

Enter the start and end of the period(s) within which you wish the view to be updated.

 Enter periods and press **Enter**.

X-Ledger User-Defined Views Maintenance

- ➡ Select the Chart of accounts option to maintain User-defined Views. You are taken to the initial entry and selection screens. Press **F10=Add Key** to add a user-defined view at the Add a User-defined Key window.

At this window select a ledger for the view, or leave blank for a cross-ledger view.

```

GL382          Y9 - Education Company - Y9          User FFY9          21/06/95
                                           17:18:55

Maintain User-defined Views

Add a User-defined Key
Ledger . . . . . ?   (Leave blank for a cross-ledger key)
Key description . : Account Code by Area
1 F3=Exit  F4=Prompt  F12=Previous
- Asset Type - - - - - 0
- Asset Type/Nominal - - - - - 0
- Cost Centre - - - - - 1
- Cost Centre/Employee - - - - - 1
- Product Group - - - - - 1
- Product Group/Account Type - - - - - 1
- Employee - - - - - 1
- P/L Account/Cost Centre/Division 1 - - - 3 2 - - 1
- P/L Division - - - - 1 - - - 1
- P/L Division/Cost Centre - - - - 1 2 - - 1
- P/L Division/Cost Centre/Account Type 3 - - - 1 2 - - 1

Position to ledger . . . . ?

0=De-select  1=Build  4=Delete  5=Enquire(X-Ledger Only)
F3=Exit  F4=Prompt  F10=Add key  F15=Build all  F16=De-select all
07-48  SP  MW  KS  IM  II  EDN400A  PCET02S3
  
```

Fields:

Ledger

Leave this field blank if you want to define a X-Ledger view.

View Description

Enter a description for the user-defined view of up to 45 characters in length.

It is suggested that the description should follow the order of level codes included and sequenced within the view.

- ➡ Press **Enter** to display a list of all the X-Ledger levels which have been set up in the company's Chart of accounts.

Select and sequence those X-Ledger levels you want to include in the view - enter the appropriate number against the appropriate level. Numbers 1 to 9 are allowed.

 **Note:** A X-Ledger user-defined view can only hold X-Ledger levels.

 **Warning:** There are only 36 X-Ledger levels available on the system.



Press **Enter** and then **F8=Update** to confirm your choice. The initial entry/selection screen redisplay.

To build the X-Ledger user-defined view, enter 1 against the displayed view and press **F8=Confirm**. See the Build User-Defined Balances Window for more information.

Hierarchy Rules Maintenance



31/GLM

The hierarchy rules enable you to specify an account or range of accounts, the period, the company and the percentage of the account values to be selected for a hierarchy.

The rules, therefore, allow you either to create accounts for a hierarchy en masse, or to enter them one by one for a specific hierarchy. Having created the rule for the hierarchy, any new accounts added to the Chart Of Accounts will be included within the hierarchy unless you decide otherwise.



Note: This field only displays when you are creating a new hierarchy.



Press **Enter** to display the Rules Maintenance Screen.

Alias Method Window (F14)

Hierarchy control account codes consist of 12 characters as set up in the Chart Of Accounts. If required, you may rename each account to allow you to extract information from the alias account instead of being restricted to the hierarchy code itself.

There are four ways of defining the alias structure, three of which base the alias on a view of an account as defined in the Chart Of Accounts.

The method of defining an alias is the same whether you are adding a single account or a range of accounts.



From the Maintain a Hierarchy's Rules first selection screen press **F14=Aliases** to make your account selection.



*Note: **F14=Aliases** is also available from the Add Single Account Window.*

GL480	Z1 - GB Demonstration Company	User GBJBA1MS	16/12/97 9:54:01
Maintain a Hierarchy's Rules			
Hierarchy	: 899011		
Ledger	: ?	(Blank=Cross-Ledger)	

Alias method			
1	Hierarchy view		
2	Ledger view		
3	Selected view		
4	Text		
Select method 4			
F12=Previous			

F3=Exit	F4=Prompt	F12=Previous	F14=Alias method
16-52	SA	MW	KS CL IM DM II STUD140 KB PKH312S1

Fields:

Select Method:

1 - Hierarchy View. Any view of the original ledger may be used to format the alias of the top level of the hierarchy. This same format will be used for aliases in the lower levels in the hierarchy.

2 - Ledger View. Any view of the original ledger may be used to format the alias of the top level of the hierarchy. Any view of the original ledger may be used to format the alias of the lower levels in the hierarchy. The alias format for the top level may be different from the lower level.

3 - Selected View. The format of the top level alias can be based on any ledger, while the format of lower levels is based on any view of the original ledger.

4 - Text. Option 4 displays as a default (most commonly used). The alias is a text description, and is not based on a view format.



When you have selected an alias method, and selected a ledger account (where prompted) you will be prompted to enter a hierarchy name.

The alias for a top-level hierarchy will be entered immediately (according to the method chosen). From then on the values cannot be amended, and the alias fields displayed will be those associated with the lower-level accounts, as they are added to the hierarchy.

- Select the ledger of the alias account (or range of accounts) to be added to this rule.
- Then select the view required, and the structure of that view will be displayed so that it can be used for the alias.
- Enter the alias account as required.
- When you have entered the single accounts, return to the main screen to see the new accounts listed.



Press **Enter** to display the Rules Maintenance Screen.

Maintain A Hierarchy's Rules Screen

Any existing rules are displayed on the screen. For a new hierarchy, no rules will exist.



Press **Enter** from the Hierarchy's Rules Maintenance Selection Screen.

```

GL400          Z1 - GB Demonstration Company      User PRODSUPP      19/07/96
                                           12:07:52

Maintain a Hierarchy's Rules

Hierarchy . : HIER04      CONSOLIDATE HIERARCHY

1 Seq Account / Rule Description      Levels      Alias      More:
- 10 HIER01                          100.00      0 Z1
- 20 HIER02                          100.00      0 Z1
- 30 HIER03                          100.00      0 Z1

Position to sequence number . █

1=Amend      3=Copy      4=Delete
F3=Exit      F5=Resequence
F12=Previous F13=Single Account F15=Copy rules F10=Add a rule F11=Delete
20-32      SF      ML      KS      IM      II KENB20A PET149S2
  
```



Note: The description of the hierarchy relating to the parent account (a valid memo account as set up on the Chart Of Accounts) is displayed at the top of the screen.

Fields:

Select (1)

- 1 - Amend. Allows you to select an individual rule and to amend it.
- 3 - Copy. Allows you to make a copy of an individual rule, which would be useful if you wish to set up two or more rules which are similar in their parameter definition.
- 4 - Delete. Allows you to select and delete individual rules.

Functions:

F5

Resequence. The sequence of the rules listed here is significant in that it is used in the hierarchy enquiry. Change the sequence by amending the sequence numbers and then pressing **F5=Resequence**.

F10

Add a Rule. Allows you to add a range of new accounts to the hierarchy. The maximum number of accounts is 9999.

F11

Delete. Delete the rules.

F13

Single Account. Allows you to add a single account to the hierarchy.

F15

Copy Rules. Allows you to copy rules from one or more other accounts.



Select a function or option or press F3=Exit to return to the first screen.

Add Single Account Window (F13)

Add a single account in the hierarchy by selecting sequence number, company and account.



To include a single account in this hierarchy, press **F13=Single Account**, and the Add Single Account window displays.

GL480		Y6 - Education Company - Y6		User FFY6		31/07/95 12:37:20	
Maintain a Hierarchy's Rule							
Hierarchy . : ASSETS / /							
1 Seq	Account / Rule Desc						
- 10	213000						
- 20	215000						
- 30	218000						
- 40	218300						
- 50	281300						
- 60	281500						
- 70	281820						
- 80	281830						
Position to sequence number		Add Single Account Sequence number 90 Company ? Y6 1 Account ? Percentage . 100.00 Period lag . F4=Prompt F12=Previous F14=Aliases				Co Y6 Y6 Y6 Y6 Y6 Y6 Y6	
1=Amend 3=Copy 4=Delete F3=Exit F5=Resequenece F10=Add a rule F11=Delete F12=Previous F13=Single Account F15=Copy rules 04-58 SP MW KS IM II KENB20A PCET02S1							

Fields:

Sequence Number

This field defaults to a sequence setting of 10 after the previous rule. This can be amended as required.

Company



Note: As long as the full account short code is specified for the hierarchy, then the company can be changed when selecting a single account.

Enter the company as required.

Account

Enter the 12-character account code of the account to be selected for the hierarchy.

Percentage

Enter the percentage of the balance to be aggregated into the hierarchy control account.

Period Lag

If you wish to pick up balances from an earlier period and not from the current period, enter the period lag here.

To aggregate the balances from the last period, for example, enter 01; or 02 for the period before that.

This could be used to hold rolling quarterly figures, for example.



Enter the single account details as required, then press **F8=Update**. The details you have entered will appear on the screen beneath the window, but the window will remain so that you can continue to enter accounts.



If you are using aliases rather than hierarchy account codes, press **F14=Aliases** to make your account selection.

Add A Range Of Accounts (F10)

Select a range of accounts to be added for the rule.



To include a range of accounts in this hierarchy, press **F10=Add a rule**.

GL400	Y6 - Education Company - Y6	User FFY6	31/07/95 12:43:23
Maintain a Hierarchy's Rules			*ADD
Hierarchy . . :	ASSETS	ASSETS	
Sequence . . .	90	Rule 0090, hierarchy ASSETS	Company Y6
Ledger . . . ?	B/S	(Leave blank for all)	
F3=Exit 06-17	F4=Prompt SF	F12=Previous MW KS	F14=Aliases IM II KENB20A PCET02S1

Fields:

Sequence

Enter the sequence number to place the rule as required in the list on the main screen.

This field defaults to the place below the previous rule.

Description

Accept or amend the description which is allocated to the rule (by the system).

Company

This defaults to the company for which the hierarchy has been created. Accept the company or enter a different company code, which you might do for the creation of consolidated accounts.

Ledger

Enter the ledger code of a valid ledger set up on the Chart Of Accounts, or leave the field blank to accept all ledgers.

If you specify a particular ledger, the accounts selected for this hierarchy rule will originate only from that ledger. If you leave the fields blank, accounts for the hierarchy will be selected across all ledgers for the company.



Press **Enter** to display the account range selection fields based on the account code and ledger.

-  If you are using aliases rather than hierarchy account codes, press **F14=Aliases** to make your selection of account level structure.
-  If you are not using aliases, press **Enter** the account range selection fields will be displayed.

Maintain A Hierarchy's Rules Selection Screen

Select a range of accounts level codes and the number of lag periods for the rule.



Press **Enter** at the Add A Range Of Accounts (F10) screen to display the account range selection fields, based on the account code and ledger.

GL480	Y6 - Education Company - Y6	User FFY6	31/07/95 12:43:54
Maintain a Hierarchy's Rules			*ADD
Hierarchy . . :	ASSETS	ASSETS	
Sequence . . :	90	Rule 0090, hierarchy ASSETS	Company Y6
Level Code	1 ACCOUNT TYPE ?		
Report Code	A ACCOUNTS SEQ.NO . . . ?		
Type of Account	3 (1=Fiscal,2=Memo,3=Both)	Percent	100.00
Period lag		0	
F3=Exit F4=Prompt F12=Previous 00-43 SF MW KS IM II KENB20A PCET02S1			

Fields:

Level Code From

Enter the name of the first level code in the range of level codes you want to be selected for this hierarchy, or leave this and the To field blank to accept all codes at this level.

You may use the asterisk * as a wildcard to specify one part of a level code.

The system will select only those accounts which comply with the level code specifications set here.

Level Code To

Enter the name of the first level code in the range of level codes you want to be selected for this hierarchy, or leave this and the From field blank to accept all codes at this level.

You may use the asterisk * as a wildcard to specify one part of a level code. The system will select only those accounts which comply with the level code specifications set here.

Type Of Account

Enter the type of account to be selected for this hierarchy rule.

- 1 - Only fiscal account.
- 2 - Only memo account.
- 3 - Both fiscal and memo accounts.

Values from these child accounts will be used to write a table of accounts which are entered into the hierarchy control account. This field will be displayed only if the full short account code is used for the hierarchy.

Percentage

Enter the percentage of the value you want to be included in the hierarchy. You can enter any value from 0.01% to 99.99%, or accept the default of 100%.

This field will be displayed only if the full short account code is used for the hierarchy.

Period Lag

Enter the number of periods you want to lag. Enter 00 for the current period, 01 for the previous period, and so on.

This field will be displayed only if the full short account code is used for the hierarchy.



Enter the range of accounts as required, and press **Enter**, then **F8=Update** to confirm the entries. You will be returned to the main screen, where you will see the new rules listed.

Maintain A Hierarchy's Rules Screen

Simply lists details of your newly created hierarchy rules.



Press **Enter** at the Hierarchy's Rules Account Range Selection Screen then **F8=Update** to confirm the entries. The main screen displays with your new rules listed.

GL400	Y6 - Education Company - Y6	User FFY6	31/07/95
			12:45:54
Maintain a Hierarchy's Rules			
Hierarchy . : ASSETS ASSETS			*AMEND
/ /			
1 Seq	Account / Rule Description	Levels	More:
			Alias % Lag Co
- 10	213000		100.00 0 Y6
- 20	215000		100.00 0 Y6
- 30	218000		100.00 0 Y6
- 40	218300		100.00 0 Y6
- 50	281300		100.00 0 Y6
- 60	281500		100.00 0 Y6
- 70	281820		100.00 0 Y6
- 80	281830		100.00 0 Y6
- 90	Rule 0090, hierarchy ASSETS	1	100.00 0 Y6
Position to sequence number . ____			
1=Amend	3=Copy	4=Delete	
F3=Exit	F5=Resequene	F8=Update	F10=Add a rule F11=Delete
F12=Previous	F13=Single Account	F15=Copy rules	
17-02	SF	MW	KS IM II KENB20A PCET02S1



Press **F8=Update** to update the hierarchy with the new or amended rules, and the hierarchy creation window will be displayed.

Enter Details Of Hierarchy Creation Window

This is your option to decide on accumulation of budgets/forecasts.



To display this window press **F8=Update** at the main Maintain A Hierarchy's Rules Screen.

GL480		Y6 - Education Company - Y6		User FFY6	31/07/95 12:45:54
Maintain a Hierarchy's Rules					
					*AMEND
Hie	Enter Details of Hierarchy Creation				
	Hierarchy . . . ASSETS ASSETS				
1 S	Accumulate budgets & forecasts? 1 (0/1)				Lag Co
--					0 Y6
--	Print all levels of the new hierarchy? 1 (0/1)				0 Y6
--	ENTER=Proceed F12=Previous				0 Y6
--	40	218300		100.00	0 Y6
--	50	281300		100.00	0 Y6
--	60	281500		100.00	0 Y6
--	70	281820		100.00	0 Y6
--	80	281830		100.00	0 Y6
--	90	Rule 0090, hierarchy ASSETS		1	100.00 0 Y6
Position to sequence number . ____					
1=Amend 3=Copy 4=Delete					
F3=Exit		F5=Resequence		F8=Update	F10=Add a rule F11=Delete
F12=Previous		F13=Single Account		F15=Copy rules	
08-56		SF		MM	KS IM II KENB20A PCET02S1

Fields:

Accumulate Budgets & Forecasts?

0 - You do not want to accumulate budgets and forecasts for this hierarchy.

1 - You do wish to accumulate budgets and forecasts, in which case values will be accumulated for each budget/forecast record for each account within this hierarchy.

Values will be accumulated whenever you create or amend a budget or forecast for an account within this hierarchy. If you accumulate values for a higher hierarchy, make sure that you do so at lower levels down to the level at which you intend to post individual account budgets or forecasts.

Print All Levels Of New Hierarchy?

0 - Do not print all levels within the hierarchy.

1 - Print all hierarchy levels.



Enter the values required and press **Enter**. The entry screen displays. Press **F3=Exit** to exit. The period range field is added.

Period Range

Enter the range of periods over which the hierarchy should be rebuilt. This defaults to the system year.



Note: Wait until the job has completed before enquiring on the hierarchy you have set up.



Enter the values as required, and press **Enter**. A batch job will be submitted to create the hierarchy.

Changing Company Within A Hierarchy

When you are specifying a single account or a range of accounts to be aggregated into the hierarchy control account, you may find a Company field displayed. This field enables you to select accounts from a company other than the current one, and will be displayed only under certain conditions:

- 1 - The hierarchy account that you are working in must include the whole of the account short code in its definition.
- 2 - If you are specifying a range of accounts, then the sub ledger field must be blank.

Rebuild Hierarchy



32/GLM

This option enables you to:

- Build an existing hierarchy over a different year.
- Correct a hierarchy in which the parent is out of balance with its children.



Select the Rebuild option (Chart of accounts) to see the following fields:

Hierarchy

Enter the hierarchy you wish to rebuild.

Period Range

Enter the period range over which the hierarchy is to be rebuilt.



Press **Enter**, and a job will be submitted to perform the rebuild.

Chart Of Accounts Report



41/GLM



Select the chart of accounts Report option to see a screen offering the following reports.

- Option 1 - Gives you a report which lists the account codes and default extension codes within the Chart Of Accounts.
- Option 2 - Gives you a report which lists the account codes and report levels within the Chart Of Accounts.
- Option 3 - Only appears if the company within which you are working has been consolidated. It gives a report listing the target accounts.

An audit trail of account level code changes and additions is available from the menu.

Account Code Reporting

Two reporting options are available to report on account level codes:

- Account Level Codes.
- Report Control Codes.

Account Level Codes Report



42/GLM

This procedure produces a report of changes made to the account level codes. An audit trail of account level code changes and additions is available.



Select Account Level Codes (Reports) option, and select the ledger you wish to report on.



Press **Enter** to accept, then **F8=Confirm**. The print job will be submitted for processing.

Report Control Codes Report



43/GLM

A screen will enable you to enter a single ledger, or leave the field blank to select all ledgers for the report.

A report of all the report control codes for the selected ledgers will be produced.

An audit trail of account level code changes and additions is available.



Select the chart of accounts option Report Control Codes (Account Reports) to run this report.

Ledger Descriptions Report



44/GLM

This report lists a history of changes made to the ledger records.



Select the Ledger Descriptions Report from the menu to display the following fields:

Fields:

Date Range

Enter the range of dates you want to cover for this report. Leave both fields blank to accept all dates.

Clear Data

Enter 1 to delete the change history data once the report has been produced.



Press **Enter** to accept. A second screen will be displayed with confirmation of the details you have entered. Press **F8=Confirm** to confirm.

An audit trail of ledger description changes and additions is available.

Linked Levels Report



45/GLM

This report gives details of linked levels between your account codes and extension codes and extension linked to extension codes.



Select the Linked Levels option (Account Reports) to see a ledger selection screen.



Select the ledger you wish to report on, or leave the field blank to select all ledgers. Press **Enter** to accept then **F8=Confirm**. The print job will be submitted for processing.

Hierarchy Reporting

Two options are available to report on your Chart Of Accounts hierarchies:

- Hierarchy Structure Report.
- Hierarchy Rules Report.

Hierarchy Structure Report



51/GLM



Select the Structure option (chart of accounts),
and the following fields will be displayed:

From Hierarchy

Enter the first hierarchy in the range of hierarchies you want to appear in the report.
Leave the field blank to start from the first hierarchy on the system.

To Hierarchy

Enter the last hierarchy in the range of hierarchies you want to appear in the report.
Leave the field blank to end at the last hierarchy on the system.

Print All Levels?

0 - To limit the print to extended codes.

1 - Print all levels.



Press **Enter**, then **F8=Update** to update.

Hierarchy Rules Report



52/GLM



Select the Hierarchy Rules Report option (chart of accounts). The following fields are displayed:

From Hierarchy

Enter the first hierarchy in the range of hierarchies you wish to appear in the report.

Leave blank to start from the first hierarchy on the system.

To Hierarchy

Enter the last hierarchy in the range of hierarchies you wish to appear in the report.

Leave blank to end at the last hierarchy on the system.



Press **Enter** then **F8=Update** to accept.