

-
-
-
-
-

Chapter 1

Maintenance



Advanced Customer Scheduling Maintenance

Default processing indicators are held against the contract, and all the associated Schedule details.

Defaults are held at company, customer / delivery sequence and contract / release / DCI levels.

- When new customer defaults are created they are defaulted from the company level.
- When new contract / release / DCI defaults are created they are created from the customer / delivery sequence level.

Defaults are always created for a contract whenever a new contract is created.


- Contract defaults define processing methods that are common to both releases and DCI requirements.
- Release and DCI defaults define processing methods that are specific to either the release or the DCI.

Customer / Delivery Point Defaults

1... 1/ACM **2...**

Customer defaults are held at customer / delivery sequence level. In general, whenever customer defaults are created the corresponding company defaults are used as default values. Company defaults **MUST** exist before any customer parameters can be maintained.

Advanced Customer Scheduling Customer defaults are entered via the Customer / Delivery Point Details option. This option navigates through up to six possible input screens, which are linked together as follows:



Customer Defaults Screen



Select Customer / Delivery Point Defaults from the menu to display the Customer Defaults screen.

```
AC015          Z1 - GB Demonstration Company    User GBJBA1MS    13/10/97
                                     14:56:05

Customer Defaults

Customer ....?.. █

F3=Exit  F4=Prompt

5-22  SA  AW  KS  CL  IA  DA  II  EDN400A  KB  PET178S1
```

Fields:

Customer

Enter a customer code or ? to display a Customer Scan Window. An incomplete customer name or number can be entered to search for a customer. This window will only present customers that are registered with the Advanced Customer Scheduling/Advanced Customer Shipping products.



Select **Enter** to display the Customer Defaults - Contracts screen.

Customer Defaults - Contracts Screen



Select **Enter** from the Customer Defaults screen to display the Customer Defaults - Contracts screen.

```

AC030          Z1 - GB Demonstration Company   User GBJBA1MS   13/10/97
                                                16:21:27

Customer ... ABC01   000   ABC Holiday Shop Ltd

Customer Defaults - Contracts
DCI/RAN processing ..... 1 (0/1/2) 0=No   1=DCI   2=RAN processing

Customer Defaults - Release Information

Call-Off type ..... 0   0=Daily   1=Timed
Default time ..... :00
Reconciliation method ...? 01   cumulative quantity
Annears processing method? 01   Normal Annears
Authorisation method ....? 01   Authorisation Code
Automatic update from EDI? 0   No EDI update
Validation rule .....? 01   Validation Rule 01
Creation rule .....?
Unique date/time ..... 1 (0/1) Hold eng. changes..... 0 (0/1)
No EDI Release = no reqmt.. 0 (0/1) Override auto update.? 0 (Blank, 0-4)
Text processing method...? 0   Drop text on consolidation
Despatch Type ..... 1 (0/1) Stock Transfer Consignment

F3=Exit F4=Prompt F12=Previous F17=Mandatory Fields

6-30  SA  NW  KS  CL  IA  DA  II  EDN400A  KB  PET178S1

```

Fields:

DCI / RAN Processing

Enter the DCI RAN processing indicator. The default is 0.

0 - Daily Call In's and RANs will not be processed.

1 - Daily Call In's are to be processed.

2 - RAN details are to be processed.

Customer Release Defaults

Call Off Type

This field is used to determine whether the deliveries are made to a time.

Enter 1 if deliveries are timed.

Enter 0 if deliveries are not timed. This is the default.

Default Time

Enter a default time for timed deliveries. This is the time the goods will normally be delivered. Enter the time in HH:MM format. The default is 00:00.

Reconciliation Method

This indicates the type of data supplied by the customer for reconciling new issues. The **F4=Prompt** key is available. The default is blank, forcing an entry.

'01' - cumulative quantity

'02' - last despatch note

'03' - both (cumulative quantity and last despatch)

'04' - assumed

'05' - Nissan RAN

'06' - none

Arrears Processing Method

This is the method of processing arrears. The **F4=Prompt** key is available. The default is blank forcing a value to be entered.

'01' - normal arrears. The customer either sends a total of arrears or sends dated requirements which are dated before the issue date.

'02' - restated arrears. The customer restates the arrears either as a new requirement or accumulated in with the forward release. The net result is that the arrears are dated on or after the new issue date.

'03' - assumed arrears. The customer does not send arrears information but assumes that the supplier will still send overdue requirements.

Authorisation Method

Enter the method used to determine the authorisation code. The **F4=Prompt** key is available. The default is blank.

'01' - authorisation code. The customer sends the appropriate code via EDI or else it is manually entered.

'02' - date horizons. The customer sends date horizons which vary from release to release.

'03' - cumulative quantity. The customer sends cumulative quantities which vary from release to release.

'04' - fixed horizons in calendar days. Date horizons are determined using the fixed horizons in days relative to the synchronisation date of the release. The fixed horizons normally remain the same during the life of a contract.

Automatic Update From EDI

This is the automatic update from EDI indicator. The **F4=Prompt** key is available. The default is blank forcing a default to be entered. Enter one of the following values:

0- No EDI update.

1 - Process into AI files only.

2 - Validate only.

3 - Validate and run comparison.

4 - Validate, run comparison and update current if all is OK.

Validation Rule

This is the rule for validating EDI transmission. The **F4=Prompt** key is available.

Creation Rule

This is the rule for mapping EDI transmissions. The **F4=Prompt** key is available.

Unique Date/Time

This is the unique date / time indicator. The default is 0.

0 - no unique date / time required.

1 - unique date / time required.

Hold Engineering Changes

This flag indicates if the system will hold a new schedule if the engineering change value of the new schedule is different to the engineering change value on the contract. The default is 0.

0 - do not hold release.

1 - hold release.

No EDI Release=No Reqmt

This field is reserved for future use.

Override Auto Update

This field is designed to hold a temporary override to the EDI Update flag. The EDI update, comparison and acceptance sleeper programs will all check this field and if not blank, use it instead of the EDI update indicator on the contract. The **F4=Prompt** key is available.

0 - No EDI update.

1 - Process into AI files only.

2 - Validate only.

3 - Validate and run comparison.

4 - Validate, run comparison and update current if all is OK.

Text Processing Method

This is the processing indicator which describes how any customer sent schedule text is actioned. The descriptions are held on the Descriptions file type - TXPM. The default is zero. The **F4=Prompt** key is available.

0 - Drop text on consolidation.

1 - Merge text on consolidation.

2 - Earliest text takes precedence.

3 - Latest text takes precedence.

Despatch Type

A sales order is created when goods are despatched directly to a customer and when goods are despatched to a consignment stockroom a transfer order is created.

Enter one of the following:

0 = Sales Order. This is the default.

1 = Transfer Order.



Select **Enter** to display the Customer Defaults -
Release Authorisation Codes screen

Functions:

F17

Mandatory Fields. This displays the Mandatory Fields screen which allows you to determine. in certain cases, which fields are mandatory and which are optional.

Customer Mandatory Fields Screen (F17)

This screen allows you to determine which of the displayed screen fields are processed as mandatory entry and which are processed as optional entry.

 Select **F17=Mandatory Fields** from the Customer Defaults Contracts screen to display the Customer Mandatory Fields screen.

AC017

Z1 - GB Demonstration Company

User GBJBACHG

16/10/97
14:32:50

Customer ... ABC01 000 ABC Holiday Shop Ltd

Customer Mandatory Fields

Application Screen/Field	Mandatory(0/1)
Contract Header - Customer Order Number	0
Contract Header - Customer Item Number	0
Contract Header - Customer Order Date	0

F3=Exit F12=Previous

9-74 SA HW KS CL IM DM II EDN400A KB PET178S1

Fields:

Mandatory

Enter one of the following against each line:

- 0 - Optional. The field is processed as an optional field.
- 1 - Mandatory. The field is processed as a mandatory field.

 Select **Enter** to confirm the data you have entered and display the Customer Defaults Contract screen.

Customer Defaults Release Authorisation Codes Screen



Select **Enter** from the Customer Defaults Contracts screen to display the Customer Defaults - Release Authorisation Codes screen

AC030	Z1 - Demonstration Company		User QPGMR	29/01/96	
				10:07:15	
Customer defaults - Release authorisation codes.					
Customer ...	F100	001	Ford Cologne		
Authorisation codes	1	2	3	4	5
Descriptions	<u>FIRM</u>	<u>MATERIAL</u>	<u>FORECAST</u>		
Mandatory reference	<u>0</u>	<u>0</u>	<u>0</u>	-	-
Unique reference	<u>0</u>	<u>0</u>	<u>0</u>	-	-
Fixed horizon days	<u>30</u>	<u>60</u>	<u>180</u>	-	-
Pass to planning appls.	<u>1</u>	<u>0</u>	<u>0</u>	-	-
F3=Exit F12=Previous F21=Release Comparison rules					
09-27 SP MK KS IM II KENB20A PET007S1					



Note: There are five authorisation columns shown in the company, customer, and contract release default screens. These are colour coded as follows:

Period 1 - Red

Period 2 - White

Period 3 - Green

Period 4 - Pink

Period 5 - Blue

Fields:

Description

Enter the authorisation descriptions, typically:

'FABRICAT

MATERIAL

FORECAST'

Mandatory Reference

Enter a 1 in this field if a mandatory reference is required, otherwise enter 0.

Unique Reference

This is the unique reference indicator. The default is 0.

0 - no unique reference is required.

1 - a unique reference is required.

Fixed Horizon In Days

Enter the fixed horizon as a number of calendar days relative to the previous authorisation code.

If this is the first authorisation code (period 1) it will be relative to the customer stated release date as entered by the user.

This field is only valid if the authorisation method is '04'.

Pass To Planning Applications

Enter a 1 in this field if the schedule requirements for this authorisation period are to be passed as a firm requirement to the MRP / MPS planning system.

Leave blank if not required.



Press **F21=Release Comparison Rules** to enter Release Comparison Rules.

Functions:

F8

Saves any changes made up to this point and returns to the menu. If the DCI flag is set to 1, this function key will be prohibited on the first pass through the Customer Profile Maintenance for a particular customer, forcing the user to visit every applicable screen prior to update.

F21

This displays the Release Comparison Rules for this Customer.

Customer Defaults Release Comparison Rules Screen (F21)

This screen can be reached by pressing **F21=Release Comparison Rules** from the Customer Defaults - Release Authorisation Codes Screen.

You do not have to enter any rules, but any values entered here will be used to default to the customer release comparison rules.

You can add new default rules by entering them at the bottom of the screen, and you can delete any existing rules using option 4 in the Select field. To replace or change a rule, you must first delete, then add the new rule.

AC040	Distribution V3 -> V3 Financials	User GBJBAPH2	16/02/96 12:37:11	
Customer defaults - Release comparison rules.				
Customer NH001 000 Northern Motor Spares Limited				
SEL	Comparison Method & Description	Rule	Description Prim.	
-	1 New Rel/Prv rel, latest rev.	002	Releases - Weekly Comp.	
-	2 New rel/Prv rel, revision 000	003	Rule 3	1
Comparison method.?. Z Rule.....?. █ Primary indicator... _				
4=Delete				
F3=Exit F4=Prompt F8=Update F12=Previous				
21-42 S MW K IM II KENB20A PET087S1				

Fields:

Comparison Type

Enter a comparison type:

- 1 - New Schedule / Previous Schedule, Latest Revision.
- 2 - New Schedule / Previous Schedule, Revision Zero.
- 3 - New Revision / Previous Revision.
- 4 - New Revision / Revision Zero.

Comparison Rule

Enter the comparison rule number.

Primary Rule

Enter 1 if a rule is the primary rule to be used in the on-line comparison enquiry.

There can only be one primary rule for comparison methods 1 and 2, and one primary rule for methods 3 and 4. At least one rule must be defined as the primary rule.

Functions:

F8

Updates the rules and returns to Customer Defaults - Release Authorisation Codes screen.



Press **F8=Update** to return to the Customer Defaults - Release Authorisation Codes screen. Then press **Enter** to continue.

Customer Defaults Daily Call Ins Default Screen



This screen is reached by pressing **Enter** from Customer Defaults - Release Authorisation Codes screen.

AC035	Z1 - Demonstration Company	User QPGMR	29/01/96 10:09:04
Customer Defaults - Daily Call In's			
Customer ... F100	001	Ford Cologne	
DCI/RAN processing	1	(0/1/2) 0=No	1=DCI 2=RAN processing
Call-off type	1	0=Daily	1=Timed
Default time	15:00		
Reconciliation method ...?	01	cumulative quantity	
Arrears processing method?.	01	Normal Arrears	
Automatic update from EDI?.	4	Validate, compare and accept	
Validation rule	—		
Creation rule	—		
Hold eng. changes.....	0	(0/1)	
Unique date/time	0	(0/1)	
Mandatory reference	0	(0/1)	
Unique reference	0	(0/1)	
No EDI DCI = no reqmt.....	0	(0/1)	Override auto update.?.
Text processing method...?	0	Drop text on consolidation	
F3=Exit F4=Prompt F8=Update F12=Previous F21=DCI Comparison rules			
08-30	SP	MK	KS IM II KENB20A PET007S1

Fields:

Call Off Type

This field is used to determine whether the deliveries are made to a time.

0 - Deliveries are not timed. This is the default.

1 - Deliveries are timed.

Default Time

This is where you enter a default time for timed deliveries. This is the time the goods will normally be delivered. Enter the time in HH:MM format. The default is 00:00.

Reconciliation Method

This indicates the type of data supplied by the customer for reconciling new issues. The default is blank, forcing an entry. The **F4=Prompt** key is available.

'01' - Cumulative quantity.

'02' - Last despatch note.

'03' - Both (cumulative quantity and last despatch).

'04' - Assumed.

'05' - Nissan RAN.

'06' - None.

Arrears Processing Method

This is the method of processing arrears. The default is blank forcing an entry to be made. The **F4=Prompt** key is available.

'01' - Normal arrears. The customer either sends a total of arrears or sends dated requirements which are dated before the issue date.

'02' - Restated arrears. The customer restates the arrears either as a new requirement or accumulated in with the forward release. The net result is that the arrears are dated on or after the new issue date.

'03' - assumed arrears. The customer does not send arrears information but assumes that the supplier will still send overdue requirements.

Automatic Update From EDI

This is the automatic update from EDI indicator. The default is blank. One of the following values must be entered: The **F4=Prompt** key is available.

0 - No EDI update.

1 - Process into AI files only.

2 - Validate only.

3 - Validate and run comparison.

4 - Validate, run comparison and update current if all is OK.

Validation Rule

This is the rule for validating EDI transmissions. The **F4=Prompt** key is available.

Creation Rule

This is the rule for mapping EDI transmissions. The **F4=Prompt** key is available.

Hold Engineering Changes

This flag indicates if the system will hold a new schedule if the engineering change value of the new schedule is different to the engineering change value on the contract. The default is 0.

0 - do not hold release.

1 - hold release.

Unique Date/Time

This is the unique date / time indicator. The default is 0.

0 - no unique date / time required.

1 - unique date / time required.

Mandatory Reference

Enter 1 if a reference number must be entered against each requirement, otherwise enter 0 which is the default.

Unique Reference

This is the unique reference indicator. The default is 0.

0 - a unique reference is not required.

1 - a unique reference is required.

No EDI DCI=No Requirement

This field is reserved for future use.

Override Auto Update

This field is designed to hold a temporary override to the EDI Update flag. The EDI update, comparison and acceptance sleeper programs will all check this field and if not blank, use it instead of the EDI update indicator on the contract.

0 - No EDI update.

1 - Process into AI files only.

2 - Validate only.

3 - Validate and run comparison.

4 - Validate, run comparison and update current if all is OK.

Text Processing Method

This is the processing indicator which describes how any customer sent schedule text is actioned. The descriptions are held on the Descriptions file type - TXPM. The **F4=Prompt** key is available. The default is zero.

0 - Drop text on consolidation.

1 - Merge text on consolidation.

2 - Earliest text takes precedence.

3 - Latest text takes precedence.



Press **F21=DCI Comparison Rules** to update the DCI Comparison Rules.

Functions:

F8

Saves all changes and returns to the menu, or to the Advanced Shipping Customer Profile on the first pass.

F21

This displays the Customer DCI Comparison Default Rules screen.

Customer Defaults DCI Comparison Rules Screen (F21)



Select **F21=DCI Comparison Rules** from the Customer DCI Defaults Screen to display the Customer Defaults DCI Comparison Rules screen.

You do not have to enter any rules, but any values entered here will be used to default to the customer release comparison rules.

You can add new default rules by entering them at the bottom of the screen, and you can delete any existing rules using option 4 in the Select field. To replace or change a rule, you must first delete, then add the new rule.

```
AC040      Distribution V3 -> V3 Financials      User GJBAPH2      16/02/96
                                           12:42:09

Customer defaults - DCI comparison rules.
Customer ..... NH001      000      Northern Motor Spares Limited

Sel  Comparison Method & Description      Rule  Description      Prim.
-    1 New Rel/Prv rel, latest rev.      002  Releases - Weekly Comp.      1
-    4 New revision / revision 000      003  Rule 3
-    3 New Revision/Previous revision      001  DCIs - Arrears Only

Comparison method.?. _      Rule.....?. ____      Primary indicator... _
4=Delete
F3=Exit  F4=Prompt  F8=Update  F12=Previous

21-24      SF      MW      KS      IM      II      KENB20A      PET007S1
```

Fields:

Comparison Type

Enter a comparison type. The **F4=Prompt** key is available.

- 1 - New Schedule / Previous Schedule, Latest Revision.
- 2 - New Schedule / Previous Schedule, Revision Zero.
- 3 - New Revision / Previous Revision.
- 4 - New Revision / Revision Zero.

Comparison Rule

Enter the comparison rule number. The **F4=Prompt** key is available.

Primary Rule

Enter 1 if a rule is the primary rule to be used in the on-line comparison enquiry.

There can only be one primary rule for comparison methods 1 and 2, and one primary rule for methods 3 and 4. At least one rule must be defined as the primary rule.



Press **F8=Update** to return to the Customer DCI Defaults screen. Then press **Enter** to return to the main menu.

Functions:


F8

Updates the rules and returns to the Customer DCI Defaults screen.

Contracts Maintenance

1...
2... 2/ACM

These values are all defaulted from the customer / delivery point defaults which must exist before a contract can be added (except default comparison rules).



Contract Maintenance Screen

This screen allows you to choose which contract you want to maintain, by entering selection parameters.



Select Contracts Maintenance to display the Contract Maintenance screen.

```
AC020                      Z1 - GB Demonstration Company    User GBJBANB1    28/05/98
                                           16:04:49

Contract Maintenance

Customer .....?. _____  (=Wildcard)
Item .....?. _____      (=Wildcard)
Customer part..... _____ (=Wildcard)
Item model year..... _____
OR
Contract number..... _____

Copy from Contract.?. _____ (Only used with Add)

F3=Exit F4=Prompt F6=Add F10=Additional Search

MA a 05/027
```

Fields: Customer

Enter a customer code or ? to display a Customer Scan Window. An incomplete customer name or number can be entered to search for a contract. This window will only present customers that are registered with the Advanced Customer Scheduling/Advanced Customer Shipping products.

Item

Enter an item code or ? to display an Item Scan Window. An incomplete item name or number can be entered to search for a contract. This window will only present items that are registered with the Advanced Customer Scheduling/Advanced Customer Shipping products.

Customer Part

Enter the customer part number as part of your contract search criteria.

Item Model Year

Enter the item model / year as part of your contract search criteria.

OR

Contract Number

If a contract number is entered, then the program will jump to the next screen without having to press enter.

Enter a blank in this field and press enter to display a Contract Scan Window. Entries made in the Customer, Item, Customer Part and Item Model Year fields can be used to narrow down the list of contracts displayed. This window also allows entry to the Additional Contract Characteristics search window.

In add mode, you can manually add a contract number (which is checked for uniqueness) or the system assigns one using the company parameter.

Copy From Contract

To copy a contract, use the **F6=Add** function key.

Functions:

F6=Add

Displays the Contract Header screen in Add mode which allows you to add a new contract, or copy from an existing one.

F10=Additional Search

Will display the Additional Contract Characteristics Panel.



Select **Enter** or **F6=Add** to display the Contract Header screen.

Contract Header Screen

This screen allows you to create and maintain Contract Header information. When a change is made to an existing contract, before and after images will be written to the contract history file. The date of change will be updated on the contract record.



Select **Enter** or **F6=Add** from the Contract Maintenance screen to display the Contract Header screen.

AC025	Z1 - GB Demonstration Company	User GBJBA1MS	13/10/97
			16:30:15
Contract Header		** Inactive **	
Customer.....	RCMC 001	Contract LOT	
Item.....	C	Costello Motor Supplies North	
Qty unit of measure...	a lot controlled item		
EA Single of----->			
Customer order number...	1	Line no....	
Customer item number....	C	Model/year	
Customer item description			
Despatch Type.....	1	Stock Transfer Consignment	
Customer order date....	1/01/96	Contact.....	Simon Costello
Contract start date....	1/01/96	Contract end date.	31/12/99
Telephone number.....	01942 56820	Fax number.....	01942 667723
Contract quantity.....	9999999.000		
Current engineering level...			
Current design revision no..			
F3=Exit F8=Update F11=Delete F12=Previous F13=Contract Prices			
F14=Activate F15=Defaults F16=Eng Levels F17=Maintain Cums F24=More keys			
8-28 SA MW KS CL IN DM II EDN400A KB PET178S1			

Fields:

Contract

Add Mode:

If a contract number was added manually on the previous screen, it will be displayed and write protected here. Otherwise the next available contract number will be displayed, but the system will not generate a contract number, until you have pressed F8=Update to create the contract. This is designed to avoid gaps in the numbering sequence.

Amend Mode:

The contract number is displayed and write protected.

Customer Order Number

Enter the customers order number. This field is optional.

Line Number

If the customer order number is not blank, you can enter a line number relating to the customer's purchase order number. This field is optional.

Customer Item Number

Enter the customer's item number. This field is optional.

Model Year

Enter a model year code. This field is optional.

Customer Item Description

Enter up to 50 characters of text to describe the item. This is required by some customers for the Advanced Shipping Note (ASN) message. This is an optional field.

Despatch Type

A sales order is created when goods are despatched directly to a customer and when goods are despatched to a consignment stockroom a transfer order is created.

Enter one of the following:

0 = Sales Order. This is the default.

1 = Transfer Order.

Customer Order Date

If the customer order number is not blank, enter the date of the order. This field is optional.

Contact

Enter the customer contact name. This field is optional.

Contract Start / End Dates

Enter the start and end dates of the contract. These fields are mandatory. The default start date is the current system date, and the default end date is 31/12/99.

Telephone / Fax Nos.

Enter telephone / fax numbers for the customer contact. The entries will default from the customer master file. This field is optional.

Contract Quantity

Enter the total expected delivery quantity for the life of the contract. This field is mandatory.

Current Engineering Level

Enter the current engineering level. This is the field which is checked when new releases / DCI's are received if the hold engineering change flag on the contract release / DCI default is a 1.

Current Design Revision

Enter the design revision number. This is optional.



Select **Enter** to validate the screen.

Functions:



Note: In ADD mode only Enter, F3, F8, and F12

are displayed and enabled.

F8

Amend Mode: Saves any changes made and redisplay the Contract Maintenance screen.

Add Mode: Validates the screen, designates a contract number if required, writes the contract record, and Release / DCI records based on the customer defaults. The Contract Header screen is then redisplayed, enabling any further amendments to be made, e.g. activate the contract.

F11

Deletes the contract provided there are no current Schedule records. (If there are active records pending the contract can only be deactivated.)

F13

Contract Prices. Displays the Maintain Contract Prices screen which allows you to set up and maintain agreed prices against a contract. For more information, refer to Maintain Contract Prices Screen.

F14

Deactivate to change the status of the contract to inactive. If inactive this key is used to change the status of the contract to active.

F15

This displays contract and release defaults.

F16

This displays the Engineering Levels screen.

F17

Maintain Despatch Cumulatives will display the Cumulative Maintenance screen.

F21=Text Entry

This displays the Maintain Text window where you enter or select a Usage Code and a Language Code for multi-lingual text entry. When you press **Enter**, the Item Text window is displayed. This is where you can enter text in the selected language to be displayed or printed on external documentation, e.g. despatch notes, according to the usage code selected.



You specify your customer's default language in Customer Details Maintenance in Sales Order Processing. You can override this default language by entering a different language code when **F16=Additional Overrides** function key is available.



Note: Language codes do not need to be selected in order to print text in the native language.

F22

This displays the High Water Cumulative screen.

Contract Header Delete Contract Window (F11)

- ➡ To delete a contract, press **F11=Delete** when you have the relevant contract header displayed on the contract header screen. The system displays the Contract Header Delete Contract window.

```

AC025          Distribution V3 -> V3 Financials    User GBJBAPH2  16/02/96
                                                    12:51:27
Contract Header      ** Inactive **                Contract AR99999
Customer..... NH001    000      Northern Motor Spares Limited
Item..... NHAC1          800 A-POST FNSHR LH (LHD)
Qty unit of measure... EA Single of.....*

Customer order number.... LK-99809/8                Line no....  4
Customer item number   Confirm Delete              1/year.  96
Customer item descri   Press F11 to confirm deletion
                        Press Enter to resume without deletion.
Customer order date.   en
Contract start date.   99
Telephone number....   26-4115
                        F11=Delete Enter=Resume
Contract quantity..... 1000.000

Current engineering level... E96
Current design revision no.. 1

F3=Exit  F8=Update  F11=Delete  F12=Previous  F14=Activate  F15=Defaults
F16=Eng Levels  F17=Maintain Cums  F21=Contract Text  F22=High Water Cums
02-01    SF        MW        KS        IM        II  KENB20A  PET087S1
  
```

- ➡ Press **F11** to delete the contract. The system will delete the contract and return to the invite screen.

Functions:

F11

This deletes the contract provided there are no records associated with the contract.

Contract and Release Defaults Screen (F15)



This screen is accessed by pressing **F15=Defaults** from the Contract Header Maintenance screen, and displays the contract release defaults.

AC030	Z1 - Demonstration Company	User QPGMR	29/01/96
Customer ... F100	001	Ford Cologne	10:36:01
Item 76000211		96FB B29904 AB W/STRIP Q/LIGHT	Contract F000211
Contract Defaults			
DCI/RAN processing 1 (0/1/2) 0=No 1=DCI 2=RAN processing			
Release Defaults			
Call-Off type 1 0=Daily 1=Timed			
Default time :15			
Reconciliation method ...?. 02 last despatch note			
Arrears processing method?. 01 Normal Arrears			
Authorisation method?. 04 Fixed horizon in calendar days			
Automatic update from EDI?. 4 Validate, compare and accept			
Unique date/time 1 (0/1) Hold eng. changes..... 0 (0/1)			
Text processing method...?. 0 Drop text on consolidation			
EDI Link Field 1			
F3=Exit F4=Prompt F12=Previous			
10-30 SF MK KS IM II KENB20A PET007S1			

Fields:

DCI / RAN Processing

Enter the DCI / RAN processing indicator. The default is 0.

0 - Daily Call In's and RANs will not be processed.

1 - Daily Call In's are to be processed.

2 - RAN details are to be processed.

Release Defaults

Call-Off Type

This field is used to determine whether the deliveries are made to a time.

0 - Deliveries are not timed. This is the default.

1 - Deliveries are timed.

Default Time

Enter a default time for timed deliveries. This is the time the goods will normally be delivered. Enter the time in HH:MM format. The default is 00:00.

Reconciliation Method

This indicates the type of data supplied by the customer for reconciling new issues. The default is blank, forcing an entry. The **F4=Prompt** key is available.

'01' - Cumulative quantity.

'02' - Last despatch note.

'03' - Both (cumulative quantity and last despatch).

'04' - Assumed.

'05' - Nissan RAN.

'06' - None.

Arrears Processing Method

This is the method of processing arrears. The default is blank. The **F4=Prompt** key is available.

'01' - normal arrears. The customer either sends a total of arrears or sends dated requirements which are dated before the issue date.

'02' - restated arrears. The customer restates the arrears either as a new requirement or accumulated in with the forward release. The net result is that the arrears are dated on or after the new issue date.

'03' - assumed arrears. The customer does not send arrears information but assumes that the supplier will still send overdue requirements.

Authorisation Method

Enter the method used to determine the authorisation code. The default is blank.

'01' - authorisation code. The customer sends the appropriate code via EDI or else it is manually entered.

'02' - date horizons. The customer sends date horizons which vary from release to release.

'03' - cumulative quantity. The customer sends cumulative quantities which vary from release to release.

'04' - fixed horizons in calendar days. Date horizons are determined using the fixed horizons in days relative to the synchronisation date of the release. The fixed horizons normally remain the same during the life of a contract.

Automatic Update From EDI

This is the automatic update from EDI indicator. The default is blank. Enter one of the following values:

0 - No EDI update.

1 - Process into AI files only.

2 - Validate only.

3 - Validate and run comparison.

4 - Validate, run comparison and update current if all is OK.

Unique Date/Time

This is the unique date / time indicator. The default is 0.

0 - no unique date / time required.

1 - unique date / time required.

Hold Engineering Changes

This flag indicates if the system will hold a new schedule if the engineering change value of the new schedule is different to the engineering change value on the contract. The default is 0.

0 - Do not hold release.

1 - Hold release.

Text Processing Method

This is the processing indicator which describes how any customer sent schedule text is actioned. The descriptions are held on the Descriptions file type - TXPM. The default is zero.

0 - Drop text on consolidation.

1 - Merge text on consolidation.

2 - Earliest text takes precedence.

3 - Latest text takes precedence.

EDI Link Field 1

Enter EDI Link field narrative.



Press **Enter** to validate the screen.

Contract Defaults Release Authorisation Codes Screen



This screen can be reached using **Enter** from the Contract and Release Defaults screen. You may be forced to update this screen if you have made amendments to the Authorisation Method on the Contract & Release Defaults screen, which conflicts with the existing Fixed Horizons data.

```

AC030          Z1 - Demonstration Company      User QPGMR      29/01/96
                                           10:37:26

Contract defaults - Release authorisation codes.

Customer ... F100      001      Ford Cologne      Contract F000211
Item ..... 76800211      96FB B29904 AB W/STRIP Q/LIGHT

Authorisation codes
Descriptions          1          2          3          4          5
                     GAB      MATERIAL  FORECAST
Mandatory reference   0          0          0          -          -
Unique reference      0          0          0          -          -
Fixed horizon days    30        120          -          -          -
Pass to planning appls. 1          0          0          -          -

F3=Exit  F12=Previous  F21=Release Comparison rules

09-27      SA      MK      KS      IM      II  KENB20A  PET087S1
  
```

Fields:

Descriptions

Enter the authorisation descriptions. A description for authorisation period 1 must exist before you can continue.

Mandatory Reference

This flag is used to indicate if a reference must be entered against each requirement.

0 - No reference is required. This is the default.

1 - A reference number is required.

Unique Reference

This is the unique reference indicator.

0 - No unique reference is required. This is the default.

1 - A unique reference indicator is required.

Fixed Horizons In Days

Enter the fixed horizon as a number of calendar days relative to the previous authorisation code. If this is the first authorisation code (1) it will be relative to the customer stated release date as entered by you. This field is only valid if the authorisation method is '04'.

Pass To Planning Applications

Set this indicator to 1 if the schedule requirements for this authorisation period are to be passed as a firm requirement to the MRP / MPS planning system.

Set the indicator to 0 if this feature is not required for an authorisation period.



Note: Fixed horizons in days can only be entered if the authorisation method is '04'.



Warning: If release details exist then only the Authorisation horizons can be changed.

Functions:

F8

This saves any changes made up to this point and returns to the Contract and Release Defaults screen.

F21

Release Comparison Rules



Press **F21=Release Comparison Rules** to display the Release Comparison Rules Screen.

Contract Defaults Release Comparison Rules Screen (F21)



This screen is accessed by taking **F21** from the Contract & Release Defaults screen. You do not have to enter any rules.



You can add new default rules by entering them at the bottom of the screen. Existing rules can be deleted using option 4 in the Select field.

To replace or change a rule, you must delete it then add a new one.

```
AC040          Distribution V3 -> V3 Financials      User GBJBAPH2  16/02/96
                                           13:13:49

Contract defaults - Release comparison rules.
Customer ..... NH001      000      Northern Motor Spares Limited  Contract AR00001
Item ..... NHAC1          000 A-POST FNSHR LH (LHD)

Sel  Comparison Method & Description      Rule  Description      Prim.
 1 New Rel/Prv rel, latest rev.          002  Releases - Weekly Comp.    1
 2 New rel/Prv rel, revision 000          002  Releases - Weekly Comp.
 3 New Revision/Previous revision          002  Releases - Weekly Comp.    1
 4 New revision / revision 000            002  Releases - Weekly Comp.

Comparison method.?. _  Rule.....?. ____  Primary indicator... _
4=Delete
F3=Exit  F4=Prompt  F8=Update  F12=Previous

00-03  SF  MW  KS  IM  II  KENB20A  PET087S1
```

Fields:

Comparison Type

Enter the comparison type.

- 1 - New Release / Previous Release, Latest Revision.
- 2 - New Release / Previous Release, Revision Zero.
- 3 - New Revision / Previous Revision.
- 4 - New Revision / Revision Zero.

Comparison Rule

Enter the comparison rule number.

Primary Indicator

This indicates the use of a primary rule.

Enter 1 if a rule is the primary rule to be used in the on-line comparison enquiry.

There can only be one primary rule for comparison methods 1 and 2, and one primary rule for methods 3 and 4. At least one rule must be defined as the primary.



Note: No rules can be added if release reconciliation method on the contract is a 5 for Nissan RAN's.



Tip: You do not have to enter default rules, but if you do the comparison type, comparison rule, and primary flag must be entered.



Press **F8=Update** to update the files.

Daily Call In Defaults Screen

This screen is used for entering the default values for Daily Call In's. This screen is only available if the contract has the DCI / RAN indicator set to 1 or 2.



Press **Enter** on the Release Authorisation Codes screen to display the Daily Call In Defaults screen.

```

AC035                Z1 - Demonstration Company      User QPGMR      29/01/96
Daily Call In Defaults                                10:38:12
Customer ... F100    001      Ford Cologne          Contract F000211
Item ..... 76800211
DCI/RAN processing ..... 1      (0/1/2) 0=No      1=DCI      2=RAN processing

Call-off Type ..... 1                0=Daily      1=Timed
Default Time ..... 15:00
Reconciliation method ...?. 01        cumulative quantity
Arrears processing method?. 01        Normal Arrears
Automatic update from EDI?.. 4        Validate, compare and accept

Hold eng. changes..... 0 (0/1)
Unique date/time ..... 0 (0/1)
Mandatory reference ..... 0 (0/1)
Unique reference ..... 0 (0/1)
Text processing method...?. 0        Drop text on consolidation
EDI Link Field 1

F3=Exit F4=Prompt F12=Previous F21=DCI Comparison rules

14-30  SE  MK  KS  IM  II  KENB20A  PET087S1
  
```

Fields:

Call Off Type

This field is used to determine whether the deliveries are made to a time.

Enter 1 if deliveries are timed.

Enter 0 if deliveries are not timed. This is the default.

Default Time

The default time is used for indicating what time the goods should be delivered.

Enter the time in HH:MM format. The default is 00:00.

Reconciliation Method

This indicates the type of data supplied by the customer for reconciling new issues. The default is blank, forcing an entry.

'01' - Cumulative quantity.

'02' - Last despatch note.

'03' - Both (cumulative quantity and last despatch).

'04' - Assumed.

'05' - Nissan RAN.

'06' - None.

Arrears Processing Method

This is the method of processing arrears. The default is blank.

'01' - normal arrears. The customer either sends a total of arrears or sends dated requirements which are dated before the issue date.

'02' - restated arrears. The customer restates the arrears either as a new requirement or accumulated in with the forward release. The net result is that the arrears are dated on or after the new issue date.

'03' - assumed arrears. The customer does not send arrears information but assumes that the supplier will still send overdue requirements.

Automatic Update From EDI

This is the automatic update from EDI indicator. The default is blank. The **F4=Prompt** key is available. Enter one of the following values:

0 - No EDI update.

1 - Process into AI files only.

2 - Validate only.

3 - Validate and run comparison.

4 - Validate, run comparison and update current if all is OK.

Hold Engineering Changes

This flag indicates if the system will hold release if the engineering change value of the new schedule is different to the engineering change value on the contract. The default is 0.

0 - Do not hold release.

1 - Hold release.

Unique Date/Time

This is the unique date / time indicator. The default is 0.

0 - No unique date / time required.

1 - Unique date / time required.

Mandatory Reference

Enter 1 if a reference number must be entered against each requirement, otherwise enter 0 which is the default.

Unique Reference

This is the unique reference indicator. The default is 0.

0 - A unique reference is not required.

1 - A unique reference is required.

Text Processing Method

This is the processing indicator which describes how any customer sent schedule text is actioned. The descriptions are held on the Descriptions file type - TXPM. The default is zero.

- 0 - Drop text on consolidation.
- 1 - Merge text on consolidation.
- 2 - Earliest text takes precedence.
- 3 - Latest text takes precedence.

EDI Link Field 1

Enter EDI Link field narrative.

Functions:

F21

This displays the Contract DCI Comparison Default Rules screen.



Press **Enter** to re-display changed descriptions.

Contract Defaults DCI Comparison Rules Screen

This facility is only used to define a DCI Comparison rule for a specific Contract.

You can add new default rules by entering them at the bottom of the screen.
Existing rules can be deleted using option 4 in the Select field.



Note: To replace or change a rule, you must delete it then add a new one.



Select **F21=Release Comparison Rules** from the Contract Defaults Release Authorisation Codes screen to display Contract Defaults Release Comparison Rules screen.

```
AC040          Distribution V3 -> V3 Financials      User GBJBAPH2      16/02/96
                                                    13:16:20

Contract defaults - DCI comparison rules.
Customer ..... NH001      000      Northern Motor Spares Limited      Contract AR000001
Item ..... NHAC1          000 A-POST FNSHR LH (LHD)

Sel  Comparison Method & Description      Rule  Description      Prim.
-    1 New Rel/Prv rel, latest rev.      001  DCIs - Arrears Only      1
-    2 New rel/Prv rel, revision 000      001  DCIs - Arrears Only
-    3 New Revision/Previous revision      001  DCIs - Arrears Only      1
-    4 New revision / revision 000        001  DCIs - Arrears Only

Comparison method.?. _      Rule.....?. ____      Primary indicator... _
4=Delete
F3=Exit  F4=Prompt  F8=Update  F12=Previous

08-03      SF      MW      KS      IM      II  KENB20A  PET087S1
```

Fields:

Comparison Method

Enter the comparison Method.

- 1 - New Schedule / Previous Schedule, Latest Revision.
- 2 - New Schedule / Previous Schedule, Revision Zero.
- 3 - New Revision / Previous Revision.
- 4 - New Revision / Revision Zero.

Rule

Enter the comparison rule number.

Primary Indicator

This indicates the use of a primary rule.

Enter 1 if a rule is the primary rule to be used in the on-line comparison enquiry.

There can only be one primary rule for comparison methods 1 and 2, and one primary rule for methods 3 and 4. At least one rule must be defined as the primary.



Note: No rules can be added if release reconciliation method on the contract is a 5 for Nissan RAN's.



Tip: You do not have to enter default rules, but if you do the comparison type, comparison rule, and primary flag must be entered.



Press **Enter**.

Engineering Levels Screen (F16)



Select **F16=Eng Levels** from the Contract Header screen to display the Engineering Levels screen.

This screen displays the known engineering levels with their expected shipment quantity and valid date range. All fields are optional and are for reference purposes only. The initial display sequence is by ascending start date.

AC050		Z1 - Demonstration Company		User QPGMR		29/01/96 10:39:34	
Engineering Levels							
Customer F100		001		Ford Cologne		Contract F000211	
Item 76000211		96FB B29904 AB W/STRIP Q/LIGHT					
* Engineering Level							
		Quantity		Expected Start End		Tolerance Quantity Days	
- VOLCAL 26/08/95							
Prefix :							
Revision :							
Suffix :							
1=Select							
F3=Exit F6=Add F8=Update F12=Previous F15=Summary/Detail							
09-03 SP MW KS IM II KENB20A PET007S1							

Functions:

F6

This displays the screen in ADD mode.

F15

This is the summary detail toggle, which hides / displays the item prefix, item suffix, and revision levels.

Engineering Levels Add Screen (F6)

All fields are optional and for reference only, with the exception of the engineering level which can be optionally used to validate engineering levels on new releases / DCI's.



Select **F6=Add** from the Engineering Levels screen to display the Engineering Level Add screen.

AC050	Z1 - Demonstration Company	User QPGMR	29/01/96 10:39:58
Engineering Levels - Add			
Customer	F100 001	Ford Cologne	Contract F000211
Item	76000211	96FB B29904 AB W/STRIP Q/LIGHT	
Engineering level.....	█		
Item prefix.....	_____		
Item suffix.....	_____		
Quantity.....	_____		
Quantity tolerance.....	_____		
Start date.....	_____		
End date.....	_____		
Days tolerance.....	_____		
Revision level	_____		
F3=Exit F12=Previous			
09-41	SP	MK	KS IM II KENB20A PET007S1

The quantities / dates / tolerances are intended to give memo information regarding when (give or take tolerance days) the engineering level is expected to be active and what quantity is expected to be called off during that time (give or take the quantity tolerance).

Engineering Level is write protected in Amend Mode. In Add Mode the following function keys are available.

Functions:

F8

This option saves changes to the date and returns to the Engineering Maintenance screen.

F11

This is the delete key, and will display a confirmation window before deleting the record.

Contract Maintenance Change Despatch Cumulative Screen (F17)

This option allows you to maintain the cumulatives on contracts when the automatically generated cumulative is incorrect, or during the set up of an existing active contract.



Select **F17=Maintain Cums** from the Contract Header screen to display the Contract Maintenance Change Despatch Cumulative screen.

AC070	Z1 - Demonstration Company	User QPGMR	29/01/96
			10:40:19
Contract Maintenance - Change Despatch Cumulative			
Customer	F100 001	Ford Cologne	Contract F000211
Item	76000211	96FB B29904 AB W/STRIP Q/LIGHT	
Current contract cumulative : 21395.000			
Change to cum despatch..... █			
Change reference.....			
Date last changed..... 13/12/95			
F3=Exit F8=Update F12=Previous			
10-44	SP	ML	KS IM II KENB20A PET007S1

Fields:

Current Contract Cumulative

This is displayed from the current contract record file.

Change To Cum Despatch

Use this field to display changes to the current cumulative despatches Year To Date on the contract record. Changes can be + or -.



Note: Values are change quantities and NOT absolute values.

Change Reference

This is a reference entered by you.

Date Last Changed

This is the date the cumulative despatches, Year To Date, were last changed manually. This is maintained by the system.

Last Year

Cumulative Despatches Ytd

This is the cumulative despatches YTD from the contract header file.

Date Reset

This is the date the last year cumulative was last set.

Functions:

F8

This saves any changes to date and returns you to the Contract Header Screen



Press **F8=Update to return** to the Contract Header Screen.

Contract Header High Water Cums Window (F22)

This screen shows the highest ever cumulative quantities for a contract as stated by the customer. The display shows the cumulative quantities for each authorisation period together with the internal reference, customer reference, and date of the release in question.

Processing Note For High Water Cumulatives

The processing logic for these EDI update / manual maintenance of releases is that the system will compare the cumulative quantity of the new version of an accepted release for each authorisation period to the cumulative quantity shown on the High Water Cumulative screen.

- If the new cumulative quantity is greater than or equal to the one in the file (which it usually will be), the new release details will overwrite the existing values.
- If the new cumulative quantity is less than the value in the file, the existing values are retained for the relevant authorisation periods.



Select **F22=High Water Cums** from the Contract Header screen to display the High Water Cums window.

```

AC025                Z1 - Demonstration Company      User QPGMR      29/01/96
                                           10:40:29
Contract Header      ** Active **      Contract F000211
Customer..... F100   001      Ford Cologne
Item..... 76000211      96FB B29904 AB W/STRIP Q/LIGHT
Qty unit of measure... EA Single of

Customer order number.... 96FB B29904 AB      Line no....
Customer item number..... 96FB B29904 AB      Model/year. 1996
Customer item description W/STRIP - QUARTER WINDOW FIXED R

High Water Cums
  Period      1      2      3      4      5
  Highest cum 33295 72295 02295
  Internal rel 1      1      1
  Internal rev 0      0      0
  Customer ref 585-10 585-10 585-10
  Release date 11/12/95 11/12/95 11/12/95

F8=Update F12=Previous
F3=Exit F8=Update F11=Delete F12=Previous F14=Deactivate F15=Defaults
F16=Eng Levels F17=Maintain Cums F21=Contract Text F22=High Water Cums
16-18 SA MK KS IM II KENB20A PET007S1
  
```



Note: This screen can only be accessed after the contract release defaults have been set up.

The display is updated automatically via the EDI interface, and / or via manual release entry, but can also be updated via this screen.

Fields:

Period

These authorisation periods will have been set up and defined on the contract. You can only enter data into authorisation periods which have been set up.

Highest Cumulative

Enter the highest cumulative value. This field is mandatory.

Internal Reference

Enter the internal reference. This must be a valid reference if entered.

Customer Reference

Enter the customer reference. This field is mandatory

Release Date

Enter the release date. This field is mandatory.





Press **F8=Update** to save any changes and return to the contract header screen.

Comparison Rules



3/ACM

This option allows you to set up and maintain comparison rules. You can add new rules, or maintain existing rules. A comparison rule is identified by its unique number in all the various comparison processes.



Maintain Comparison Rules Screen 2 (F6)



Enter 1 next to the rule you want to amend, or select **F6=Add** for a new rule from the first Maintain Comparison Rules Selection screen to display the second Maintain Comparison Rules screen.

Rule elements can only be added or deleted, not revised. Entries are displayed in rule type / from days / authorisation period sequence.

Rule Element 1

- From / To days are mandatory and authorisation period must be blank.
- The only permissible negative days range is -999 to -1.
- 'From Days' must be less than 'To Days'.
- Overlapping day ranges are prohibited.
- Rule / element / days range must be unique.

Rule Elements 2, 3, and 4

- Authorisation period is mandatory and is validated against company defaults.
- From / To days must be blank.
- Rule / element / authorisation period must be unique.

Rule Element 5

- From / To days AND authorisation period must be blank.
- Not allowed to enter a percentage.
- No - decrease tolerance values are allowed.
- Rule / element must be unique.



Tip: If you want to make changes to an existing rule, you have to first delete the rule then add it again.

AC060		Z1 - Demonstration Company		User QPGMR		29/01/96 10:52:01	
Maintain Comparison Rules							
Rule 001		Description <u>high Runners, Releases</u>					
Sel	Rule	Days	Days	Auth.	+/-	-----Tolerances----->	
Elem	From	To	Period ?	Quantity	%	Sales	Sever
?	<-Elem 1->	1->	Elem 2/3/4			Value	ity
-	1	999-	1-		+	100	9
-	1		5		-	100	9
-	1		6	20	+	10	8
-	1		20		-	500	8
-	2			1 FIRM	+	20	7
-	2			2 MATERIAL	-	1000	7
-	2				+	1000	7
-	2				-	500	7
-	2				+	2000	6
-	2				-	2000	6 +
-					+		-
-					-		-
4=Delete							
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous							
20-07 SF ML KS IM II KENB20A PET087S1							

Fields:

Rule Number

This field is input capable in Add mode only. Enter a rule number, which must be unique.

Rule Description

This field describes the rule and is maintainable at all times.

Select

You can enter 4 here to delete an individual element, with a confirmation message.

Rule Elements

Enter the rule element:

- 1 - Quantity within period.
- 2 - Cumulative at authority period end (new date only *).
- 3 - Cumulative at authority period end (new / current date **).
- 4 - Cumulative at high water mark.
- 5 - Cumulative mismatch (Despatches - Receipts).



*Note: * 'New Date Only' implies compare cumulative requirements on new release as at period end on the new release to cumulative on current release as at new release period end.*



*Note: ** 'New / Current Date' implies compare cumulative requirements on new release as at new period end with cumulative requirements on current release as at current period end.*

Days From

Enter the number of days relative to the customer issue date to define the start date of the period.

Days To

Enter the number of days relative to the customer issue date to define the end date of the period.

Authorisation Period

Enter the Authorisation Period to be used by rule elements 2, 3, and 4.

Period Description

For elements 2, 3, and 4 the period description from the company profile is displayed but is not maintainable.

+ / -

+ - Line specifies increase tolerances.

- - Line specifies decrease tolerances.

Quantity Tolerance

Enter the quantity change tolerance.

Quantity % Tolerance

Enter the quantity % change tolerance.

Sales Value Tolerance

Enter the sales value change tolerance.

Margin Tolerance

Enter the margin change tolerance.

Severity Code

Enter a severity code from 0 to 9. Exceptions with a severity code greater than or equal to 4 will hold new Schedules and prevent them from being automatically accepted into 'current'.

Functions:

F8

This validates and saves any changes made and returns you to the selection screen.

F11

This is the delete key which will delete a comparison rule and all associated element records. It will display a confirmation message first. You can only delete rules which are not attached to company / customer / contract release or DCI defaults.



Note: Each rule must have at least one rule element.



Note: Each element must have at least one of the tolerance parameters (quantity / percentage / sales value / margin) entered for a least one of +

increase / - decrease comparisons.



Tip: If any tolerance values are entered, the severity code for that element increase / decrease comparison must also be entered.



Press **F8=Update**.

Contract Pricing



4/ACM

This facility allows prices to be maintained against each contract. No schedule will be accepted into 'current' if there is no valid contract price established.

The price / discount structure within the Sales Order Processing application is not used for Advanced Customer Scheduling. Instead a contract price structure is used. This enables prices to be established for each schedule with effective date control which may be used for retrospective invoicing.

Prices can have two dates attached - the change from date which is used to price the orders, and the effective date that is used for retrospective invoicing.

If price at despatch is in operation for Advanced Customer Scheduling, then the price at despatch routine within Sales Order Processing will be used at invoice time; this will mean that contract prices will not be effective.


Price at despatch for Advanced Customer Scheduling is defined at company level via an Inventory descriptions file entry defined as follows:

Major Type 'MISC'

Minor Type 'PRCD'

Description 1 - Schedule priced at despatch.

A 1 in the first character of the description signifies price at despatch as being effective at company level for all scheduled orders.



Enter a blank in this field and press enter to display a Contract Scan Window. Entries made in the Customer, Item, Customer Part and Item Model Year fields can be used to narrow down the list of contracts displayed. This window also allows entry to the Additional Contract Characteristics search window.

In add mode, you can manually add a contract number (which is checked for uniqueness) or the system assigns one using the company parameter.

Copy From Contract

To copy a contract, use the **F6=Add** function key.

Functions:

F6=Add



Displays the Contract Header screen in Add mode which allows you to add a new contract, or copy from an existing one.

F10=Additional Search


Will display the Additional Contract Characteristics Panel.



Select **Enter** or **F6=Add** to display the Contract Header screen.



Price



Enter the date from which this price is effective.

Enter the date from which the price is to be charged.

F8

This updates the screen.

F10

Next Price. Allows you to add further prices when the maximum of eight has already been entered. The new price will automatically be entered as the last price on the list. The existing prices will move up the list by one position and the first price, which is the oldest, is removed.



Press **F8=Update** to update the screen.