

-
-
-
-
-

Chapter 1

Maintenance



Setting up DRP

As this is an advanced application module, you set up most of the primary data through the base modules. However, you must still define additional reference data specific to DRP. This data includes:

- Company level DRP defaults.
- Calendar and planning period information applicable to distribution centres.
- Details of the distribution networks, centres and associated stockrooms.
- Planning information at Distribution Centre (DC) and item level.
- Supplier schedule report profiles.

Calendar Maintenance

1... **2...** 1/DRM

The Distribution Requirements Planning application allows for each centre or DC to have a separate calendar. You use this option to maintain the calendars for all sites within the company.

You can then assign the calendar codes defined here to each site via the Periods Maintenance option.



Note: Before generating a new calendar year, review the calendar details on the Company Profile, to make sure that they are accurate for this particular year.

Calendar Maintenance Selection Screen



To display the Calendar Maintenance Selection Screen, select Calendars.

You use this screen to select a calendar to maintain or enter a new calendar.

DR017	Z1 - Demonstration Company	USER SP1	22/09/94 11:54:56
-------	----------------------------	----------	----------------------

Calendar Maintenance

Se1	Code	Year	Days	Working Days	Year Start
1	C1	94	364	257	3/01/94
-	C1	95	364	260	2/01/95

1=Select 4=Delete 6=Print

Enter Calendar code: __ and Year: __ Based on Calendar __

F3=Exit

Fields:

Se1

Enter one of the following:

- 1 - To maintain the calendar.
- 4 - To delete the calendar.
- 6 - To print the details of the calendar.

Enter Calendar Code

To maintain a calendar, enter the calendar code.

To add a calendar, enter a new code.

Year

Enter the calendar year (YY).

Based On Calendar

Enter the code of an existing calendar to base the new calendar on it.



Press **Enter** to display the Calendar Maintenance Holidays Screen.

Calendar Maintenance Holidays Screen

 To display this screen, on the Calendar Maintenance Selection Screen, either enter a new calendar, or select a calendar, then press **Enter**.

You use this screen to maintain the start date and all holidays for this calendar.

DR017

Z1 - Demonstration Company

USER SP1

22/09/94
11:55:30

Calendar Maintenance

Calendar Code C1

Year 95

Start Date 20195

Standard Week: M T W T F S S
N N

Holidays

From	To
010195	040195
290395	010495
060595	060695
270595	270595
260895	260895
251295	270895
_____	_____
_____	_____
_____	_____
_____	_____
_____	_____
_____	_____

F3=Exit

F8=Update

F12=Previous

F13=Maintain Week Templates

Fields:

Start Date

Enter the date of the first Monday of the year.

Holidays From

Enter the start date for the holiday in the format DDMMYY.

To

Enter the end date for the holiday.

 *Note: Holidays must not overlap.*

Functions:

F13

Maintain Week Templates. Use this function to display the Week Templates Screen.

 Select **F8=Update** to update the calendar holiday records. DRP audits all updates.



Note: Effectivity dates must not overlap.



Select **F8=Update Week Templates** to update the calendar template records. DRP audits all updates.

Period Maintenance



2/DRM


You use this procedure to define the time slots (periods), for which you want to assess the supply and demand. You set up time slots for each centre or DC and you can amend them before any processing run. You define the periods in terms of calendar days and associate them with a particular Calendar Code.

This is the first stage in defining a new centre or DC. Conversely, it is the last stage in deleting one.

Maintain Periods Selection Screen

 To display the Maintain Periods Selection Screen, select Periods.

You use this screen to select the centre or DC. This also gives details of the last processing run for each centre or DC.



The screenshot shows a terminal window with the following text:

```
DR031          Z1 - UK Demonstration Company      USER GBJBANB4      6/02/98
Maintain Periods                                     13:19:51

Enter Centre/DC.....?... _

F3=Exit  F4=Prompt
```

Fields:

Centre/DC

Enter the code of the centre or DC you wish to create or amend.

 Enter the centre or DC code to display the Maintain Periods Details Screen.

Maintain Periods Details Screen



To display this screen, on the Maintain Periods Selection Screen, enter the centre or DC code.

You use this screen to associate a calendar with the centre or DC, and to enter a definition of the periods to be analysed by DRP for this site.

DR031		Z1 - UK Demonstration Company				USER GBJBANB4		6/02/98		13:20:56	
Maintain Periods (in Calendar days)						Centre/DC..... D1					
						Calendar Code...?.. 01					
1	2	3	4	5	6	7	8	9	10	11	12
28	28	28	28	28	28	28	28	28	28	28	28
13	14	15	16	17	18	19	20	21	22	23	24
28	28	28	28	28	28	28	28	28	28	28	28
25	26	27	28	29	30	31	32	33	34	35	36
—	—	—	—	—	—	—	—	—	—	—	—
37	38	39	40	41	42	43	44	45	46		
—	—	—	—	—	—	—	—	—	—		

F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous

Fields:

Calendar Code

Enter a calendar code.

1 - 46

Enter up to 46 periods, each defined in calendar days. These must be contiguous.



Select **F8=Update** to update the period details. DRP audits all updates. The Maintain Periods Selection Screen redisplay.



Select **F3=Exit**.

Stockroom Maintenance

1... **2...** **3/DRM**

You use this procedure to define stockrooms to centres or DCs. If a centre or DC only includes a single stockroom, you can use the same code for the centre or DC as for the stockroom.

You must have defined the stockrooms to Inventory Management.

Maintain DRP Stockrooms Selection Screen



To display the Maintain DRP Stockrooms Selection Screen, select Stockrooms.

You use this screen to select the Centre/DC and/or stockroom you want to maintain.

```
DR015                Z1 - UK Demonstration Company    USER GBJBANB4    6/02/98
                                     13:21:09
Maintain DRP Stockrooms.
Centre/DC...?... █    Include all Stockrooms 0 (0=No 1=Yes)

F3=Exit  F4=Prompt
```

Fields:

Centre/DC

Enter any centre or DC code with defined periods.

Include All Stockrooms

Enter one of the following:

0 - Not to include all inventory stockrooms.

1 - To add all inventory stockrooms to a centre or DC.



Press **Enter** to display the Maintain DRP Stockroom Details Screen.



*Note: If the stockroom you select does not exist, select **F8=Create** to create the stockroom.*

Maintain DRP Stockrooms Details Screen

- To display this screen, on the Maintain DRP Stockrooms Selection Screen, enter a Centre or DC code, then press **Enter**.

You use this screen to select the stockrooms to define to the Centre or DC.

DR015 Z1 - UK Demonstration Company USER GBJBANB4 6/02/98
13:21:24
Maintain DRP Stockrooms.
Centre/DC...?... D1 Include all Stockrooms 0 (0=No 1=Yes)
..... Stockrooms to be included

02	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—

F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous

Fields:

Stockrooms

This displays all valid stockroom codes. If you need to confirm orders as despatched from this stockroom, then you must define it as a depot within Sales Order Processing.

-  *Note: Select delete to remove the centre/DC and all its associated stockrooms.*
-  Select **F8=Update** to update the displayed stockrooms. Then select **F3=Exit**.

Customer Maintenance



4/DRM

You process distribution orders, created through DRP, through the Sales Order Processing application in a similar way to normal sales orders.

Therefore you must set up an internal customer account, in sales order processing, for each stockroom that is to supply DCs in the DRP network. The internal customer must have a delivery address sequence number of 001. Use this option to define the customer code to the appropriate stockroom.

DRP Stockroom / Customer Maintenance Selection Screen



To display the DRP Stockroom/customer Maintenance Selection Screen, select Customers.

You use this screen to select the DRP Stockroom / Customer you want to maintain.

DR340	Z1 - Demonstration Company	User SP1	22/09/94 12:08:52
-------	----------------------------	----------	----------------------

DRP Stockroom/Customer Maintenance		
SR	Description	Customer
- F1	Paris Central Stockroom	
- WH	Central Warehouse	
I 01	Central Stockroom	C1
- 02	Northern RDC Stockroom	D1
- 03	Southern RDC Stockroom	D2

1=Select
F3=Exit

Fields:

Select

Enter 1 alongside the stockroom you want to maintain.



Press **Enter** to display the Details Screen.

DRP Stockroom / Customer Maintenance Details Screen



To display this screen, on the **DRP Stockroom/ Customer Maintenance Selection Screen**, enter 1 alongside a stockroom and press **Enter**.

You use this screen to enter the dummy Internal Customer Code, which holds distribution orders for receipt at the stockroom.

DR340	Z1 - Demonstration Company	User SP1	22/09/94 12:09:18
DRP Stockroom/Customer Maintenance			
Stockroom.....	01	Central Stockroom	
Internal Customer.....?	<u>C1</u>	Internal Customer (Supply	
F3=Exit F4=Prompt F12=Previous			

Fields:

Internal Customer

Enter the customer code to use when you enter a distribution order with a destination of this stockroom.



Note: The internal customer must be a sales order processing customer with a delivery sequence of 001.



Press **Enter** to save the details.

Network Maintenance

1... **2...** 5/DRM


You use this procedure to define DRP networks. A DRP network consists of one centre and any number of Distribution Centres (DCs) supplied by that centre. You can define a centre or DC to more than one network.

You can define a hierarchy of networks, where a centre in one network is a DC in a higher network.

Maintain DRP Networks Selection Screen

 To display the Maintain DRP Networks Selection Screen, select Networks.

You use this screen to select the Network code to maintain.



DR016 Z1 - Demonstration Company USER SP1 22/09/94
12:13:42

Maintain DRP Networks

Enter Network Code...?.. ?

Select DRP Networks

1 M1 UK Supply Network

1=Select Position to:

F12=Previous

F3=Exit F4=Prompt

Fields:

Network Code

Enter an existing code to maintain a network or a new code to add a network.

 Press **Enter** to display the Maintain DRP Networks Screen.

Maintain DRP Networks Centre Detail Screen



To display this screen, on the Maintain DRP Networks Selection Screen, enter a network code and press **Enter**.

You use this screen to maintain the centre code and descriptions.

DR016 Z1 - UK Demonstration Company USER GBJBANB4 6/02/98
13:21:57

Maintain DRP Networks

Network Code..... N1 Description Northern Network

Centre for Network..?.. Q1 Description Birmingham supply center

F3=Exit F4=Prompt F12=Previous

Fields:

Network Description

Enter a description of the network.

Centre For Network

Enter a centre code.

Centre Description

Enter a description of the supply centre.



Press **Enter** to update the DRP Network file with the centre code and descriptions. DRP audits updates to the Network file.

Maintain DRP Networks DC's Detail Screen

 To display this screen, on the Maintain DRP Networks Centre Detail Screen, press **Enter**.

You use this screen to maintain the DC details for the selected network.

DR016	Z1 - UK Demonstration Company	USER GBJBANB4	6/02/98
Maintain DRP Networks			13:22:11
Network Code..... N1		Northern Network	
Centre for Network.. C1		Birmingham supply center	
Line	DC	DCs Supplied By Centre	
1	D1	Description	
		DC 1	
Line: DC.?...: Desc.:			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			

Fields:

Line

Enter a line number corresponding to the DC you want to amend.

DC

Enter a DC or centre.

Description

Enter a description for the DC.

 Select **F8=Update** to update.

Select delete, with a line retrieved at the bottom of the screen, to delete the corresponding DC.

If you select delete, with no line retrieved, you delete the details for the whole Network. Confirm the deletion by selecting **F11=Delete** a second time.

DRP adds all updates to the audit files.

 Select **F3=Exit**.

Distribution Item Master Maintenance

1... **2...** 6/DRM

You use this procedure to maintain additional distribution details, in order to include an Inventory Item within DRP.

You must maintain this information for each site, this means the centre or DC handling the item. The site can be a distribution or retail outlet for the item.



Note: If you manufacture the item, only define it to DRP at its retail DCs. Define the manufacturing centre, and its items in the Production applications. The MPS/MRP applications then treat the centre as a Model.

Distribution Item Master Maintenance Screen



To display this screen, select Distribution Item Master.

You use this screen to enter the item you want to maintain.



Tip: To get the standard Inventory item prompt, select **F16=Inventory Search Item**.

```
DR007          Z1 - UK Demonstration Company   User GBJBANB4   6/02/98
13:22:32

Distribution Item Master Maintenance

  Centre/DC....?.. █
  Item.....?.. _____

F3=Exit  F4=Prompt  F16=Inventory item search
```

Fields:

Centre/DC

Enter a centre or DC with periods and stockrooms defined.

Item

Enter an Inventory Item Code.

Functions:

F16

Inventory Item Search. Use this function to select the standard Inventory item search facility, for all Items within the company.



Press **Enter** to display the Distribution Item Master File Maintenance Screen.

Distribution Item Master File Maintenance Screen



To display this screen, on the Distribution Item Master Maintenance Screen, enter an Item code and Centre / DC. Then press **Enter**.

You use this screen to maintain the replenishment parameters for the selected item.

```

DR007          Z1 - UK Demonstration Company      USER GBJBANB4      6/02/98
Distribution Item Master File Maintenance          13:22:46

Item..... 5001          Suncream Factor 4 225ml
Centre/DC..... D1          sdf
                        Date Last Planned.... 11/12/97
Source of Supply... 1 (1=Local, 2=Central)
Planner.....?.. JFB
DRP Forecast..... 3 (0=None, 1=Sales, 2=Stock, 3=Both)
Forecast Error Tolerance% Absolute.. .00
Forecast Profile.?.. 01 Period profile
Order Policy..... H (A,B,D,G,H) Min Order Qty..... 60.000
                                OR
Max Order Qty.....          Use Inventory Order Qty... _
Fixed Order Qty....          (1=Economic Order Qty., 2=Reorder Qty.)
Mult Order Qty..... 20.000
Safety Stock.....          Stockroom Details
Days supply..... 0 Local Stockroom.....?.. 02
Time fence days.... 14
Safety stock weeks.. 2
Safety stock days.. 3

F3=Exit F4=Prompt F11=Delete F12=Previous
WARNING - Forecast Profile not set up for current year.
  
```

Fields:

Source Of Supply

Enter one of the following:

- 1 - If you purchase the Item locally.
- 2 - If you centrally supply the item, or purchase, or manufacture, it at a centre defined to DRP or production.

Planner

Enter the person responsible for this Item.

DRP Forecast

Enter one of the following:

- 1 - To use sales forecasts for this Item.
- 2 - To use stock level forecasts for this Item.
- 3 - To use both sales forecasts and stock levels for this Item.
- 0 - To use neither forecast. In this case, DRP only considers the actual orders.

Forecast Error Tolerance % Absolute

Enter the percentage difference between sales forecast quantities, and actual sales quantities, before DRP writes a Net Change trigger for the item concerned. If you do not enter a value, this defaults to the value set up for the company.

Forecast Profile

Enter the default Seasonal Profile used as a template to break down sales forecasts, and maintain stock levels, at period, weekly and daily level. You can override this during forecast processing.

Order Policy

Enter one of the following order policy codes:

Code	Description	Mandatory Quantities
A	Discrete. DRP suggests an order for the actual quantity required.	None.
B	Discrete above minimum. DRP suggests an order for the actual quantity required if greater than minimum. Otherwise use minimum quantity.	Minimum order quantity.
D	Fixed quantity. DRP suggests multiple orders of the fixed quantity to satisfy the required quantity.	Fixed order quantity.
G	Number of days supply. Accumulates the requirements over the specified days and suggests an order quantity to satisfy this demand.	Number of days supply.
H	Fixed quantity above minimum. Suggested order quantity must be greater than minimum and divisible by the multiple quantity.	Minimum order quantity. Multiple order quantity.

Min Order Qty

Enter the minimum quantity that DRP suggests for replenishment of this Item. If the re-order quantity calculated by DRP is less than this minimum DRP uses the latter. Applies only to order policies B and H.

OR

Use Inventory Order Quantity

Enter one of the following:

- 1 - To use the economic order quantity as the DRP minimum order quantity.
- 2 - To use the Inventory re-order quantity as the DRP minimum.

Leave blank - To use neither.



Note: You can enter either Min Order Qty or Use Inventory Order Qty. You must specify a Min Order Qty for order policies B and H.

Max Order Qty

Enter the maximum quantity that DRP suggests for replenishment of this Item. If DRP calculates the re-order quantity as greater than this maximum, the DRP Planner Action Report highlights it.

If specified, DRP uses this maximum order quantity regardless of the order policy specified for the Item.

Fixed Order Qty

Enter the re-order quantity DRP should suggest for this item.

If the required quantity is greater than the fixed order quantity then DRP suggests multiples of the fixed order quantity to satisfy the demand.



Note: If you have specified order policy D, you must enter a fixed order quantity greater than zero.

Mult Order Qty

Enter a quantity. DRP suggests multiples of this quantity for the re-order quantity.



Note: If you have specified order policy H, you must enter a multiple order quantity greater than zero.

Safety Stock

If you do not need to calculate the safety stock during DRP processing, enter the fixed quantity of safety stock.

Days Supply

Enter the number of days DRP sums the requirements for, and raises a single order to meet them.



Note: If you have specified order policy G, you must enter a number of days.

Time Fence Days

Enter the number of days forward, from the current date of a DRP Processing Run, during which DRP schedules no new supply suggestions for forecasted demand, only for actual demand.

You can override this, when you submit a DRP run, with a blanket time fence that applies to all items in the run.

Leave this field blank, to calculate the item level time fences:

- For centrally supplied items from the item/stockroom lead time.
- For locally purchased items from the lead time for the item/preferred supplier.

Safety Stocks Weeks & Days

Enter the required safety stock cover, expressed in weeks and days. This defaults from company profile but you can vary it at item / DC level. DRP calculates safety stock from the forecast demand for the item. You must enter sales forecasts for items if you want to create safety stocks. You can override this when you submit a DRP run by a blanket value that applies to all items for that run.

Local Stockroom

Enter a stockroom code. You must have defined the stockroom to the item in Inventory, and to the centre/DC in DRP. DRP updates on-order and in-transit quantities against this stockroom for the item. This is the primary stockroom for the item at this centre or DC.

Centre

This only displays if the source of supply is 2 (Central). Enter a centre code defined as a centre within at least one network (refer to Network Maintenance). Use this to include or exclude Items when processing a particular centre.

Central Stockroom

This only displays if the source of supply is 2 (Central). Enter a stockroom code defined to the Item within Inventory, and to the centre within DRP.

You create Distribution Order lines for this item against this stockroom.



Press **Enter** to update. DRP records all updates in the DRP Item master audit file.



Select **F3=Exit**.

Planner Maintenance

1... 7/DRM **2...**

You use this procedure to maintain details of all planners, at each centre or DC. Then assign this planner code to all items the planner is responsible for (via Distribution Item Master Maintenance).

DRP Planners Selection Screen



To display the DRP Planners Selection Screen,
select Planners.

You use this screen to select the Centre/DC and the planner code you want to maintain.

```
DR043          Z1 - UK Demonstration Company    USER GBJBANB4    6/02/98
                                           13:23:14

DRP Planners - Selection

Centre/DC.....?.. █
Planner Code....?.. █

F3=Exit  F4=Prompt
```

Fields:

Centre/DC

Enter any centre or DC code which has periods defined.

Planner Code

Enter a planner to maintain , or enter a new planner code.



Note: If you specify a centre or DC, this restricts the list of planners to this centre/DC. If not, all planners for the company display.



Press **Enter** to display the DRP Planners Details screen.

DRP Planners Details Screen



To display this screen, on the DRP Planners Selection Screen, enter a planner code and press **Enter**.

You use this screen to update information relating to the planner and specify the purchase officer number. Purchase Management uses the purchase officer number, when you create purchase orders from DRP suggestions (for items controlled by the planner).

DR043	Z1 - UK Demonstration Company	USER GBJBANB4	6/02/98 13:24:24
DRP Planners - Details			
Centre/DC..... D1			
Planner..... JFB			
Name..... John F. Barlow			
Department..... Planning			
Telephone..... 1345			
Purchase Officer No...?... 00001 John F. Barlow			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			

Fields:

Name

Enter the name of the planner.

Department

Enter the planner's department.

Telephone

Enter the planner's telephone or extension number.

Purchase Officer No

Enter the Purchase Officer number as defined in the Purchase Management application.



Select **F8=Update** to update the details displayed in the DRP Planners file.

Net Change Reason Codes Maintenance



8/DRM

You use this procedure to maintain up to twenty Reason Codes for DRP Net Change processing. Each Reason Code corresponds to a type of transaction which may affect the supply, demand, stock or replenishment parameters of items within DRP. Transactions that affect DRP items set Net Change triggers in DRP, grouped by Reason Code. This allows a flexible approach to DRP planning runs, whereby a subset of DRP items can be re-planned based on an analysis of triggers, set for particular Reason Codes.

Net Change Reason Codes Maintenance Screen



Select Net Change Reason Codes.

You use this screen to enter conditions that trigger net change DRP processing.

DR060	Z1 - Demonstration Company	USER SP1	22/09/94 12:22:35
Net Change Reason Codes Maintenance.			
Code	Description	Active (1=Yes, 0=No)	
01	Forecast vs Actual Comparison.	1	
02	Forecast Generation.	1	
03	Forecast Maintenance.	1	
04	Distribution Item Master.	1	
05	Unplanned Inventory Transactions.	1	
06	Requisition Maintenance.	1	
07	Unplanned Issue or Receipt.	1	
08	Purchase Order Maintenance.	1	
09	Distribution Order Maintenance.	1	
10		0	+
F3=Exit F5=Refresh F8=Update			

Fields:

Code

This displays the net change reason codes. There are nine reason codes currently set up. There are eleven more reason codes reserved for possible future development of the product.

Description

Enter the reason code description. Each Reason describes a type of transaction which potentially affects the planning of DRP items.

Active

Enter one of the following:

0 - To de-activate the Reason Code.

1 - To activate the Reason Code



Note: DRP only processes Net Change Triggers for activated Reason Codes.



Select **F8=Update** to update the details displayed.

Supplier Schedule Profile Maintenance



9/DRM

You use this function to define different report formats for the Supplier Schedules at individual Supplier or Supplier/minor item Group levels. These reports are of particular use to companies who want to forward schedule their suppliers with details of future commitments. The suppliers use these reports to buy in material, manufacture and plan to meet these schedules.

Supplier Schedule Period Maintenance Selection Screen



Select Supplier Schedule Profile.

You use this screen to specify the supplier and, if required, Minor Item group for which you want to maintain schedule formats.

DR400	Z1 - Demonstration Company	USER SP1	22/09/94 12:26:09
Supplier Schedule Period Maintenance			
Enter a Supplier and optionally a Minor Item Group			
Supplier.....?.. <u>FS04</u>			
Minor Item Group...?.. <u>3</u>			
F3=Exit F4=Prompt			

Fields:



Note: To maintain schedule formats at supplier level, enter a Purchase Management supplier. To maintain Schedule formats at Supplier and Item Group Level, enter a Supplier and a Minor Item Group.

Supplier

Enter a supplier defined within Purchase Management.

Minor Item Group

Enter a Minor Item Group defined in the Inventory Descriptions File.



To display the Supplier Schedule Period Maintenance Detail Screen, enter a Supplier, and if required, Minor Item Group, and then press **Enter**.

Supplier Schedule Period Maintenance Detail Screen



To display this screen, on the Supplier Schedule Period Maintenance Selection Screen, enter a Supplier, and if required, Minor Item Group, and then press **Enter**.

You use this screen to define the Supplier Schedule Report Column headings, Reporting intervals and Inclusion/exclusion rules.

DR400	Z1 - Demonstration Company	USER SP1	22/09/94 12:26:10
Supplier Schedule Period Maintenance			
Supplier.....	FS04	Thierry Industrie SARL	
Minor Item Group.....	3	Sun Protection	
Time Period	Weekly Report (Max. 16 Weeks)	Monthly Report (Max. 15 Periods)	Supply Records (1=Include, 0=Exclude)
			PO RQ SG
<u>FIXED</u>	—		1 1 1
<u>FIRM</u>	—		1 1 1
<u>PROBABLE</u>		—	1 1 1
<u>TENTATIVE</u>		—	1 1 1
F3=Exit F8=Update F12=Previous			

Fields:

Time Period

The weekly and period reports are each split into two sections, representing short term and long term scheduling. You define each section to consist of a number of weeks and periods. You can change the default column headings for each section.

Weekly Report

Specify how many weeks, from the start date of the report, to include in the short and long term sections of the weekly report. Maximum of 16 weeks total.

Period Report

Specify how many periods from the start of the report to be included in the short and long term sections of the period report. Maximum of 15 periods total.

Supply Records:

PO

Enter one of the following to specify whether to include Purchase Orders in the short term section of the Weekly Report:

- 1 - To include.
- 2 - To exclude.

RQ

Enter one of the following to specify whether to include Requisitions created from DRP Supply suggestions in the short term section of the Weekly Report:

- 1 - To include.
- 2 - To exclude.

SG

Enter one of the following to specify whether to include suggested Purchase Orders in the short term selection of the weekly report.

- 1 - To include.
- 2 - To exclude.



Note: This does not include changes to suggested quantity or dates.



Select **F8=Update** to save the record.



Select **F3=Exit**.