

-
-
-
-
-


Chapter 3

Processing



The DRP Cycle

The following diagram represents the DRP Cycle:



Review DC Forecasts

Review and update the stock and sales forecasts for each item at the DC.

Evaluate DC Demand

Assess the supply and demand figures for all DCs in a specified Network. Suggest new supply orders, from the centre or from external suppliers, and amend existing supply orders. Delete all previous suggestions. You initiate this DC Run via DRP Processing.

Confirm Suggestions

Once you have reviewed and accepted the DC Run, convert the suggestions to Requisitions using the Requisitioning application. You can amend the requisitions before creating the actual Purchase or Distribution Orders.



Note: DRP deletes all outstanding requisitions for the stockrooms, and adds new ones from the latest DRP suggested orders.

Create Local Purchase Order

Use Requisitioning to convert the purchase requisitions, created from DRP, into Purchase Orders on the external suppliers. DRP transfers purchase orders into Purchase Management.

Create Distribution Orders

Use Requisitioning to convert the distribution requisitions, for supply from a centre, into Distribution Orders. DRP transfers Distribution Orders into Sales Order Processing and places the order lines against the centre stockroom defined to the item in DRP.

You can enter distribution orders directly into Sales Order Processing, using the Distribution Order Entry or Amend options. Specify the From and To stockrooms to automatically create a link between the two stockrooms. DRP creates an internal sales order against the customer defined for the stockroom.

Note the following:

- DRP treats the distribution order as an internal sales order, and raises no invoice details. The customer is the one defined to the stockroom that receives the supply.
- On confirmation of despatch, DRP adds the distribution order lines to the DRP shipments in-transit file. If you have World Trade attached, and the transfer is across an EC Border, DRP writes a movement record for processing within the World Trade application. DRP uses this to produce Intrastat and ESL reports, and to post the acquisition VAT due on receipt of the goods.
- When the stockroom receives the distribution order lines at the stockroom, use the DRP processing options to confirm the goods as received.

Run Central Supply Plan

Assess the supply and demand figures for the supply centre. Suggest new purchase orders from external suppliers and recommend amendments to existing purchase orders.



Note: If the centre is a Manufacturing site, you must define the Items at the centre to Manufacturing not DRP, and the centre run should be an MPS run not a DRP run.

Create Purchase / Production Orders

If the centre run was within DRP, create the requisitions from DRP suggestions and then convert them to purchase orders, using Purchase Management.

If the centre run was within production, create the requisitions then convert them into purchase orders, using Requisitioning.

You can create manufacturing orders from MPS suggestions within the Master Production Scheduling application. Refer to Requisitioning and/or Manufacturing Product Information for further details.

DRP Cycle Summary

This description represents a one-level DRP cycle run. You can repeat or partially repeat this cycle for each network.



Note: You can define a supply centre in one network as a DC in another network.

You can automate the Evaluate DC Demand, Confirm Suggestions, Create Local Purchase Order, Create Distribution Orders and Run Central Supply Plan steps in a single Network Run.

Evaluate DC Demand



1/DRP

You use this procedure to assess the supply and demand status for items handled at DCs within the selected network.

DRP produces a separate schedule for each DC, with supply and demand quantities, and suggested actions, for each Item.

Evaluate DC Demand Screen



To display this screen, select Evaluate DC Demand.

You use this screen to select the network for which you want to evaluate DC demand.

DR025	Z1 - Demonstration Company	USER SP1	23/09/94 11:25:32
Evaluate DC Demand			
Enter Network Code...?.. ?			
F3=Exit F4=Prompt			

Fields:

Network Code

Enter a network code as defined to DRP via Network Maintenance.



Press **Enter** to display the DC Run Selection Screen.

DC Run Selection Screen



On the Evaluate DC Demand Screen, enter a Network Code and press **Enter**.

You use this screen to select criteria and submit a DRP processing run.

DR002	Z1 - Demonstration Company	USER SP1	23/09/94 11:26:22
-------	----------------------------	----------	----------------------

DRP DC Run Selection

Network..... N1 UK Supply Network

DRP run type..... 1 1=Full regeneration
2=Net change
3=Selective

Enter: Current date..... 230994
Overdue days..... 7
Time fence days..... 1 Item Dependent
Calculate safety stock.... 1 (0=No, 1=Yes)
Safety stock cover weeks.. 0 Item Dependent
Days... 0
End date..... 311294
Include forecasts..... 1 (1=Sales, 2=Stock building, 3=Both,
0=Neither, Blank=As per item)

F3=Exit F5=Refresh F8=Submit F12=Previous F14=Review specification
F16=Restrict extractions F19=Print last run details

Fields:

DRP Run Type

Enter the type of DRP run:

1 - Full Regeneration. Re-plan all items.

2 - Net Change. Re-plan a subset of items on the basis of changes in the supply, demand, stock or replenishment parameters of items. Select **F14=Review Specification** to select some or all of these.

3 - Selective. Re-plan a subset of items on the basis of a selection of ranges of Items, DRP Planners, Minor Item Groups, Cost/Usage Elements and/or Preferred Suppliers. Select **F14=Review Specification** to enter the ranges.

Enter:

Current Date

Enter the current date. This defaults to the system date. DRP uses this in conjunction with Overdue Days to establish the start date for the DRP run as follows:

Start Date = Current Date - Overdue Days.

Overdue Days

Specify the number of days prior to the current date within which the application still includes outstanding supply and demand orders (exclude any forecasts).

Time Fence Days

Specify the number of days, forward from the current date of the DRP run, during which the plan remains frozen. DRP sets any supply suggestions, required within this period, for action on the first working day after the time fence. If this is blank or zero, DRP calculates the time fences at item level (defined within Distribution Item Master Maintenance), based on lead times.

Calculate Safety Stock

Enter one of the following:

- 0 - To only consider fixed safety stocks.
- 1 - To calculate safety stock cover for DRP items based on forecasted demand.

Safety Stock Cover Weeks & Days

Specify the number of weeks and days safety cover to use, as a blanket value for all items in this run. DRP calculates this from Forecast demand for each item, you must therefore enter sales forecasts for all items requiring safety stock cover.

If this field is blank or zero and you require safety stock calculations, the number of weeks/days safety cover defaults to that entered at DRP Item Master level.

End Date

Specify the last date for the planning run to consider. Defaults to the end date of the previous run.

Include Forecasts

Enter the type of forecast(s) that the planning run considers:

- 1 - Include Sales Forecast only.
- 2 - Include Stock Level Forecasts only.
- 3 - Include both Sales and Stock Level Forecasts.
- 0/Blank - Exclude all forecasts, only consider the actual demand.

DRP considers each item separately, with forecasts included or excluded on the basis of the Distribution Item Master DRP Forecast Field Entry.

Functions:

F14

Review Specification. Use this function to enter further Net Change or Selective processing details.

F16

Restrict Extractions. Use this function to exclude certain purchase order details.

F19

Print Last Run Details. Use this function to print the report of the last run.



Select **F8=Submit**. This validates all details and submits the regeneration plan batch job.

DC Run Net Change Trigger Selection Window (F14)



To display this window, on the DC Run Selection Screen, set the DRP Run Type to 2 and select **F14=Review Specification**.

Use this window to maintain the Net Change selections for the current run. Each time you press **Enter**, if all the details are valid, the next DC in the network displays.

DR002	Z1 - Demonstration Company	USER SP1	23/09/94 11:27:47
DRP DC Run Selection			
Network..... N1 UK Supply Network			
Net Change Trigger Selection			
DC..... D1 Northern Regional DC			
Sel	Trigger Reason	Description	Unprocessed Triggers
-	01	Forecast vs Actual Comparison.	0
-	02	Forecast Generation.	0
-	03	Forecast Maintenance.	0
-	04	Distribution Item Master.	0
-	05	Unplanned Inventory Transactions.	0
-	06	Requisition Maintenance.	0
-	07	Unplanned Issue or Receipt.	0
-	08	Purchase Order Maintenance.	0
-	09	Distribution Order Maintenance.	4
			Quantity to Process
			0
			0
			0
			0
			0
			0
			0
			0
			0
			0
1=Select All 2=Select with Limit			
F3=Exit F18=Select All			

Fields:

Sel

Enter one of the following:

- 1 - To select all triggers to process for this reason code.
- 2 - To select a particular quantity of triggers to process for this reason code.

Quantity To Process

Enter the number of unprocessed triggers to process for this reason code. If you want to process all triggers, do not enter a value in this field

Functions:

F18

Select All. Use this function to select all unprocessed triggers for all Reason Codes.



Press **Enter**.

DC Run Selection Criteria Window (F14)



To display this window, set the DRP Run Type to 3 and select **F14=Review Specification** on the DC Run Selection Screen.

You use this screen to maintain the details for the selective processing run. The selections for the last selective processing run for the network display. You can enter selection details for each DC in the selected network. Each time you press **Enter**, if all the details are valid, the next DC in the network display.

DR002 Z1 - Demonstration Company USER SP1 23/09/94
11:26:30

DRP DC Run Selection

Network..... N1 UK Supply Network

DRP run type..... 3 1=Full regeneration

Enter Selection Criteria

DC..... D1 Northern Regional DC

Item.....?.. to

Planner.....?.. to

Item Group.....?.. to

Value/Usage Class..... to

Preferred Supplier.?.. to

F4=Prompt F12=Previous

Fields:

Item

Enter a range of items to be re-planned.

Planner

Enter a range of DRP Planners.

Item Group

Enter a range of Inventory Minor Item Groups.

Value/Usage Class

Enter a range of Inventory Values/Usage Classes.

Preferred Supplier

Enter a range of Preferred Suppliers. (You define Preferred Suppliers in Item/Stockroom Maintenance in Inventory Management.)

Rules for Range Selection:

Leave the From and the To fields blank to select all items.

If you enter a From value and leave the To field blank, then the To field defaults to the from field

If you enter a To value, you must enter a From value.

The To field must not be less than the From field.



Press **Enter**.

DC Run Restrict Order Extractions For Run Window (F16)



To display this window, select **F16=Restrict Extractions** on the DC Run selection Screen.

You use this window to select the purchase orders to extract for DRP processing. This improves processing efficiency by restricting data extraction.

DR002	Z1 - Demonstration Company	USER SP1	23/09/94 11:27:23
DRP DC Run Selection			
Network...	Restrict Order Extractions for Run		
DRP run t	Exclude Unconfirmed Quantities on Scheduled Purchase Orders..... 0 (1=Yes, 0=No)		
	Exclude Confirmed Purchase Orders (Outstanding, GI, Inspection).... 0 (1=Yes, 0=No)		
Enter:	Current date..	F12=Previous	
	Overdue days.....	7	
	Time fence days.....	1	
	Calculate safety stock....	1 (0=No, 1=Yes)	
	Safety stock cover weeks..	0 Item Dependent	
	Days...	0	
	End date.....	311294	
	Include forecasts.....	1 (1=Sales, 2=Stock building, 3=Both, 0=Neither, Blank=As per item)	
F3=Exit F5=Refresh F8=Submit F12=Previous F14=Review specification F16=Restrict extractions F19=Print last run details			

Fields:

Unconfirmed Quantities On Scheduled Purchase Orders

Enter one of the following:

0 - To include all scheduled purchase order quantities whether confirmed or not. DRP assigns the unscheduled order quantities to the last planning period in the DRP run.

1 - To exclude unconfirmed order quantities from scheduled orders.

Confirmed Purchase Orders Not Yet Accepted Into Stock

Enter one of the following:

0 - To include all purchase order quantities for processing.

1 - To exclude all purchase orders from processing. This applies particularly where there is no local purchasing at the DC.



Press **Enter** to update exclusion criteria.

Run DRP for Centre

1... **2...** 2/DRP

You use this function to assess the supply and demand for the selected supply centre, and to produce the central supply plan.

The supply plan, for example, the schedule, may contain suggested Purchase Orders and/or amendments to existing orders.

Run DRP for Centre Screen



Select Run DRP for Centre.

You use this screen to select the supply centre to evaluate.

DR029	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
Run DRP for Centre		10:53:15	
Enter Centre Code...?... █			
F3=Exit F4=Prompt			

Fields:

Centre Code

Enter the code of a centre defined to at least one network, via DRP Network Maintenance.



Press **Enter** to Continue.

Centre Run Selection Screen



To display this screen, on the Run DRP for Centre Screen, enter a Centre Code and press **Enter**.

You use this screen to specify and submit a DRP processing run.

```

DR002          Z1 - UK Demonstration Company      USER GBJBANB4   10/03/98
                                           10:53:44

DRP Centre Run Selection

      Centre..... C1  AS

      DRP run type..... 1  1=Full regeneration
                           2=Net change
                           3=Selective

-----

Enter:  Current date..... 100398
        Overdue days..... 10
        Time fence days..... 5
        Calculate safety stock.... 1      (0=No, 1=Yes)
        Safety stock cover weeks.. 25
        Days... 0
        End date..... 280398
        Include forecasts..... -      (1=Sales, 2=Stock building, 3=Both,
                                         0=Neither, Blank=As per item)

-----
F3=Exit F5=Refresh F8=Submit F12=Previous F14=Review specification
F16=Restrict extractions F19=Print last run details
  
```

Fields:

DRP Run Type

Enter the type of DRP run to process:

1 - Full Regeneration. Re-plans all items.

2 - Net Change. Re-plans the items that have changes in the supply, demand, stock or replenishment parameters, since you last planned them. To select which you want to process, select **F14=Review specification**.

3 - Selective. Re-plans items within specified ranges of items, DRP Planners, Minor Item Groups, Cost/Usage Elements and/or Preferred Suppliers. To enter these ranges, select **F14=Review Specification**.

Enter:

Current Date

Enter the current date. DRP uses this in conjunction with Overdue Days to calculate the start date for the DRP run as follows:

Start Date = Current Date - Overdue Days.

Overdue Days

Enter the number of days prior to the current date within which outstanding supplies are still valid.

Time Fence Days

Enter the number of days, forward from the date of the DRP run, the plan remains frozen. DRP sets any supply suggestions within this period for action on the first working day after the time fence. If this is blank or zero, DRP calculates time fences at item level (defined through Distribution Item Master Maintenance).

Calculate Safety Stock

Enter one of the following:

1 - To calculate safety stock cover for DRP items based on forecasted demand.

0 - To only consider the fixed safety stocks defined within Distribution Item Master Maintenance.

Safety Stock Cover Weeks & Days

Enter the number of weeks and days safety stocks cover required for a blanket entry applicable to all items in this run. DRP calculates this from the Sales Forecast for each item; you must therefore enter sales forecasts for all items requiring safety stock cover.

If the safety weeks and days cover for this run is blank or zero, the number of weeks and days cover defaults to that entered at DRP item master level.

End Date

Specify the last date the planning run considers. Defaults to the end date of the previous run.

Include Forecasts

Enter one of the following:

1 - Include sales forecast only

2 - Include stock level forecasts only.

3 - Include both sales and stock level forecasts.

0/Blank - Exclude all forecasts. Only consider actual demand.

DRP considers each item separately, with forecasts included or excluded on the basis of specification in Distribution Item Master Maintenance.

Functions:

F14

Review Specification. Use this function to enter further details relating to net change or selective processing.

F16

Restrict Extractions. Use this function to exclude certain Purchase Orders.

F19

Print Last Run Details. Use this function to print a report showing the last print run details.



Select **F8=Submit**.

Centre Run Net Change Trigger Selection Window (F14)



To display this window, on the Centre Run Selection Screen, set the DRP Run Type to 2, and select **F14=Review specification**.

You use this screen to change the selections for the net change processing run for the selected DRP Centre.

DR002 Z1 - UK Demonstration Company USER GBJBANB4 10/03/98
10:53:44

DRP Centre Run Selection

Centre..... C1 AS

Net Change Trigger Selection
Centre... C1 AS

Sel	Trigger Reason	Description	Unprocessed Triggers	Quantity to Process
☒	01	Forecast vs Actual Comparison.	0	0
☐	02	Forecast Generation.	62	0
☐	03	Forecast Maintenance.	0	0
☐	04	Distribution Item Master.	0	0
☐	05	Unplanned Inventory Transactions.	2	0
☐	06	Requisition Maintenance.	1	0
☐	07	Unplanned Issue or Receipt.	0	0
☐	08	Purchase Order Maintenance.	4	0
☐	09	Distribution Order Maintenance.	0	0

h, m)

1=Select All 2=Select with Limit
F3=Exit F18=Select All

Fields:

Sel

Enter one of the following:

- 1 - To select all triggers to process for this reason code.
- 2 - To select a particular quantity of triggers to process for this reason code.

Quantity To Process

Specify the number of unprocessed triggers to process for this reason code in the DRP Net Change run. Do not enter a value in this field if you want to process all triggers for this reason code.

Functions:

F18

Select All: Use this function to select all unprocessed triggers for all reason codes.



Press **Enter**.

Centre Run Selection Criteria Window (F14)



To display this window, on the Centre Run Selection Screen, set the DRP Run Type to 3, and select **F14=Review specification**.

You use this screen to maintain the selections for the last selective processing run for the centre.

DRP002 Z1 - UK Demonstration Company USER GBJBANB4 10/03/98
11:00:20

DRP Centre Run Selection

Centre..... C1 AS

DRP run type..... 3 1=Full regeneration

Enter Selection Criteria

Centre... C1 AS

Item.....?.. to

Planner.....?.. to

Item Group.....?.. to

Value/Usage Class..... to

Preferred Supplier.?.. to

F4=Prompt F12=Previous

h,
m)

Fields:

Item

Enter a range of Items to select for re-planning.

Planner

Enter a range of DRP planners.

Item Group

Enter a range of Inventory Minor Item Groups.

Value/Usage Class

Enter a range of Inventory Values/Usage Classes.

Preferred Supplier

Enter a range of preferred suppliers. You define preferred suppliers in Item/Stockroom Maintenance in Inventory Management.)

Rules for Range Selection

Leave the From and the To fields blank, to select all items.

If you enter a From value and leave the To field blank, then the To field defaults to the From field.

If you enter a To value, you must enter a From value.

The To field must not be less than the From field.



Press **Enter** to continue.

Centre Run Restrict Order Extractions For Run Window (F16)



To display this window, select **F16=Restrict Extractions** on the Centre Run Selection Screen.

Use this window to select which Purchase orders the DRP processing run extracts. You use this to control the efficiency of DRP processing.

```
DR002          Z1 - UK Demonstration Company      USER GBJBANB4  10/03/98
                                                    11:00:57

DRP Centre Run Selection

  Centre...
  DRP run t

  Restrict Order Extractions for Run
  Exclude Unconfirmed Quantities
  on Scheduled Purchase Orders..... 1 (1=Yes, 0=No)
  Exclude Confirmed Purchase Orders
  (Outstanding, GI, Inspection).... 0 (1=Yes, 0=No)

Enter:  Current date.. F12=Previous
        Overdue days..... 10
        Time fence days..... 5
        Calculate safety stock.... 1      (0=No, 1=Yes)
        Safety stock cover weeks.. 25
        Days... 0
        End date..... 280398
        Include forecasts..... -      (1=Sales, 2=Stock building, 3=Both,
                                         0=Neither, Blank=As per item)

F3=Exit F5=Refresh F8=Submit F12=Previous F14=Review specification
F16=Restrict extractions F19=Print last run details
```

Fields:

Unconfirmed Quantities On Scheduled Purchase Orders

Enter one of the following:

0 - To include all outstanding order quantities on scheduled orders irrespective of whether the supplier has confirmed.

1 - To exclude unconfirmed quantities.

Confirmed Purchase Orders Not Yet Accepted Into Stock

Enter one of the following:

0 - To include all orders which may be in transit; received but not inspected, or in inspection.

1 - To exclude all orders not yet received into stock.



Press **Enter** to update exclusion criteria.

Network Run

1... **2...** 3/DRP

You use this function to access the supply and demand for the whole of the selected Network within a single run.

It includes the following automated processes:

- Evaluate DC Demand - Full Regeneration, Net Change or Selective.
- Confirm Supply Suggestions.
- Create Local Purchase Orders.
- Create Distribution Orders.
- Run Central Supply Plan - Full Regeneration only.

This removes the manual intervention stage of amending suggestions and creating orders (via Purchase Requisitioning) for the DCs.

The automated run is particularly useful where supply suggestions are unlikely to require many amendments. You can assess the whole network with a single overnight run. You can review the resulting DC and centre schedules either by the schedule enquiries, or by schedule reports.



Note: You can make any amendments to the generated supply orders by maintaining the Purchase Order (via Purchase Management) or Distribution Order (via the Distribution Order amend option).

Network Run Screen



Select Network Run.

You use this screen to select the network to evaluate.

DR042	Z1 - Demonstration Company	User SP1	23/09/94 11:32:33
Network Run			
Enter Network Code...?.. ____			
This Run will do the following :-			
- Evaluate DC Demand, allowing Full Regeneration, Net Change or Selective Run - Create Purchase Orders - Create Distribution Orders - Run Full Regeneration for Centre			
F3=Exit F4=Prompt			

Fields:

Enter Network Code

Enter a code, as defined to DRP via Network Maintenance.



Press **Enter** to display the Network Run Selection Screen.

Network Run Selection Screen



To display this screen, press **Enter** on the Network Run screen, enter a Network Code.

You use this screen to specify and submit a DRP processing run.

DR002	Z1 - Demonstration Company	USER SP1	23/09/94 11:33:02
DRP Network Run Selection			
Network..... N1		UK Supply Network	
DRP run type..... 2		1=Full regeneration 2=Net change 3=Selective	
Enter:	Current date..... 230994		
	Overdue days..... 7		
	Time fence days..... 1	Item Dependent	
	Calculate safety stock.... 1	(0=No, 1=Yes)	
	Safety stock cover weeks.. 0	Item Dependent	
	Days... 0		
	End date..... 311294		
	Include forecasts..... 1	(1=Sales, 2=Stock building, 3=Both, 0=Neither, Blank=As per item)	
F3=Exit F5=Refresh F8=Submit F12=Previous F14=Review specification F16=Restrict extractions F19=Print last run details			

Fields:

DRP Run Type

Enter the type of DRP run to process:

1 - Full Regeneration. Re-plans all items.

2 - Net Change. Re-plans the items that have changes in the supply, demand, stock or replenishment parameters, since you last planned them. To select which you want to process, select **F14=Review specification**.

3 - Selective. Re-plans items within specified ranges of items, DRP Planners, Minor Item Groups, Cost/Usage Elements and/or Preferred Suppliers. To enter these ranges, select **F14=Review Specification**.

Enter:

Current Date

Enter the current date. DRP uses this in conjunction with Overdue Days to calculate the start date for the DRP run as follows:

Start Date = Current Date - Overdue Days.

Overdue Days

Enter the number of days prior to the current date within which outstanding supplies are still valid.

Calculate Safety Stock

Enter one of the following:

0 - To only consider the fixed safety stocks defined within Distribution Item Master Maintenance.

1 - To calculate safety stock cover for DRP items based on forecasted demand.

Safety Stock Cover Weeks & Days

Enter the number of weeks and days safety stocks cover required for a blanket entry applicable to all items in this run. DRP calculates this from the Sales Forecast for each item. You must therefore enter sales forecasts for all items requiring safety stock cover.

If the safety weeks and days cover for this run is blank or zero the number of weeks and days cover defaults to that entered at DRP item master level.

Time Fence Days

Enter the number days, forward from the date of the DRP run, the plan remains frozen. DRP sets any supply suggestions within this period for action on the first working day after the time fence. If this is blank or zero, DRP calculates the time fences at item level (defined through Distribution Item Master Maintenance).

End Date

Specify the last date the planning run considers. Defaults to the end date of the previous run.

Include Forecasts

Enter one of the following:

1 - Include sales forecast only.

2 - Include stock level forecasts only.

3 - Include both sales and stock level forecasts.

0/Blank - Exclude all forecasts. Only consider actual demand.

DRP considers each item separately, with forecasts included or excluded on the basis of specification in Distribution Item Master Maintenance.

Functions:

F14

Review Specification. Use this function to enter further details relating to net change or selective processing.

F16

Restrict Extractions. Use this function to exclude certain purchase orders.

F19

Print Last Run Details. Use this function to print the report of the last run details.



Select **F8=Update** to validate the entries and submit the regeneration batch job.

Network Run Net Change Trigger Selection Window (F14)



To display this window, on the Network Run Selection Screen, set the DRP Run Type to 2, and select **F14=Review Specification**.

Use this window to maintain the net change selections for the selected network. You can enter net change details for each DC, when you press **Enter**, if all the details are valid, the next DC in the network displays.

```

DR002                Z1 - Demonstration Company        USER SP1        23/09/94
                                                11:33:02

DRP Network Run Selection

Network..... N1 UK Supply Network
Net Change Trigger Selection
DC..... D1 Northern Regional DC

Sel Trigger Description      Unprocessed Quantity to
Reason                      Triggers      Process
- 01 Forecast vs Actual Comparison.      0      0
- 02 Forecast Generation.                0      0
- 03 Forecast Maintenance.               0      0
- 04 Distribution Item Master.            0      0
- 05 Unplanned Inventory Transactions.    0      0
- 06 Requisition Maintenance.            0      0
- 07 Unplanned Issue or Receipt.         0      0
- 08 Purchase Order Maintenance.         0      0
- 09 Distribution Order Maintenance.      4      0

1=Select All  2=Select with Limit
F3=Exit  F18=Select All
  
```

Fields:

Sel

Enter one of the following:

- 1 - To select all triggers to process for this reason code.
- 2 - To select a particular quantity of triggers to process for this reason code.

Quantity To Process

Specify the number of triggers you want to process for this reason code. Do not enter a value in this field if you have entered 1 alongside this reason code.

Functions:

F18

Select All. Use this function to select all unprocessed triggers for all reason codes.



Press **Enter** to continue.

Network Run Selection Criteria Window (F14)



To display this window, set the DRP Run Type to 3, and select **F14=Review Specification** on the Network Run Selection Screen.

Use this window to maintain the details for the selective processing run. You can enter selection details for each DC in the selected network. When you press **Enter**, if all the details are valid, the next DC in the network displays.

```
DR002          Z1 - Demonstration Company      USER SP1      23/09/94
                                                    11:33:53

DRP Network Run Selection

      Network..... N1 UK Supply Network
      DRP run type..... 3 1=Full regeneration
Enter Selection Criteria
DC..... D1 Northern Regional DC

Item.....?..      _____ to _____
Planner.....?..      _____ to _____
Item Group.....?..      _____ to _____
Value/Usage Class.....      _____ to _____
Preferred Supplier.?..      _____ to _____

F4=Prompt F12=Previous
```

Fields:

Item

Enter a range of items to select for re-planning.

Planner

Enter a range of DRP Planners.

Item Group

Enter a range of Inventory Minor Item Groups.

Value/Usage Class

Enter a range of Inventory Values/Usage Classes.

Preferred Supplier

Enter a range of Preferred Suppliers. You define preferred suppliers in Item/Stockroom Maintenance in Inventory Management.)

Rules for Range Selection:

Leave the From and the To fields blank to select all items.

If you enter a From value and leave the To field blank, then the To field defaults to the From field.

If you enter a To value, you must enter a From value.

The To field must not be less than the From field.



Press **Enter**.

Network Run Restrict Order Extractions For Run Window



To display this window, set the DRP Run Type to 3, and select **F14=Review Specification** on the Network Run Selection Screen.

Use this window to select which purchase orders to extract for DRP processing. This helps to improve the processing efficiency of DRP runs.

DR002	Z1 - Demonstration Company	USER SP1	23/09/94 11:34:29
DRP Network Run Selection			
Network...	Restrict Order Extractions for Run		
DRP run t	Exclude Unconfirmed Quantities on Scheduled Purchase Orders..... 0 (1=Yes, 0=No)		
	Exclude Confirmed Purchase Orders (Outstanding, GI, Inspection).... 0 (1=Yes, 0=No)		
Enter: Current date..	F12=Previous		
Overdue days.....	7		
Time fence days.....	1	Item Dependent	
Calculate safety stock....	1	(0=No, 1=Yes)	
Safety stock cover weeks..	0	Item Dependent	
Days...	0		
End date.....	311294		
Include forecasts.....	1	(1=Sales, 2=Stock building, 3=Both, 0=Neither, Blank=As per item)	
F3=Exit F5=Refresh F8=Submit F12=Previous F14=Review specification F16=Restrict extractions F19=Print last run details			

Fields:

Unconfirmed Quantities On Scheduled Purchase Orders

Enter one of the following:

0 - To include all outstanding order quantities on scheduled orders, irrespective of whether the buyer has confirmed unscheduled order line balances.

1 - to exclude any unconfirmed quantities.

Confirmed Purchase Orders Not Yet Accepted Into Stock

Enter one of the following:

0 - To include all confirmed orders that may be in transit; received but not inspected, or in inspection.

1 - To exclude all confirmed orders not yet received into stock.



Press **Enter** to update exclusion criteria.

Distribution Order Entry

1... 4/DRP
2... 1/WTB

A Distribution Order controls the movement of goods between two stockrooms in a single company. For most of its processing cycle, you manage a Distribution Order using functions in the Sales Order Processing or Warehousing applications.

You assign each stockroom to a particular customer, known as the internal customer, using Distribution Requirements Planning customer maintenance or, if using World Trade, World Trade Stockroom Maintenance. You create the Distribution Order with a From and a To stockroom, and allocate a sales order number. DRP uses the order number and the internal customer associated with the To stockroom to process the order through the allocate, generate pick list and confirm despatch stages.

After confirm despatch, the confirm receipt procedure receives the stock into the to stockroom and updates the stock balance. Order entry identifies the order as a Distribution Order and does not print an invoice.

If the From and To stockrooms are in different EC countries, confirm despatch creates World Trade movements. DRP uses these movements to produce Intrastat and ESL reports, and to post the acquisition VAT due on receipt of the goods.

DRP takes into account manually entered Distribution Orders in the distribution planning runs.

Catchweight

The Distribution order entry options calculate secondary values and UoMs. You can enquire upon orders for catchweight items using the Distribution Enquiry options.

Distribution Order Entry Selection Screen



Select Distribution Order Entry.

You use this screen to select the despatching and receiving distribution stores, and to specify the required despatch date. If you create a number of Distribution Orders sequentially, the previously created order details display.

DR300	Z1 - Demonstration Company	User SP1	23/09/94 11:36:26
-------	----------------------------	----------	----------------------

Distribution Order Entry	
From Stockroom.....?	<u>01</u>
To Stockroom.....?	<u>02</u>
Despatch due date.....	<u>23/09/94</u>

F3=Exit F4=Prompt	
-------------------	--

Fields:

From Stockroom

Enter the stockroom that sources the distribution order.

To Stockroom

Enter the stockroom that receives the distribution order.

Despatch Due Date

Enter the date on which the distribution order is due for despatch.



Press **Enter** to display the delivery address
override screen.

Distribution Order Entry Delivery Address Override Screen



To display this screen, enter the required details and press **Enter** on the Distribution Entry Selection Screen.

You use this screen to override the delivery name and address that appear on the despatch note.

DR300	Z1 - Demonstration Company	User SP1	23/09/94 11:36:40
-------	----------------------------	----------	----------------------

Distribution Order Entry

From Stockroom..... 01 Central Stockroom

To Stockroom..... 02 Northern RDC Stockroom

Despatch due date..... 23/09/94

Internal Customer..... D1 001

Delivery name and address:

Internal Customer (Northern RDC)

Unit 12

East Lancs. Trading Estate

Salford

Greater Manchester

UK

M27

F3=Exit F12=Previous F21=Internal Text F22=External Text

Fields:

Delivery Name And Address Details

Enter the delivery name and address to appear on the pick/despatch notes for the distribution order. This defaults to the delivery address defined to the Internal customer for the order.

Functions:

F21

Text. Use this function to enter text for the order using the Maintain Text Window.



Press **Enter** to display the Distribution Order Line Entry screen.

Maintain Text Window (F21)



To display this window, select **F21=Text** on the Distribution Order Entry Delivery Address Override Screen.

Or To display this window, on the Distribution Order Amendment Header Screen, select **F21=Text**.

Use this window to enter or select a Usage Code and/or a Language Code.

DR300 NR - Neil Radford and Co. Ltd User GBJBA1MS 19/07/96 11:06:56

Distribution Order Entry

From Stockroom..... 01 Neil's Stockroom 01

To Stockroom..... 02 Neil's Stockroom 02

Despatch due date..... 19/07/96

Internal Customer... **Maintain Text**

Delivery name and ad

1450 NRC Test Compan

Address Line 1 ----->

Address Line 2 ----->

Address Line 3 ----->

Address Line 4 ----->

Address Line 5 ----->

9999 9999

F3=Exit F12=Previous F21=Text

14-44 SF MW KS IM II KENB20A PET166S2

Fields:

Usage Code

Select a Usage Code to specify where to print or display the text.



Note: Inventory supplies some standard text usage codes. You can define other usage codes in Inventory Descriptions Maintenance under major type USGC.

Language Code

Select a language code, as well as a usage code, if you want to enter multi-lingual text.



Note: You do not need to select Language codes to print text in the native language.

F13

Select existing text. Use this function to list all Usage codes that have text defined for the specified text type and text reference. You can select the text you want to use.




Select **F12=Previous** to return to the previous screen.

Order Header Text Entry Window

-  To display this window, enter a usage code, and, if required, a Language code on the Delivery Address Details Maintain Text Window, and press **Enter**.

You use this window to enter the header text.



DR300 Z1 - GB Demonstration Company User: GBJBA1MS 18/11/97
15:03:08

Distribution Order Entry

From Stockroom..... AM Mats DRP stockroom A

To Stockroom..... BM Mats DRP Stockroom B

Despatch due date..... 18/

Internal Customer... **Maintain**

Delivery name and ad Text Typ

Mats delivery address Text Ref

Holyhead Road Usage Co

Seaton Language

Devon F4=Prompt

F3=Exit F12=Previous F21=Text

Order Header Text

Lin	Internal Text
1	
2	
3	
4	
5	
6	

Position to ____ Insert ____ after ____
Delete ____ from ____

F5=Refresh F8=Update F12=Previous
F13=Change usage/language

Fields:

Internal Text

Enter the text you want to appear on the specified document.

Position To

Use this field to move the cursor to a specified line.

Insert After

Specify how many blank lines you want to insert after the line number specified.

Delete After

Specify how many lines you want to delete and the first line you want to delete.

Functions:

F13


Change Usage/Language. Use this function to redisplay the Maintain Text window so you can maintain a different Usage code.

-  Select **F8=Update** to return to the Maintain Text Window.

Order Header Text Selection Window (F13)

-  To display this window, on the Delivery Address Details Maintain Text Window, select **F13=Select Existing Text.**

You use this window to select a usage code or usage code/language code combination so you can maintain the header text.



DR300 Z1 - GB Demonstration Company User GBJBAIMS 18/11/97 15:10:23

Distribution Order Entry

From Stockroom..... AM Mats DRP stockroom A

To Stockroom..... BM Mats DRP Stockroom B

Despatch due date..... 18/ Order Header Text

Internal Customer... Maint Order Header Text

Delivery name and ad Text

Mats delivery address Text

Holyhead Road Lang

Seaton F4=Pr

Devon

Reference.. 000524J

Sel	Text Usage	Language
☒	E External Text	
☐	I Internal Text	

1=Select

F12=Previous

F13=Change usage/language

F3=Exit F12=Previous F21=Text

Fields:

Sel

Enter 1 alongside the Usage Code for which you want to maintain the text.

-  Select a usage code to display the Order Header Text Entry Window

Distribution Order Entry Lines Screen



To display this screen, press **Enter** on the Order Entry Delivery Address Override Screen.

You use this screen to enter Distribution Order lines. If the despatch date is within the time fence and sufficient stock exists in inventory, DRP automatically allocates the line. Otherwise the quantity shows in reverse image as unallocated.

DR320	Z1 - Demonstration Company	USER SP1	23/09/94
			11:37:10
Distribution Order Entry			
From Stockroom... 01 Central Stockroom		Due Date.. 23/09/94	
To Stockroom..... 02 Northern RDC Stockroom			
Item/Description	Despatch Due	Receipt Due	Quantity UOM
5001	23/09/94	23/09/94	10.000 BX
- Suncream Factor 4 225ml			
1=Amend, 2=Int Text, 3=Ext Text, 4=Delete, 6=Avail, 8=Force Alloc, 9=Dealloc			
Item?.. _____ Qty.. _____ .000 Dsp. 23/09/94 Rcpt. 07/00/00			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F15=Restart			

Fields:

(Untitled)

Enter one of the following:

- 1 - To amend the order line details.
- 2 - To enter text for the order line.
- 4 - To delete the line from the order. This reverses any existing allocations.
- 6 - To enquire on the current stock level details for the item at the from stockroom and the current supply/demand situation.
- 8 - To fully allocate a partially or wholly unallocated order line. Allocation takes place regardless of the available stock quantity, allocation priority or allocation time fence.
- 9 - To fully deallocate a fully or partially allocated order line.

To add a new order line or amend an existing order line, enter the following:

Item

Enter an inventory item. You must define the item to both the From and To stockrooms for the order.

Qty

Enter the quantity for the order line.

Dsp

Enter the despatch date. This defaults to the due date from the previous screen.

Rcpt

Enter the receipt date. If you leave this blank, DRP calculates this as the date of receipt at the To stockroom, based on the item lead time.



Note: You do not need to enter both despatch and receipt dates. If you enter one, DRP calculates the other based on the lead time at the To stockroom.

Functions:

F11

Delete. Use this function to delete the whole order.

F15

Restart. Use this function to abandon all changes made since last update and return to the Distribution Order entry Selection Screen.



Select **F8=Update** to update the distribution order details and display distribution order numbers.

Distribution Order Amendment



5/DRP
2/WTB

You use this function to amend an existing Distribution Order number. You can amend order header or line details. If you do not know the order number, you can enquire on Distribution Orders by internal customer.

Distribution Order Amendment Selection Screen



To display this screen, select Distribution Order Amend.

You use this screen to select the Distribution Order you want to alter.

DR310	Z1 - Demonstration Company	User SP1	23/09/94 11:40:27
-------	----------------------------	----------	----------------------

Distribution Order Amendment

Order Number..... 0000115

Amend header or lines... 2 (1=Header, 2=Lines).

If Order number is not known, enter an Internal Customer to enquire on Orders by Customer.

Internal Customer....?.. _____

F3=Exit F4=Prompt

Fields:

Order Number

Enter an existing Distribution Order number.

Amend Header Or Lines

Enter one of the following:

- 1 - To amend Header level details.
- 2 - To amend Line level details.

Internal Customer

If you do not know the correct order number, enter an internal customer to list the Distribution Orders for that Customer.



Press **Enter** to continue.

Distribution Order Amendment Header Screen



To display this screen, on the Distribution Order Amendment Selection Screen, set Amend Header or Lines to 1, and press **Enter**.

You use this screen to override the delivery name and address details that appear on the despatch note.

DR310	Z1 - Demonstration Company	User SP1	23/09/94 11:40:10
-------	----------------------------	----------	----------------------

Distribution Order Amendment

From Stockroom..... 01 Central Stockroom

To Stockroom..... 02 Northern RDC Stockroom

Despatch due date..... 23/09/94

Internal Customer..... D1 001

Delivery name and address:

Internal Customer (Northern RDC)

Unit 12

East Lincs. Trading Estate

Salford

Greater Manchester

UK

M27

F3=Exit F12=Previous F21=Internal Text F22=External Text

Fields:

Despatch Due Date

Enter the date on which the distribution order is due for despatch.

Delivery Name And Address

Enter the name and address to print on the pick or despatch note for the distribution order.

Functions:

F21

Text. Use this function to maintain the text for the order.



Press **Enter**. The changed details update and the order amendment screen re-displays.

Distribution Order Amendment Lines Screen



To display this screen, set Amend Header or Lines to 2 on the Distribution Order Amendment Selection Screen, and press **Enter**.

You use this screen to enter the Distribution Order line of an inventory item and a quantity. If the despatch date is within the time fence, and sufficient stock exists in inventory, DRP automatically allocates the line. Otherwise the quantity shows in reverse image as unallocated.

DR320	Z1 - Demonstration Company	USER SP1	23/09/94
			11:40:41
Distribution Order Amendment			
From Stockroom.... 01 Central Stockroom		Due Date.. 23/09/94	
To Stockroom..... 02 Northern RDC Stockroom			
Item/Description	Despatch Due	Receipt Due	Quantity UOM
- 5001	23/09/94	23/09/94	10.000 BX
Suncream Factor 4 225ml			
1=Amend, 2=Int Text, 3=Ext Text, 4=Delete, 6=Avail, 8=Force Alloc, 9=Dealloc			
Item?.. _____ Qty.. _____ .000 Dsp. 23/09/94 Rcpt. 0/00/00			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F15=Restart			

Fields:

Selection

Enter one of the following:

- 1 - To amend the Order Line.
- 2 - To enter text associated with the order line.
- 4 - To delete a Line from the order. This reverses any existing allocations.
- 6 - To enquire on the current stock level details for the Item at the From Stockroom and the current supply/demand situation.
- 8 - To fully allocate a partially or wholly unallocate order line. Allocation takes place regardless of the available stock quantity, allocation priority or allocation time fence.
- 9 - To fully deallocate a fully or partially allocated order line.

To add a new order line, or amend an existing order line, enter the following:

Item

Enter an inventory item. You must define the item to both the From and To stockrooms for the order.

Qty

Enter the quantity for the order line.

Dsp

Enter the despatch date. This defaults to the due date of the previous screen.

Rcpt

Enter the receipt date. If you leave this date blank, DRP calculates this based on the lead time for the To stockroom.



Note: You do not need to enter both despatch and receipt date. If you enter one, DRP calculates the other based on the lead time at the To stockroom.

Functions:

F15

Restart. Use this function to abandon all changes made since last the update.



Select **F8=Update** to update distribution order details and display the distribution order number.

Record Transfer Out

1...
2...

6/DRP

This is for domestic transactions only. Use this function to record the transfer of goods out of one stockroom and into another internal stockroom.

Record Transfer Out Screen



To display this screen, select Record Transfer Out.

You use this screen to enter the details of the transfer.

IN086	NR - Neil Radford and Co. Ltd	USER GBJBA1MS	23/08/96 11:44:04
Record Transfer Out			
From stockroom....?.. █			
To stockroom.....?.. __			
Internal customer.?.. _____			
Ref.no. date & type.?.. _____		23/08/96	__
Narrative.....?.. _____			
Reason code.....?.. __			
For domestic transactions only			
F3=Exit F4=Prompt			
05-24	SA	MW	KS IM II KENB20A PET087S1

Fields:

From Stockroom

Enter the stockroom from which you transferred the goods.

To Stockroom

Enter the stockroom that is to receive the goods.

Internal Customer

Enter the Internal Customer code.

Ref. No. Date & Type

Enter the reference number, the date and the type code.

Narrative

Enter some text to explain the transfer.

Reason Code

Enter the reason code for the transfer.



Press **Enter** to confirm the transaction.