

-
-
-
-
-

Chapter 6

Utilities



Maintain Company Profile



1/DRU

You use this procedure to define new companies within DRP and maintain existing company details. The Company Code must correspond to the one defined to the Inventory Management application for this company.



Note: You maintain period details in this company profile. You must review these before you create a new calendar year using the Calendar Maintenance option.

Maintain Profile Records Screen



Select Maintain Company Profile to display the Maintain Profile Records Screen.

You use this screen to enter the company code you want to define new DRP companies and maintain existing DRP company details for.

DR019

DRP Company Profile

User SP1

22/09/94
11:52:04

Maintain Profile Records

Sel

Company

1

Z1

Demonstration Company

Enter new company

1=Select

F3=Exit

Fields:

Sel

Enter 1 to select the company to maintain.

Enter New Company

Enter a code for the new company.



Note: This code must not already exist in DRP. However, it should exist in Inventory Management.



Select a company, or enter a new company code to display the Maintain DRP Company Profile Screen.

Maintain DRP Company Profile Screen



To display the Maintain DRP Company Profile Screen, select a company, or enter a new company code on the Maintain Profile Records Screen.

You use this screen to specify the company defaults, including how you consume forecasts by actual demand, and the maximum number of lines on a distribution order.

DR019		USER SP1		22/09/94 11:52:41	
Maintain DRP Company Profile.					
Company code..... Z1 Company name... Demonstration Company					
Consume forecast.... 1 (0=No) Lines per Distribution Order... 999					
(1=Run level, 2=Week level, 3=Period level) Forecast Error Tolerance%					
Calc. safety stock.. 1 (0=No, 1=Yes) Absolute..... 30.00					
Safety stock weeks.. 2 Include Quotations Percentage.. 100					
Safety stock days... 3 Period Forecasts.. 1 (0=No, 1=Yes)					
Calendar Parameters.					
Calendar code..... C1 Number of periods per year..... 13					
Period name		Days		Period name	
1. 1		28		3. 3	
4. 4		28		6. 6	
7. 7		28		9. 9	
10. 10		28		12. 12	
13. 13		28			
2. 2		28		5. 5	
5. 5		28		8. 8	
8. 8		28		11. 11	
11. 11		28			
Standard week template.					
M T W T F S S					
N N (Blank for working day or 'N' for non-working day)					
F3=Exit					

Fields:

Consume Forecast

Enter one of the following:

0 - If you do not require forecast consumption. Demand for a particular period is the greater of the forecast or actual sales for that period.

1 - If you require consumption of forecast with no period control. The system bases demand for a particular period on cumulative consumption of forecast and actual demand, without reference to period ends, between the start and end dates specified for a DRP run (see Example 1).

2 - If you require consumption of forecast by week. The system bases demand on cumulative consumption of forecast and actual demand within each week defined in the calendar for the DC/Centre. At week ends, the system resets accumulations to zero.

3 - If you require consumption of forecast by period. The system bases the forecast on cumulative consumption of forecast and actual demand within each period defined in the calendar for DC/Centre. At period ends the system resets accumulations to zero (see Example 2).

Lines Per Distribution Order

Enter the maximum number of lines to include on any Distribution Order. This must be greater than zero.

Calculate Safety Stock

Enter one of the following:

0 - Not to calculate safety stock during DRP processing. The system uses the Fixed Safety Stocks maintained at Item/DC level.

1 - To calculate variable safety stock. The system calculates the Safety Stock on the basis of Sales Forecasts and the minimum safety stock cover (weeks and days) specified.

Forecast Error Tolerance % Absolute

Specify the default percentage by which sales forecast quantities and actual sales quantities can differ without the system writing a Net Change trigger for the item. The system uses this if you do not enter a tolerance at item level.

Safety Stock Weeks & Days

If you want to calculate safety stock, enter the minimum cover required, in weeks and days. You can override this at item/DC level or at DRP run time.

The system calculates the sales forecast for the specified time and uses this as the safety stock quantity. However, it excludes the forecast in the current column, as the calculation of demand includes this.

The system does not calculate safety stocks at daily level.

Include Quotations Percentage

Specify a percentage of the quantities of sales quotations, set up in Advanced Order Entry, to be included as demand in the DRP processing runs.

For example: 100% = Include full quantities of all quotations.

20% = Assume demand to be 20% of quantities of all quotations.

0% = Exclude all quotations from DRP demand.

Period Forecasts

Enter one of the following:

0 - Not to calculate period forecasts.

1 - To calculate period forecasts. You can then maintain both Seasonal Profiles at period level and Item Group/Item level period forecasts.

Calendar Code

Enter the default Calendar Code for the company. Any DC or Centre without a Calendar Code assigned to it via Period Maintenance uses this calendar (defined via Calendar Maintenance).

Number Of Periods Per Year

Enter the number of periods per year, in the range 1 to 13 inclusive.

Period Name

Enter a description for each period, up to the number of periods specified.

Days

Enter the number of days for each period.

Standard Week Template

Enter N against non-working days in a normal working week. Leave blank for working days.



Press **Enter** to update the Company Profile record and return to the Maintain Profile Records screen.



Note: The total number of days must equal 364 or 371. Also, you must ensure that the next year begins on a Monday.

For example: 1994 Period 12:

Set the number of days to 32. This ensures that the year ends on a Sunday (01/01/95) rather than a Saturday (31/12/94). The total number of days in the year is then 364.

This is necessary because you maintain forecasts on a weekly basis, with the week always commencing on a Monday.

Example 1: Consumption Method 1 (No period control)

FTD - Accumulated Forecast to Date

ASD - Accumulated Actual Sales to Date

DTD - Demand To Date (greater of FTD & ASD)

CD - Consumed Demand (DTD for period less DTD for previous period)

Period	Week	F`Cast	Sales	FTD	ASD	DTD	CD
1	1	10	0	10	0	10	10
1	2	10	25	20	25	25	15
1	3	15	40	35	65	65	40
1	4	15	4	50	70	70	5
2	5	20	7	70	77	77	7
2	6	20	25	90	102	102	25
2	7	20	0	110	102	110	8
2	8	20	8	130	110	130	20
3	9	15	15	145	125	145	15
3	10	15	8	160	133	160	15
3	11	15	35	175	168	175	15
3	12	15	45	190	213	213	38

Example 2: Consumption Method 3 (Period)

Same principle of calculation applies for Consumption Method 2, that is by week.

Period	Week	F`Cast	Sales	FTD	ASD	DTD	CD
1	1	10	0	10	0	10	10
1	2	10	25	20	25	25	15
1	3	15	40	35	65	65	40
1	4	15	4	50	70	70	5
2	5	20	7	20	7	20	20
2	6	20	25	40	32	40	20
2	7	20	0	60	32	60	20
2	8	20	8	80	40	80	20
3	9	15	15	15	15	15	15
3	10	15	8	30	23	30	15
3	11	15	35	45	58	58	28
3	12	15	45	60	103	103	45

Copy Company



2/DRU

You use this function to duplicate the data relating to one company across libraries and companies. You can therefore, create backup libraries and create or update company data from a master company.

Copy Company Select Libraries Screen



Select Copy Company.

You use this screen to enter details for the Copy Company Select Libraries facility.

DR902CLP	DRP Copy Company Utility	User SP1	27/09/94 13:13:46
Copy Company - Select Libraries			
Library to copy from.....?.. <u>OSLDEM3</u>			
Library to copy to..... <u> </u>			
Regenerate file list..... _ (0=No> 1=Yes)			
Company number field default start position on files..... <u>0000</u>			
F3=Exit F4=Prompt F12=Previous			

Fields:

Library To Copy From

Enter the name of the AS400 Library which holds the Source DRP data. This defaults to the standard DRP Files library.

Library To Copy To

Enter the name of the AS400 Library to copy the source DRP data to.

Regenerate File List

Enter one of the following:

0 - Not to not regenerate file list.

1 - To regenerate file list.

Company Number Field Default Start Position On Files

Enter the company code from which to start the copying.



Press **Enter** to continue.

