

-
-
-
-
-

Chapter 1

Parameter Maintenance



Parameters

When you first install Job Management, your first task is to set up your company using the Company Profile option.

However, you will be unable to access one of the company profile screens. This is because you need to set up certain parameters before the screen will be available to you. You have to leave the Company Profile option, set up these parameters, and then re-enter it to complete the screen you were unable to enter at first.

Most of the parameters are simple to set up, you just enter a code and a description, but others are more complex, in particular the job types and employee grades and details.



Some parameters are mandatory entry. However, if your jobs do not need the breakdown of detail provided by the different parameters - if, for example, you do not need a breakdown by manager - you can set up your parameters with a blank code. Having a blank manager code, for example, means you can leave the Manager field blank in your job details if you wish. You can of course enter a description for this blank code.

Managers



1/JCK

A manager is specified at job detail level. A manager code can be for either a project manager or an account manager. The project manager is associated with any reviews, i.e. chargeable transaction reviews and invoice reviews.



Tip: Some parameters are mandatory entry. If you do not want to be forced to enter a manager, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Managers Update Screen



Take the Managers option to see the Managers Update Screen.

Fields:

Manager

Enter the code for the manager you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Locations



2/JCK

A location is specified at job detail level, and at employee level. Location codes specify the location of the employee who will carry out work against jobs, and/or the location where the work is taking place.



Tip: Some parameters are mandatory entry. If you do not want to be forced to enter a location, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Locations Update Screen



Take the Locations option to see the Locations Update Screen.

Fields:

Location

Enter the code for the location you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Regions



3/JCK

Specified at job detail level only. Regions identify the region responsible for carrying out work on jobs.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Regions Update Screen



Take the Regions option to see the Regions Update Screen.

Fields:

Region

Enter the code for the region you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Divisions



4/JCK

Specified at job detail level only. Division codes are used within Job Management to identify the division within the company which will be responsible for carrying out work on jobs.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Divisions Update Screen



Take the Divisions option to see the Divisions Update Screen.

Fields:

Division

Enter the code for the division you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Industry Codes



5/JCK

The industry code is specified at job level only. Each job can hold the industry code of the customer for whom the work is being carried out. You can then analyse across jobs on work carried out for a specific industry. You can set up the codes in any way you please, but we recommend the use of SIC (standard industry codes) codes.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Industry Codes Update Screen

 Take the Industry Codes option to see the Industry Codes Update Screen.

Fields:

Industry Code

Enter the code for the industry code you wish to add or amend.

 Press **Enter**, and the Description field appears.

Description

Enter or amend the description.

 Press **Enter** to update.

Profit/Cost Centres



6/JCK

Profit/cost centres are specified at job detail level and at employee level, and you can use them to analyse costs and income by profit/cost centre across jobs.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Profit/Cost Centres Update Screen



Take the Profit/Cost Centres option to see the Profit/Cost Centres Update Screen.

Fields:

Profit/Cost Centre

Enter the code for the profit/cost centre you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Charge Codes



7/JCK

Charge codes are specified at transactional level. They can further break down entries against direct transactions (including standing costs), timesheets and employee expenses. These could include items such as hotel bills, travel time, bank holiday and sickness.

If you have created an SOP order from within Job Management, and the SOP charge code on that order is also set up here in Job Management with an expense type and transaction type, then the system will automatically bring the SOP order value across to Job Management as a cost.

This means that you should make sure that any Job Management charge codes you want to use in this way are also set up in SOP.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Charge Codes Update Screen

 Take the Charge Codes option to see the Charge Codes Update Screen.

Fields:

Charge Code

Enter the charge code you wish to add or amend.

 Press **Enter**, and the following fields appear.

Description

Enter or amend the description.

Expense Type

Enter the expense type you wish to associate with this charge code. When the system creates a transaction from SOP, this is the expense type which will be on the transaction.

If you enter both an expense type and transaction type, this tells the system that you wish to bring costs from SOP into Job Management, as long as the charge code in SOP matches that in Job Management.

Transaction Type

Enter the transaction type you wish to associate with this charge code. When the system creates a transaction from SOP, this is the transaction type which will be on the transaction.

If you enter both an expense type and transaction type, this tells the system that you wish to bring costs from SOP into Job Management, as long as the charge code in SOP matches that in Job Management.

 Press **Enter** to update.

Retention Types



8/JCK

Retention types are specified at job detail level only. They are used in conjunction with stage payments in Job Management to highlight any contractual agreements regarding payments. They are used for memo purposes only.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Retention Types Update Screen



Take the Retention Types option to see the Retention Types Update Screen.

Fields:

Retention Type

Enter the retention type you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Penalty Clauses



9/JCK

Penalty clause codes are specified at job level. They identify those jobs which are subject to penalty clauses. They are used for memo purposes only.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Penalty Clause Update Screen

 Take the Penalty Clause option to see the Penalty Clause Update Screen.

Fields:

Penalty Clause

Enter the penalty clause you wish to add or amend.

 Press **Enter**, and the Description field appears.

Description

Enter or amend the description.

 Press **Enter** to update.

Status Codes



10/JCK

Every job has a status. Two of these are reserved by the system, as they are assigned automatically for its own use:

01 - Job opened.

99 - Job closed.

Each job level initially defaults to a status code of 01 and remains open until set to status 99 (you can close off jobs at any level when you want).

However, you can set up other status codes (called user-defined status codes) to monitor the progress on jobs using your own criteria. You can, for example, set up a completion status and other milestones. Thus a status code 25 could represent '25% Complete', or status 32 'Preliminary Site Visit'.



Note: You must set up status codes for each of the six process codes required by the system.

All user-defined status codes are considered by the system to be open, so you can enter costs and income against any job level as long as it has not been set to status 99.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Status Codes Update Screen



Take the Status Codes option to see the Status Codes Update Screen.

Fields:

Status Code

Enter the status code you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Budget Codes



11/JCK

The system provides for multiple budgets and forecasts at any job level, although if you want a simple set-up you can use one budget code for all jobs, and simply define different figures for each job.

The budget codes and forecasts set up can be used in preparing budgets and forecasts and in reports and enquiries.

You can use the same code for both a forecast and a budget, so a budget or forecast is identified by its code plus its type.

Budget Codes Update Screen



Take the Budget Codes option to see the Budget Codes Update Screen.

Fields:

Budget Code

Enter the three character code for the budget or forecast you wish to set up or amend.

Budget Type

Enter one of the following:

0 - Forecast.

1 - Budget.



Press **Enter** to see the Budget Description field.

Budget Description

Enter the description for the budget or forecast.



Press **Enter** to update.

Transaction Sources



12/JCK

When you create a new Job Management company the system creates transaction source codes. These prefix Job Management transaction numbers, and identify the originating source of transactions logged against a job:

- IM - Inventory movement.
- SC - Standing cost.
- SR - Standing cost reversal.
- JM - Job Management.

If the transaction source is an associated module such as Accounts Payable or Inventory Management, then the transaction source code is the ID of that module (PL for Accounts Payable, IN for Inventory Management).

When a code - the prefix plus the transaction number - arrives in the General Ledger the code J is prefixed, to indicate that the transaction is from Job Management. The transaction source is not removed, but is there after the J.

When transferring the transaction within General Ledger - for example from work in progress to profit and loss - the initial J is kept, but the transaction source is changed:

- IM, JM and PL become RC.
- SC and SR become RS.
- RI - Release of income.



Note: These transaction sources, once in GL, are called transaction types.

You can if you wish define your own transaction source codes for transactions logged within Job Management, although this is generally not required. We strongly recommend that you use JM as the transaction source for direct transactions within Job Management.

Transaction Sources Update Screen



Take the Transaction Sources option to see the Transaction Sources Update Screen.

Fields:

Transaction Source

Enter the code you want to set up or amend.



Press **Enter** to see two more fields.

Source Description

Enter the description of the transaction source code.

Document Reference

Job Management automatically generates a unique transaction number for each transaction. This number increments by one for each transaction.



Press **Enter** to update.

Transaction Types



13/JCK

These are specified at transaction level. Transaction types are used to further identify transactions within a job, in addition to transaction source.

These transactions are defined by you. As a minimum, transaction types must be set up for any employee expenses, timesheet and Inventory transactions.

All timesheets and employee expense sheet functions must have an associated expense type and transaction type. Similarly, Inventory movements must have an associated expense type, transaction type and charge code.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Transaction Types Update Screen



Take the Transaction Types option to see the Transaction Types Update Screen.

Fields:

Manager

Enter the code for the transaction type you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Variation Reason Codes



14/JCK

When you change, at job detail level, a budget, a selling price, or the estimated hours, the system will ask you to enter a variation reason.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Variation Reason Codes Update Screen



Take the Variation Reason Codes option to see the Variation Reason Codes Update Screen.

Fields:

Variation Reason Code

Enter the variation reason code you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Analysis Codes



15/JCK

These are specified at job level. Up to eight analysis codes can be recorded against a job, enabling flexible analysis across jobs. The code is used only for reporting purposes.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Analysis Codes Update Screen



Take the Analysis Codes option to see the Analysis Codes Update Screen.

Fields:

Analysis Code

Enter the analysis code you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Expense Types



16/JCK

All cost transactions entered against a job must have an associated expense type. Expense type transactions typically include materials, labour, accommodation, travel expenses and so on.

The expense types that are relevant for a particular job type are set up within the Job Types parameter option. Each timesheet, employee expenses and Inventory transaction has a default expense type attributed to it.

Costs are analysed at each level by expense type, giving Job Management a very flexible, user-defined method of analysing costs.

Expense Types Update Screen



Take the Expense Types option to see the Expense Types Update Screen.

JM038	Z1 - GB Demonstration Company	USER GBJBATD0	15/10/97 16:36:26
Expense Types Update			
Expense type..... EXP			
Description..... <u>Employee Expenses</u>			
Category..... 3 1=Labour 2=Material 3=Other Direct			
F3=Exit F11=Delete F12=Previous			
7-23 SA MW KS CL IM DM II STUD140 KB PKH317S1			

Fields:

Expense Type

Enter the code for the expense type you wish to set up or amend.

Description

Enter or amend the description.

Category

Enter the category of cost that this expense type is to cover. A different cost to complete method will be applied for expenses depending on the choice you make here.

1 - Labour.

2 - Material.

3 - Other direct.



Press **Enter** to update.

Job Types

1... 17/JCK **2...**

The job type is specified at job level. Job types are used in Job Management to:

- Enable analysis on jobs by like type, for example, software projects, construction, manufacturing contracts and so on.
- Set defaults for credit checking, income deferral and so on.
- Set default text to appear on invoices.
- Identify valid expense types.

You can set up a job type to close a job as soon as its first invoice has been created.

Job Types Update Selection Screen



Take the Job Types option to see the Job Types Update Selection Screen.

Fields:

Job Type

Enter a new or existing job type.



Press **Enter** to see the Job Types Update Screen.

Job Types Update Screen



Press **Enter** on the Job Types Update Selection Screen. The Job Types Update Screen is displayed.

JM046	Z1 - GB Demonstration Company	USER GBJBABL	23/06/97																				
Job Types Update			11:15:34																				
			*Update																				
Job type..... JT1																							
Job type description..... <u>Job Type 1 Rvw/Def</u>																							
Close job after 1st invoice... 0 (1/0)																							
Review invoice..... 0 (1/0)																							
Invoice hours text..... 0 (1/0)																							
Credit check required..... 0 (1/0)																							
Income deferred..... 1 (1/0)																							
Invoicing/Capitalisation..... 3 (1/2/3)																							
<table border="1"> <thead> <tr> <th>Method</th> <th>0</th> <th>1</th> <th>2</th> <th>3</th> <th>4</th> <th>5</th> <th>6</th> <th>7</th> <th>8</th> </tr> </thead> <tbody> <tr> <td>Disable transfer methods (1/0)</td> <td>0</td> <td>0</td> <td>0</td> <td>0</td> <td>0</td> <td>0</td> <td>0</td> <td>0</td> <td>0</td> </tr> </tbody> </table>				Method	0	1	2	3	4	5	6	7	8	Disable transfer methods (1/0)	0	0	0	0	0	0	0	0	0
Method	0	1	2	3	4	5	6	7	8														
Disable transfer methods (1/0)	0	0	0	0	0	0	0	0	0														
F3=Exit F11=Delete F12=Previous F19=Expense types F21=Job type text																							
07-33 S2 MW KS IM II KENB20A PET178S2																							

Fields:

Job Type Description

Enter a description for the job type.

Close Job After 1st Invoice

0 - Automatic close of jobs is not required after the first invoice has been produced.

1 - Job is to be closed automatically once an invoice has been produced. This would be used mostly in consultancy companies, and other T&M businesses, where a job is typically invoiced only once it is complete.



Note: Once the first invoice has been produced at a particular job level, then the job closes and no further invoices can be requested at that level.

Review Invoice

This field provides the default value for the Review field specified at job detail level.

0 - Invoices can be produced without review.

1 - Invoices for this job type are to be reviewed before the invoice is printed.

Invoice Hours Text

0 - The time and material invoice will not include a breakdown of chargeable timesheet details showing hours and rate.

1 - The time and material invoice is to include a line giving a breakdown of chargeable timesheet details showing hours and rate.

Credit Check Required

0 - No warning is given on jobs for customers over the credit limit.

1 - A warning message is shown when you are maintaining a job for a customer who is over the credit limit.

Income Deferred

0 - Income is to be posted directly to profit and loss accounts within General Ledger.

1 - Income from this job type is to be deferred.

Invoicing/Capitalisation

You can enter the following options:

1 - Raise invoices once all job details are closed.

2 - Raise invoices once this particular job detail is closed.

3 - Raise invoices on demand.

Disable Transfer Methods

0 - This transfer method can be used for this job type.

1 - This transfer method cannot be used for this job type.



Press **Enter** to save your job types before selecting any other function.

Functions:

F19

Expense Types. Display all expense types for this job type, enabling amendment. The screen displayed is the Job Type Expense Type Update Screen.

F21

Job Type Text. Display the Job Type External Text Update Screen. Any text entered will be printed on every invoice for jobs of this type.

Job Type Expense Type Update Screen (F19)



Select **F19=Expense Types** on the Job Types Update Screen to see the Job Type Expense Type Update Screen.

This screen enables you to set up or amend the expense types that are associated with this job type.



Tip: When you have entered an expense type and VAT code, you can press **Enter** to see the expense type description.

```

JM076          Z1 Amalgamated Amalgamations PLC  USER GBJBANB1  17/04/96
                                           14:44:25

Job Type Expense Type Update

Job type.... JT1   Job Type 1 Rvw/Def

      Expense          VAT      Mark
      Type?           Code?    Up %

■ CON  External Consultants  S      5.00
- EXP  Employee Expenses    S      .00
- INV  Inventory            S      .00
- LAB  Labour               S     30.00
- MAT  Material             S     10.00
-      -                   -      .00
-      -                   -      .00
-      -                   -      .00
-      -                   -      .00
-      -                   -      .00

4=Delete
F3=Exit  F4=Prompt  F12=Previous

11-02  SF      MW      KS      IM      II  KENB20A  PED149S1
  
```

Fields:

Unnamed (Option)

Option. Enter 4 to delete the line.

Expense Type

Enter a valid expense type.

You must include here the expense types for timesheets and the expense types for expenses (employee) as set up in the company profile. Otherwise, timesheet or employee expenses entries will be prohibited for this job.

VAT Code

Enter a VAT code applicable to this expense on this job type, used when generating invoices on time and material jobs.

Mark Up %

If the expense type is chargeable, you can increase the cost by the mark-up percentage for income.

Each job detail has an income currency. This may or may not differ from the cost currency or base currency of the job number. When you are putting in a mark-up for an expense type for a transaction (timesheets/expenses/direct) with a currency other than the income currency, the mark-up is ignored. Job Management expects the charge value to be entered.



Note: If you want to add more expense types, you must use the Expense Types option.



Press **Enter** to update, then **F12=Previous** to leave the screen.

Job Type External Text Update Screen (F21)



Select **F21=Job Type Text** on the Job Types Update Screen to see the Job Type External Text Update Screen.

JM078	Z1 Amalgamated Amalgamations PLC	USER GBJBANB1	17/04/96
Job Type External Text Update			14:57:32
Job type.... JT1 Job Type 1 Rvw/Def			
External Text			
■	30-day payment discount -		
-	Call 0121-606-2723		
-			
-			
-			
-			
-			
-			
-			
4=Delete			
F3=Exit F12=Previous			
11-02	SP	MW	KS IM II KENB20A PED149S1

Fields:

Unnamed

Option. Enter 4 against a line of text to delete that line. The lines below the deleted line will move up to fill the gap.

External Text

This screen displays the text against the job type. Any text entered here appears on all invoices for jobs of this type.

Page down for more lines of text.



Press **Enter** to update, then select **F12=Previous** to leave the screen.

Employee Grades



18/JCK

Each employee has an employee grade, which specifies that employee's currency and exchange rate.

Employee Grades Update Selection Screen



Take the Employee Grades option to see the Employee Grades Update Selection Screen.

Fields:

Employee Grade Code

Enter a new or existing employee grade.



Press **Enter** to see the Employee Grades Update Screen.

Employee Grades Update Screen



When you have selected the employee grade you wish to maintain, press **Enter** to see the Employee Grades Update Screen.

JM087	Z1 - GB Demonstration Company	USER GBJBATD0	13/10/97
			16:11:43
Employee Grades Update			*Update
Employee grade code..... M1DM			
Grade description..... <u>Manager 1 France</u>			
Currency code.....?.. <u>GBP</u>			
Conversion rate code.?.. <u>CURC</u>			
F3=Exit F4=Prompt F11=Delete F12=Previous			
7-27	SP	MW KS CL IM DM II	STUD140 KB PKH317S1

Fields:

Grade Description

Enter a grade description as required.

Currency Code

The currency code of the grade rate to be entered. These currency codes are set up in the General Ledger.

Conversion Rate Code

Enter the conversion rate for the currency. This must be set up in the General Ledger.



Press **Enter** to update.

Employee Details



19/JCK

You must set up basic data about employees in order to capture timesheet and employee expense details. These details can be altered once set up.

The claim rate and charge rate on this screen are used for company mileage calculations.

Employee Details Update Selection Screen



Take the Employee Details option to see the Employee Details Update Selection Screen.

Fields:

Employee Number

Enter the employee you want to set up or maintain.



Press **Enter** to see the Employee Details Update Screen.

Employee Details Update Screen



When you have selected an employee on the Employee Details Update Selection Screen, press **Enter** to see the Employee Details Update Screen.

```

JM000          Z1 Amalgamated Amalgamations PLC   USER GBJBANB1   17/04/96
                                           15:26:43
Employee Details Update                                *Update

Employee number.....      1

Employee Surname..... Moore
Employee Initials..... RF
Normal Weekly Hours.... 37.50
Employee Grade Code?... GBPG1           grade 1
Profit Centre.....?.. 000002           Central Admin
Location Code.....?.. 20                Cambridge

Claim Rate.....          .005
Charge Rate.....          .350
Vehicle Make.....
Vehicle Registration...
Vehicle cc.....          0
Total Mileage.....        0

-----
F3=Exit  F4=Prompt  F11=Delete  F12=Previous

07-26   SA      MW      KS      IM      II  KENB20A  PED149S1
  
```

Fields:

Employee Surname

Enter the employee's surname.

Employee Initials

Enter the employee's initials (up to four characters).

Normal Weekly Hours

Enter hours per week.

Employee Grade Code

Enter the employee's grade. This sets the currency for the employee. This field is mandatory.

Profit Centre

Enter an existing profit centre. When reconciling timesheets, a timesheet reconciliation report for each profit/cost centre is produced. This field is mandatory.

Location Code

Enter an existing location. This field is mandatory.

Claim Rate

The claim rate is the amount an employee is entitled to claim for business mileage. If this employee is entitled to claim mileage then this field should not be left blank.

The claim rate is held in base currency, even if the employee grade is for a currency other than base. In such cases, a currency value is held, but base is the overriding value.

Charge Rate

The charge rate per hour/mile for invoice purposes. Remember these rates can only be invoiced on chargeable T&M jobs, in the prime currency of the job or sub-job, as specified in the job detail.

Vehicle Make

This field is for memorandum purposes only.

Vehicle Registration

This field is for memorandum purposes only.

Vehicle CC

This field is for memorandum purposes only.

Total Mileage

This field is for memorandum purposes only.



Press **Enter** to save any entries you have made.

Uplift Codes



20/JCK

Uplift codes enable you to increase or decrease labour costs by a percentage.

They are specified on timesheets.

Uplift codes recalculate the cost of labour for an employee in the base currency, using the formula:

uplift code value * no of hours * hourly rate.

Therefore if the uplift code X equals 1.5, then the cost of labour will be multiplied by 1.5 for all timesheet lines with an uplift code of X.

Uplift Codes Update Screen



Take the Uplift Codes option to see the Uplift Codes Update Screen.

JM274	Z1 Amalgamated Amalgamations PLC	USER GBJBANB1	7/05/96 14:09:00
Uplift Codes Update			
Uplift code..... A			
Uplift description... <u>Uplift 1.3</u>			
Uplift rate..... <u>1.3333</u>			
F3=Exit F11=Delete F12=Previous			
07-34		MW	KS IM II KENB20A PET149S2

Fields:

Uplift Code

Enter the uplift code you want to set up or maintain.



Press **Enter** to see two more fields.

Uplift Description

Enter a description for the code. It is a good idea to include the percentage rate in the description.

Uplift Rate

Enter the factor to be used when multiplying the number of hours.



Press **Enter** to save any changes you have made.

Process Codes



21/JCK

Process codes cannot be used unless the Auto Process Codes field is switched on in the company profile.

The following process codes are system defined. Their status codes are selected/set up by you, and you can switch them on and off:

- IVD - Invoiced.
- PDS - Partial despatch.
- RCV - Goods received.
- RTN - Return generated.
- SOC - Sales order created.
- TDS - Total despatch.

Each job detail has a status code, which can be anything from 01 (open) to 99 (closed). This option enables you to change the status code of a job detail automatically, depending on the processing stage it has reached. This option is where you specify the status code to which the job details are to be set when the relevant process is performed.

Process Codes Update Screen



Take the Process Codes option to see the Process Codes Update Screen.

JM303	Z1 Amalgamated Amalgamations PLC	USER GBJBANB1	17/04/96 16:14:55
Process Codes Update			
Process code..... IVD			
Description..... Invoiced			
Status code....?... 10			
Active (0/1)..... 1			
F3=Exit F4=Prompt F11=Delete F12=Previous			
07-21  MW KS IM II KENB20A PED149S1			

Fields:

Process Code

Enter a new or existing process code.



Press **Enter** to see three more fields.

Description

Enter the process code's description.

Status Code

Enter the status code to which the job details are to be set when this process is complete. Do not set this to 99, which is a reserved value meaning closed.

Active

0 - The job detail status will not be changed.

1 - Using this process will automatically change the job detail status.



Press **Enter** to save any entries you have made.

Activity Codes



22/JCK

Activity codes have two main purposes:

- They enable you to attach any number of activities to a job detail, so that you can subsequently report on all job details that, for example, involved a site visit, or all those which have been invoiced.
- You can, if you want, attach an activity code (or more than one) to a stage payment, so that a stage payment is made when an activity is complete, and you will then be able to analyse such payments.



Use this option to set up the activity codes you intend to use, with a description for each one.

Once the codes are set up, you will take the Job Detail Activities option to assign any number of activities to a job detail. Each activity will have a start and completion date entered, and text with it.

From there, you can enter option 3 against an activity to link it to a stage payment, or you can enter the Stage Payments option to link a payment to an activity.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Activity Codes Update Screen



Take the Activity Codes option to see the Activity Codes Update Screen.

Fields:

Activity Code

Enter the activity code you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Cost To Complete Codes



4/JCK

Any job you wish to include in the cost to complete process must have a cost to complete code against it, and these codes are set up here.

If a job has a cost to complete code, then that means it is to be included in the Cost To Complete Initiation option's batch job.

If you have a large number of jobs to process in the Cost to Complete Initiation option, then this batch job could be a big job. To split the processing into two, three or more batches, simply set up two, three or more cost to complete codes, and assign different ones to different jobs. You can then choose to process only those jobs of a certain code.



Tip: Some parameters are mandatory entry. If you do not wish to use these, then you can set up a blank code here. This will make a blank code a valid entry for the parameter.

Cost To Complete Codes Update Screen



Take the Cost To Complete Codes option to see the Cost To Complete Codes Update Screen.

Fields:

Cost To Complete Code

Enter the cost to complete code you wish to add or amend.



Press **Enter**, and the Description field appears.

Description

Enter or amend the description.



Press **Enter** to update.

Parameter Enquiries



Each parameter has a corresponding enquiry.
Take the relevant option, enter the code you wish to enquire on, and press **Enter** to see the details displayed.

Parameter Reports



Each parameter has a corresponding report. Take the relevant option, and a window tells you to press **F8=Submit** to submit a job to produce a report of all existing codes for the selected parameter.