

-
-
-
-
-

Chapter 2

Fixed Assets Processing



Job Management and Fixed Assets

When you use the Fixed Assets module with Job Management, you can use costs captured for a job detail to create a fixed asset.



Tip: In order to use the Fixed Assets interface you must have the advanced edition of Fixed Assets installed.

If a project using Job Management involves the construction or assembly of fixed assets, you can transfer the asset from Job Management to Fixed Assets via Job Management. All costs are initially posted to a work in progress General Ledger account.

Job Management Company Profile

The following fields on the company profile are related to fixed assets:

- Fixed Assets Active
- Parent/Child Relationship
- Summarise GL Postings
- Fixed Asset Suspense Account
- Default Write Off Account

Job Details with Transfer Methods 4, 5, 6 & 8

The essential setting if you want to create an asset from a job number is the transfer method. This is set up for each job detail, on the Job Details Maintenance Screen 2.

Valid transfer methods range from 0 to 8. Transfer methods 4, 5 and 6 are for jobs which are totally capital-orientated, i.e. which involve the creation of fixed assets with capitalised values based on costs entered against jobs.

Transfer method 8 allows for costs on a job detail to be a combination of capital and revenue expenditure.

One job detail is usually associated with only one asset, but special conditions apply for serial controlled Inventory item costs. Any asset number can be associated with any number of job details.

If you enter a transfer method of 4, 5 or 6, a Fixed Asset Details Window appears. Remember to set up your asset groups before you take this option. You cannot validate the window without entering a valid asset group.

Transfer from WIP to Fixed Assets

You can transfer costs from WIP to Fixed Assets for job details with a transfer method of 4, 5, 6 or 8. The following options process the transfer:

- Release Automatic Transfers
- Transfer Validation
- Confirm Transfer

Follow the above sequence when you are releasing the costs to Fixed Assets. A message warns you if you take an option out of sequence. A Restart Transfer option enables you to restart the transfer process. The Fixed Assets interface must be active.

Release Automatic Transfers



1/JCE

This option is one of the four options concerned with transferring assets to Fixed Assets. The others are:

- Validate Transfer
- Confirm Transfer
- Restart Transfer

This option releases all cost transactions for job details that have a transfer method of 4, ready for capitalisation. The purpose of this option is to prepare the costs for transfer to Fixed Assets.

Once you have run this option, you must run either Confirm Transfer or Restart Transfer before you can run it again.



Take the Release Automatic Transfers option.
Use **F8** to proceed with the batch process.



Note: This option will not release any cost which was posted to a GL period that is ahead of the current Fixed Assets period.

Validate Transfer



2/JCE

This option concerns transfer methods 4, 5 and 6, and is one of the four options concerned with transferring assets to Fixed Assets. The others are:

- Release Automatic Transfers
- Confirm Transfer
- Restart Transfer

This option checks for errors, and reports on assets which are to be maintained or created.

Once you have run this option, you must run either Confirm Transfer or Restart Transfer before you can run it again.

Transfer From WIP To Fixed Assets Screen



Take the Validate Transfer option to see the Transfer From WIP To Fixed Assets Screen.

JM216	Z1 Amalgamated Amalgamations PLC	USER GBJBANB1	14/05/96
Transfer From WIP To Fixed Assets			13:53:55
Choose which transfer method you wish to transfer :-			
		Start Capitalisation	Start Depreciation
		Date	Date
		Period	Period
4. (Periodic transfer).....	0 (0/1)	0/00/00	0/00/00
5. (Transfer on request).....	0 (0/1)	0/00/00	0/00/00
6. (Transfer on completion)...	0 (0/1)	0/00/00	0/00/00
F3=Exit F8=Confirm request			
10-33	SP	MK	KS IM II KENB20A PET149S2

Fields:

Unnamed

Select transfer methods.

Enter 1 against the transfer methods you wish to select.

All job details with the selected method(s) will have their costs transferred.

Start Capitalisation Date/Period

Enter as required. The system will check that the date and/or period is in the currency year.

Start Depreciation Date/Period

Enter as required. The system will check that the date and/or period is in the currency year.



Select **F8=Confirm Request** to submit a batch job to perform the validation.

Three reports are produced:

- Asset Creation Report - This lists every asset that has been created.
- Asset Posting Report - This lists the costs being posted to Fixed Assets.
- Exception Report - This reports on any errors which arose during the creation or amendment of fixed assets. Transactions which have such errors are not transferred.

Confirm Transfer



3/JCE

This option affects transfer methods 4, 5 and 6, and is one of the four options concerned with transferring assets to Fixed Assets. The others are:

- Release Automatic Transfers
- Validate Transfer
- Restart Transfer

Released transactions must be validated (using the Validate Transfer option) before posting them to the General Ledger and Fixed Assets via this option. The following processes take place:

- General Ledger posting
- Fixed Asset update
- Summary report produced



Take the Confirm Transfer option, and select **F8=Confirm Submit** to submit the batch job.

General Ledger Posting

- A. Credit the WIP account of the original debit, and debit the Fixed Asset suspense account held on the company profile.
- B. Credit the GL account specified in the credit mask of the cost book, in Fixed Assets. It is recommended that you set this to be the same value as the Fixed Asset suspense account. This will use activity level 090. Debit as per the debit mask of cost book in Fixed Assets. This will use activity level 090.



Note: Part B will not occur for a reversible, or reversing, standing cost.

In terms of GL data, the following will occur

- The GL period posted to will be the current FA period.
- The GL transaction type will be RC.
- There will be a GL session for each job header level (not sub-job, task) for the initial postings to Fixed Assets suspense account (in A above). There will be a further GL session for each asset created, subsequent to the suspense account (in B above).
- The system will post either detail or summary postings by asset according to the setting of the company profile.



Note: The activity level 090 is automatically created as an ACTY reference code when you create your Job Management company. The ACTY reference code is the standard General Ledger account types.

Fixed Asset Update - New Asset

The actual update of Fixed Assets depends upon whether the asset already exists or not.

If the asset does not exist, then it will be created with the following data in Fixed Assets:

Data Field	Source
Asset number	Job details
Document date	System date
Period	Current period (FA company profile)
Reason	Job detail
Description (reason)	Description of reason code from job detail.
Description (asset)	Description of the job detail whose capitalised costs initially created the asset.
Parent asset	If the parent/child relationship on company profile is set to 0, this is blank. If set to 1, this is the asset number of the job details parent. So, if the job detail has a task value, then, this is the asset number of the job/sub-job
Reference	The job, sub-job and task (separated by a blank) of the job detail whose capitalised costs initially created the asset.
Model	This contains the Inventory item number if multiple assets are being created (see the section on Job Maintenance).
Serial number	Serial number of Inventory item, if applicable.
Quantity	The accumulation of all quantities of transactions relating to this asset. This will be meaningful only if the transactions are all of a similar nature.

Location	The description of the job detail location.
Date acquired	Capitalisation start date (from the selection screen), or current date (if earlier).
Date commissioned	As date acquired

Analysis Types

The analysis types and codes will be created for an asset according to the rules laid out in the analysis type mapping file.

Financial Details

Data Field	Source
Cost book	Asset group associated with job detail
Asset cost	Transaction cost (base value)
Capitalisation date/period	Selection screen
Life (periods)	From job detail, if data recorded there, else from asset group associated with job detail
Retirement period	Calculated from Life.
Replacement value	Same as asset cost
Valuation date	Current date
Disposal date	Zero

Depreciation Book Data

This data is held for each depreciation book held against the asset group associated with the job detail.

Data Field	Source
Depreciation book	Asset group associated with job detail
Depreciation flag	1 (yes)
Book value	Same as total asset cost

Max. per period	Same as total asset cost
Start date/period	Selection screen
Depreciation method	Asset group associated with job detail
Depreciation rate	Asset group associated with job detail
Depreciation life	Asset group associated with job detail

Fixed Asset Update - Existing Asset

The actual update of Fixed Assets depends upon whether the asset already exists or not.

If the asset does exist, then it will be created with the following data in Fixed Assets:

Base Details

Data Field	Source
Quantity	The transaction quantity is added to the existing asset quantity
Analysis types	No update takes place

Financial Details

Data Field	Source
Asset cost	The transaction cost (base value) will be added to the existing asset transaction cost
Replacement	The transaction cost (base value) will be added to the existing replacement value

Depreciation Book Data

This data is held for each depreciation book held against the asset group associated with the job detail.

Data Field	Source
Maximum per period	The transaction cost (base value) is added to the existing maximum per period

Restart Transfer



4/JCE

This option affects transfer methods 4, 5 and 6, and is one of the four options concerned with transferring assets to Fixed Assets. The others are:

- Release Automatic Transfers
- Validate Transfer
- Confirm Transfer

This option enables you to restart the Fixed Asset interface process. It resets the transactions back to before the Validate Transfer option was run, and optionally to before Release Automatic Transfers was run. These options must be run again.



Take the Restart Transfer option.

Asset Groups



11/JCE

If you are using the Fixed Asset interface, then there are two primary areas of additional maintenance in Job Management. The first of these is the maintenance of asset groups, and the second is Analysis Type Mapping.

This option enables you to record Fixed Assets data that needs to be held against more than one job detail.

Asset Groups Update Screen



Take the Asset Groups option, enter a new or existing asset group, and press **Enter** to see the Asset Groups Update Screen.

```

JM202                Z1 Amalgamated Amalgamations PLC    USER GBJBANB1    7/05/96
                                           15:35:20
Asset Groups Update                                     *UPDATE*

Asset group..... ASGRP1

Asset group description..... ASSET GROUP 01
Cost book.....?.. CST    Cost Book

Depreciation Data :-
Book?                               Method?          Rate          Life (Prds)
DEV    Depreciate                   001             10.00          ____
____                                     ____             ____          ____
____                                     ____             ____          ____
____                                     ____             ____          ____
____                                     ____             ____          ____
____                                     ____             ____          ____
____                                     ____             ____          ____
____                                     ____             ____          ____
____                                     ____             ____          ____
____                                     ____             ____          ____

F3=Exit  F4=Prompt  F11=Delete  F12=Previous

12-02    S2      MW      KS      IM      II  KENB20A  PET149S2
  
```

Fields:

Asset Group Description

Enter the description.

Cost Book

This book is a Fixed Asset book. The book is used to generate General Ledger asset cost accounts. Without a cost book, values are not posted to the General Ledger.

Book

Financial control of the company's assets is exercised via depreciation books. Advanced Fixed Assets enables the use of multiple depreciation books. Like the cost book, the depreciation book is maintained within Fixed Assets. At least one depreciation book must be entered per asset group.

Method

You must enter a depreciation method for each depreciation book. Job Management uses the standard Fixed Assets rules for depreciation methods.

Rate

You must enter a depreciation rate in the form of a percentage, unless the depreciation method is 004, which depreciates in equal amounts over the asset life. Leave this field blank if you are using depreciation method 004.

Life

Leave blank unless depreciation method is 004.

If depreciation method is 004 then enter the life value in periods.



Press **Enter** to validate any additions or amendments.

Analysis Type Mapping



12/JCE

This option automatically creates analysis codes in Fixed Assets for the required analysis types. This is achieved by mapping Job Management data, i.e. job details, the job header, transactions, customer details, and Inventory item details, into Fixed Assets.

Job Management-related assets can then be analysed in Fixed Assets, according to the parameters of Job Management.



Tip: This is similar to the way in which Job Management and the Advanced Financial Integrator build masks to translate one code into another.



These analysis codes for the Fixed Assets interface are not in any way related to the analysis codes which can be set up in Job Management via the Analysis Codes option. These Fixed Asset codes are set up within Fixed Assets, using the System Reference Codes option, under the reference code ANTY.

Analysis Type Mapping Screen 1



Take the Analysis Type Mapping option to see a list of existing codes on the first Analysis Type Mapping Screen.

JM208		Z1 - GB Demonstration Company		USER GBJBABL		19/06/97 11:12:51	
Analysis Type Mapping							
Tests : EQ NE LT GT RANGE SST							
Analysis JM							
Type Code ?	Field?	Test	Value 1	Value 2	More (0/1)		
ATP T&M	?AC122	RANGE	A	9	0		
CLM					0		
COS ADMIN	SAC222	RANGE	A	9	0		
LOC BHAM	PFCT23	RANGE	000001	000001	0		

F3=Exit F4=Prompt F8=Update

01-78 **S2** MW KS IM II KENB20A PET178S2

Fields:

When first used, the screen displays one line for each analysis type defined to Fixed Assets.

You must then identify, for each analysis type, how the interface will create the Fixed Asset analysis code for each analysis type. This can be done via a number of methods. These are as follows.

Where the analysis code is a known value:

Analysis Code

Enter the known value.

JM Field

Not used.

Test

Not used.

Value 1

Not used.

Value 2

Not used.

More

1 - See more details. This brings up the second Analysis Type Mapping Screen.
If a line already has more details entered against it, it has an asterisk.

Where the analysis code is the same as the value of a known job detail field:

Analysis Code

Not used.

JM Field

The job header/detail field whose value is to be put into the analysis code.

Test

Not used.

Value 1

Not used.

Value 2

Not used.

More

1 - See more details. This brings up the second Analysis Type Mapping Screen.
If a line already has more details entered against it, it has an asterisk.

Where the analysis code is the same as part of the value of a known job detail field:

Analysis Code

Not used.

JM Field

The job header/detail field, part of whose value is to be put into the analysis code.

Test

SST (sub-string).

Value 1

The starting position of the required data.

If data entered in either Value 1 or 2 is greater than the field length of the chosen JM field, then the extra data characters will be ignored.

Value 1 cannot be greater than length of the data field.

The combination of Value 1 and 2 must not mean that the extracted data is outside of the fields limits.

Therefore, if Value 1 (start at) is 2 and Value 2 (length) is 6 then this cannot be validated for JM field JMNO since the JMNO is only 6 characters long.

If range is entered, Value 2 cannot be less than Value 1.

Value 2

The length of the required data.

If data entered in either Value 1 or 2 is greater than the field length of the chosen JM field, then the extra data characters will be ignored.

Value 1 cannot be greater than length of the data field

The combination of Value 1 and 2 must not mean that the extracted data is outside of the fields limits.

Therefore, if Value 1 (start at) is 2 and Value 2 (length) is 6 then this cannot be validated for JM field JMNO since the JMNO is only 6 characters long.

If range is entered, Value 2 cannot be less than Value 1.

More

1 - See more details. This brings up the second Analysis Type Mapping Screen.

If a line already has more details entered against it, it has an asterisk.

Where the analysis code is dependant upon the value of a job detail field:

Analysis Code

Enter the known value that is dependant on a particular JM field value.

JM Field

The job header/detail field whose value needs checking

Test

EQ (equal), NE (not equal), LT (less than), GT (greater than), RANGE.

Value 1

This must be entered for all tests. If Range is being used, this is the beginning of the value range.

If data entered in either Value 1 or 2 is greater than the field length of the chosen JM field, then the extra data characters will be ignored.

Value 2

If Range is being used, this is the end of the value range, otherwise leave blank.

If data entered in either Value 1 or 2 is greater than the field length of the chosen JM field, then the extra data characters will be ignored.

More

1 - See more details. This brings up the second Analysis Type Mapping Screen.

If a line already has more details entered against it, it has an asterisk.



If the mapping is achieved by testing for certain Job Management data values, then it follows that more than one is needed for that particular analysis type. In this instance, enter 1 into the More field at the right end of the screen line. This gives the second Analysis Type Mapping Screen.

Valid Entries For The JM Field

The job header/details fields that are available for mapping from are the following
:

ACMG - Account manager (4 characters)
ASGP - Asset group (6 characters)
CUSD - Customer code (job detail) (8 characters)
CUSH - Customer code (job header) (8 characters)
DIVN - Division (2 characters)
IDCD - Industry code (5 characters)
JBTP - Job type (3 characters)
JMNO - Job number (6 characters)
LOCN - Location (2 characters)
MAJC - Major contract (6 characters)
PRCT - Profit centre (6 characters)
PJMG - Project manager (4 characters)
PNCL - Penalty clause (3 characters)
PRTP - Price type (1 character)
RCOD - Retention code (2 characters)
REGN - Region (3 characters)
SAC1 - Secondary analysis code 1 (2 characters)
SAC2 - Secondary analysis code 2 (2 characters)
SAC3 - Secondary analysis code 3 (2 characters)
SAC4 - Secondary analysis code 4 (2 characters)
SAC5 - Secondary analysis code 5 (2 characters)
SAC6 - Secondary analysis code 6 (2 characters)
SAC7 - Secondary analysis code 7 (2 characters)
SAC8 - Secondary analysis code 8 (2 characters)
SJBN - Sub-job (4 characters)
STTS - Status (2 characters)
TRFM - Transfer method (1 character)
TSKN - Task (3 characters)

turn, in the sequence specified, and will take the first test which is successful.



Select **F8=Update** and you return to the first Analysis Type Mapping Screen. A + sign against a line indicates that more details are available by entering 1 in the More field.

Make sure you select **F8=Update** from the first Analysis Type Mapping Screen too - do not select **F3=Exit** or your updates will be lost.

Job Enquiry by Asset Number



21/JCE

Use this enquiry to identify all job details that are associated with a particular asset number.

Job Enquiry By Asset Number Screen

 Take the Job Enquiry By Asset Number option and enter the asset you wish to enquire on. You will see the Job Enquiry By Asset Number Screen.

JM212Z1 Amalgamated Amalgamations PLCUSER GBJBANB128/06/9617:45:25

Job Enquiry By Asset Number

Asset number..... A123456

Job/Sub-Job/Task	Description	Capitalised This Level
NEWONE FAR	far test	1000.00

S=Financial details

F3=Exit F12=Previous

00-02



MW

KS

IM

II

KENB20A

PET149S2

Fields:

Untitled

Selection field. Enter 5 against a job/sub-job/task to display the Financial Details Screen, as found in the Main Job Enquiry option.