

-
-
-
-
-

Chapter 2

Processing



Create Load Schedule



1/TPP

The Create Load Schedule option is similar to the Create Pending Loads option. However you can use a single batch job to create many loads based on skeleton loads. The batch job copies across the skeleton load header information and associated text.

Create Load Schedule Date Screen

 Select Create Load Schedule.

Use this screen to enter the ship date for the load you are creating.

TP480A	Z1 - Demonstration Company	User: SP1	9/03/95
	Demonstration Transport Centre		12:49:50
Create Load Schedule			
Ship date..... <u>9/03/95</u>			
F3=Exit			

Fields:

Ship Date

Enter the planned ship date for the given load. The ship date defaults to today's date plus the planner's time fence days.

 Press **Enter** to display the Create Load Schedule Details Screen.

Create Load Schedule Details Screen



To display this screen, on the Create Load Schedule Date Screen, enter a date and press **Enter**.

Use this screen to create a load schedule for the ship date, based on a specified skeleton load.

TP480B	Z1 - Demonstration Company Demonstration Transport Centre	User SP1	9/03/95 12:49:59
Create Load Schedule			
Ship date.....		9/03/95	
Based on Load (?)	Route	Route description	
A1	BHAM	Birmingham Route	
A2	YORKS1	Yorkshire Route 1	
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

Based On Load

Enter the skeleton load number to use as a base for creating a new load number.

The batch program copies the load header information together with any associated text.

If the based on load is a master load, then this also creates the sub-loads associated with it.



Note: You must select a route before you can select a skeleton load. If there is only one skeleton load for the route, the system by-passes the load selection and displays the load reference.



To build the load, select **F8=Submit**.

Build Loads



2/TPP

Use the build loads option to review outstanding order requirements for various selection criteria. You can amend transport order and despatch note or drop requirements. These include accumulated order requirements for a given customer, so you can assign requirements to specific loads.

You can switch between the review of all orders associated with a delivery point drop and the summarised drop requirement for the delivery point.

You can control the number of requirements presented via a range of ship dates together with one of the following criteria:

- Route or drop range.
- Particular carrier.
- Origin and optionally destination.

Build Loads Detail

Orders with special instructions display a flashing asterisk. These orders normally have external text recorded against them.

If a customer requires delivery confirmation, a flashing asterisk displays against the customer delivery point code and customer name. You can set the flag to highlight specific delivery time slots and planner text assigned to the delivery point (usually to indicate fixed delivery requirements).

Transport Planning calculates the gross weight, to add to the load, by accumulating all lines with a 1. It assumes that you are building one load at a time.

Build Loads Selection Screen



Select Build Loads.

Use this screen to enter the selection criteria for the loads you want to build.

TP420A	Z1 - Demonstration Company	User SP1	9/03/95
	Demonstration Transport Centre		12:59:06
Build Loads			
Ship date..... 9/03/95 to 9/03/95			
Route from.....?.. _____			
Drop..... _____			
Route to.....?.. _____			
Drop..... _____			
OR			
Carrier.....?.. _____			
OR			
Origin.....?.. _____			
Destination.....?.. _____			
Summary/detail..... 1 (1=Drops,2=Orders)			
Preselect drops..... 1 (0=No,1=Yes,2=Amend)			
F3=Exit F4=Prompt			

Fields:

Ship Date

Enter the range of ship dates for which you want to review orders. The ship dates default to today's date plus the planner's time fence days for planning.

Route From / Route To

Enter the range of routes for which you want to review orders.

Drop

Enter the range of drops, within the specified route, for which you want to review orders.

Carrier

Enter the carrier for which you want to review orders.

Origin

Enter the origin or start point for which you want to review orders. You must have defined the origin as a transport node.

Destination

Enter the destination or end point for which you want to review orders. You must have defined the destination as a transport node.



Note: You only need to enter either a route and drop range, or a carrier, or an origin and

destination.

Summary / Detail

Enter one of the following:

- 1 - To summarise transport requirements by drop for a particular delivery point.
- 2 - To detail transport requirements by order or despatch note number for a particular delivery point.

Preselect Drops

Enter one of the following:

- 0 - If you want no preselection of details.
- 1 - To select order transport details or drops to place on a suggested load. On the Build Loads Detail Screen, all the displayed lines are pre-selected with a 1.
- 2 - To select order transport details or drops to amend the route, drop or suggested load. On the Build Loads Detail Screen, all the displayed lines are pre-selected with 2.



Enter the required selection details, and press
Enter to display the Build Loads Details Screen.

Build Loads Details Screen



To display this screen, on the Build Loads Selection Screen, enter the required selection details and press **Enter**.

Use this screen to select or amend the load details. The details display by order or drop and weight or volume. You can change the information displayed by selecting either **F14=Orders/Drops** or **F15=Volume/Weight**.



Note: The appearance of this screen varies depending upon the selection criteria you entered on the previous screen.

TP420B	Z1 - Demonstration Company		User SP1	9/03/95
	Demonstration Transport Centre			12:59:22
Build Loads - Drop/Weight				
			Total weight	48.1
Ship date	Ship time	Route	Drop Gross weight	Containers Suggested load
S Customer			Vehicle type	
1 9/03/95	16:00	YORKS1	010	48.1 1.0 A4
Reeves Chemist's				38T
1=Select 2=Amend 3=Load details 4=Delivery profile enquiry				
F3=Exit F5=Refresh F8=Update F12=Previous F24=More keys				

Fields:

S

Select. Enter one of the following:

- 1 - To add the order or drop to the suggested load.
- 2 - To transfer the order or drop to another load, or split it across multiple loads.
- 3 - To display the Load Details Enquiry for the suggested load.
- 4 - To display the Delivery Profile Enquiry for the customer delivery point.
- 5 - To display the Sales Order Details Enquiry. For more information, see the Order Entry Product Information.



Note: Option 5 is only available if you are displaying the selection criteria by order.

Functions:

F13

Create Load. Use this function to create new loads. For more information, see Create Loads.

F14

Orders / Drops. Use this function to toggle between order and drop information for customers.

F15

Volume / Weight. Use this function to toggle between volume and weight capacities for the transport requirements.

F16

Pending loads. Use this function to display the pending load's headers that conform to the entered selection criteria; for example, ship date, route, carrier or origin and destination.



To add the selected orders or drops to the load, select **F8=Update**. Then select **F3=Exit**.

Amend Drop Requirement Window (Option 2)



To display this window, with the Drop details displayed on the Build Loads Details Screen, enter 2 alongside a drop.

Use this window to amend drop information, such as route, drop sequence or load.



Note: This amends all order requirements associated with the drop.

TP420B		Z1 - Demonstration Company		User SP1		9/03/95	
		Demonstration Transport Centre				13:11:33	
Build Loads - Drop/Weight							
				Total weight		48.1	
Ship date	Ship time	Route	Drop	Gross weight	Containers	Suggested Load	
S Customer							
2 9/03/95	16:00	YORKS1	010	48.1	1.0	M	
Reeves Chemist's				38T			
Amend drop requirement							
Customer..... GC01 / 000							
Reeves Chemist's							
From							
Route..... YORKS1 Yorkshire Route 1							
Drop..... 010							
Load..... A4							
To							
Route.....?.. YORKS1 Yorkshire Route 1							
Drop..... 010							
Load.....							
1=Select F3=Exit F4=Prompt F5=Refresh F8=Update F12=Previous F24=More keys							

Fields:

Route To

Enter the route to move the drop onto.

Drop To

Enter the drop sequence assigned to the customer delivery point for the entered route.

Load Number To

Enter the load number to assign to the drop details. If this field is blank, Transport Planning checks all pending loads, for this route, on this date. If Transport Planning only finds one load, it displays the number. If it finds many loads, select a load from the displayed window.



Note: If the drop is no longer outstanding, you cannot make any more amendments.

Functions:

F16

Pending loads. Use this function to display the loads that conform to selection criteria such as ship dates, route entered (all routes if blank), and all carriers.



To save the information and return to the previous screen, select **F8=Update**.

Amend Transport Requirements Window



To display this window, with the order details displayed on the Build Loads Details Screen, enter 2 alongside an order.

Use this to amend order information such as route, drop sequence or load.



Note: This also amends the drop record, detailing total requirements at a delivery point. You cannot amend the weight, volume and container details until you have created the picking note.

TP420B	Z1 - Demonstration Company		User SP1	9/03/95
	Demonstration Transport Centre			13:11:55
Build Loads - Order/Weight				
Ship date	Ship time	Route	Drop	Gross weight
S Customer	9/03/95	16:00	YORKS1	010
2 Reeves Chemist's				
				Total weight
				48.1
				Containers
				1.0
				Order number
				0000122
				Priority
				50
				Suggested load
				A4
				Stockroom
				01

Amend transport requirements

Order number..... 0000122

Stockroom..... 01 Central Stockroom

Route.....?.. YORKS1 Yorkshire Route 1

Drop..... 010

Load number..... A4

Gross weight..... 48.1

Net weight..... 47.0

Tare weight..... 1.1

Volume..... 60.0

Containers..... 1.0

1=Select
F3=Exit F4=Prompt F5=Refresh F8=Update F12=Previous F24=More keys

Fields:

Route

Enter the route for the order.

Drop

Enter the drop sequence assigned to the customer delivery point.

Load

Enter the load number for the order requirements.

Gross Weight

Enter the gross weight for the order requirement.

Net Weight

Enter the total weight of the actual goods for the order.

Tare Weight

Enter the total weight of the containers.



Note: Gross weight must always equal the sum of net and tare weight.

Volume

Enter the total volume for the order requirement.

Containers

Enter the total number of containers for the order requirement.

Functions:

F14

Lines. Use this function to display the order lines.

F16

Pending loads. Use this function to display the pending loads headers that conform to the selection criteria; for example, ship dates, route entered (all routes if blank), and all carriers.



To save the details and return to the previous screen, select **F8=Update**.



Note: Transport Planning refreshes order requirements to the latest detail. If the order is no longer outstanding you cannot make any more amendments.

Maintain Loads



3/TPP

Use this option to maintain loads once you have processed them using the Build Loads option or loads automatically processed by the system.

You can:

- Review load header, drop and order information.
- Move drop, order and order line details onto new loads or new routes or both.
- Amend order capacities (weight, volume or number of containers).
- Record consignee name and address details and external text.
- Release the load and print the documentation.

You can control the loads presented by ship date and one of the following criteria:

- Route
- Particular carrier
- Origin or destination
- Particular load.

To maintain a load, the status must be pending, not released for printing of transport documentation. If you select a load at a more advanced state, you cannot change any details. If you want to amend this load, use **F13** to return the load to pending.

Maintain Load Selection Screen



Select Maintain Loads.

Use this screen to select the load you want to maintain.

TP430	Z1 - Demonstration Company Demonstration Transport Centre	User SP1	9/03/95 13:38:41
Maintain Load			
Ship date		<u>9/03/95</u>	
Route		?.. _____	
OR			
Carrier		?.. _____	
OR			
Origin		?.. _____	
OR			
Destination		?.. _____	
OR			
Load number		<u>A4</u>	
F3=Exit F4=Prompt			

Fields:

Route

Enter the route for which you want to review loads.

Carrier

Enter the carrier for which you want to review loads.

Origin

Enter the origin or start point for which you want to review loads.

Destination

Enter the destination or end point for which you want to review loads.

Load Number

Enter the number of the load you want to maintain.



Tip: Press **Enter** to display all loads that match the selection criteria. Select the load you require and press **Enter** again. If only one load conforms to the selection criteria, this load reference automatically displays on the selection screen.



To display the details, make sure there is a Load number displayed, and press **Enter**.

Maintain Load Detail Screen



To display the Maintain Load Details Screen, on the Maintain Load Selection Screen, make sure there is a Load number displayed, and press **Enter**.

Use this screen to enter all the details for the selected load.



*Note: If you have released the load, using **F13=Release**, you cannot change any details on this screen.*

TP430B	Z1 - Demonstration Company	User SP1	9/03/95
	Demonstration Transport Centre		13:38:47
Maintain Load			
Load number	A4	Load status	Pending
Master load		Consolidation Load ..	
Master drop		Master Area	?
Ship date	9/03/95	Ship time	16:00
Route	YORKS1	Yorkshire Route 1	
Carrier	OWN	Demonstration Fleet	
Vehicle type	38T	38 Tonne Artic	
Origin	TCOT	Destination	YORKS
Vehicle		Seal number	
Driver		Crew	
Temperatures		Skeleton load	0
Agent contact ...			
Exclusive load ..	0	Payment method ..?	01
Confirmation	0	P & L override ..?	
Bill required ...	0	Rating status	0 0
Bill format ..?		Rate method	
Copies	1	Rate code	
F3=Exit F4=Prompt F5=Refresh F8=Update F24=More keys			

Fields:

Master Load

If this load is a sub-load, enter the load number of the master load.

The system accumulates the capacity requirements of the master load by summing those of its sub-loads and bases the master load rate on accumulated capacity, plus any drops defined directly to the master load. The master load normally has no drops associated with it.

When you are maintaining a master load, Master Load displays at the top of the screen. When you release a master load, it automatically releases the sub-loads. When you print the transport documentation for the master load, it automatically prints those for the sub-loads. Each sub-load prints on the master load documentation. You should only release a master load when you have built all the sub-loads and you have confirmed as despatched all the associated orders.

You can enter up to ten levels of master load. A sub-load can be a master load in its own right. You should release master loads from the lowest level upwards.



Note: If you are maintaining a skeleton load, the master load must also be a skeleton.



Note: The master load must be at a status of pending to assign the current load as a sub-load



Note: If you rate the master load and return the current load to a status of pending, then you should reprint and rerate the master load (when applicable) to reflect any amendments made to this sub-load.



Note: You cannot link a load to both a master load and a consolidation load. A master load cannot be a consolidation load.

Master Drop

Enter a drop number for the sub load. You must enter this if you specify a master load. It sequences the sub-loads when you display or print the master load and groups sub-loads when you rate the master load.

Master Area

Enter the area to drop the sub-load. You must enter a value if you want to rate a master by area.

Consolidation Load

Enter an existing load number. The current load automatically becomes a secondary load to the specified consolidation load.

Transport Planning uses this to calculate a consolidated rate based on the total weight, volume or number of containers. It then automatically apportions the calculated rate value over the primary and all secondary loads based on their relative weight, volume or number of containers.

When you maintain the primary load, consolidated load displays at the top of the screen. The consolidation load can be any of the loads grouped together for rating. It has no significance other than as a common reference for the group. Consolidation normally applies where you carry a number of loads together on a single vehicle, possibly in separate compartments, with the carrier charging for a single load.



Note: The consolidation (primary) load must be at a status of pending for you to assign the current load as a secondary load.



Note: If you have rated the consolidated loads and return any to a status of pending, then Transport Planning suggests they are rerated.



Note: You cannot link a consolidation (primary) load to another consolidation load.



Note: All consolidated loads must have the same carrier, rating method and rate code.



Note: You cannot link a load to both a master load and a consolidation load.

Ship Date

Enter the required ship or despatch date for the load.

Ship Time

Enter the ship time for the load.

Route

Enter the route assigned to the load.

Carrier

Enter the internal or external carrier assigned to the load.

Vehicle Type

Enter the type of vehicle to use for the load.

Origin

Enter the start point for the load. You must have defined the origin as transport nodes or geographical location.

Destination

Enter the end point for the load. You must have defined the destination as a transport node or geographical location.

Vehicle

Enter the vehicle for the load.

Seal Number

Enter the seal number for the load. Use this for security tagging. It prints on the bill of lading documentation.

Driver

Enter the driver for the load.

Crew

Enter the second driver or driver's mate, for the load.

Temperatures

Enter the temperatures required for the load.

If you enter a single temperature, the fixed temperature message, defined to the transport centre, prints on the bill of lading.

If you enter two temperatures, the temperature range message, defined to the transport centre, prints on the bill of lading.

Skeleton Load

Enter one of the following:

0 - If this load is not a skeleton load.

1 - If this load is a skeleton load. Skeleton loads contain the base load information you use to create pending loads or load schedules.

Agent contact

Enter the contact name at the carrier.

Exclusive Load

Enter one of the following:

- 0 - If the load contains more than one customer's requirements.
- 1 - If this load consists of requirements for a single customer delivery point (based on its eight character account code and three character delivery sequence).

Payment Method

Enter the payment method for this load.

Confirmation

Enter one of the following:

- 0 - If you do not need to confirm the delivery time.
- 1 - If you need to confirm the delivery time with the customer.
- 2 - If you have confirmed the delivery time with the customer.

P & L Override

Enter the Profit and Loss Account Number for this load. You use this, in conjunction with the Advanced Financial Integrator, to post transport costs to the General Ledger.

Bill Required

Enter one of the following:

- 0 - If you only require a load sheet.
- 1 - If you require the bill of lading and a load sheet.

Rating Status

Enter one of the following:

- 0 - If load rating is not required.
- 1 - To automatically rate the load.
- 2 - To manually rate the load.
- 3 - If you have rated the load.

Bill Format

Enter one of the following:

- 01 - One document per load. The capacity totals are from the load header and the despatch notes are per load.
- 02 - One document per drop or delivery point on route. The capacity totals are per drop or delivery point and the despatch notes are per drop or delivery point.
- 03 - One document per load. The capacity totals are from the load header with one totals line per drop. The despatch notes are for each drop or delivery point.
- 04 - One document per load. The capacity totals are per area and for the load. The despatch notes are for the load.

You use the Inventory descriptions file, major type of TPBL to support and maintain these formats.

Rate Method

Enter one of the following:

01 - To calculate charges, based on the loads gross weight, volume or number of containers, using a rating table.

02 - To calculate charges for each drop, based on the gross weight, volume or number of containers, using a rating table.

03 - To calculate charges using a fixed rate, based on the gross weight, volume or number of containers dropped into each area.

04 - To calculate charges, based on the gross weight, volume or number of containers for each area, using a rating table.

Copies

Enter the number of copies of the bill of lading documentation you require.

Rate Code

Enter the rate code for the selected rating method and carrier. This defines the rating criteria that are effective on a given date.

Functions:

F13

Release. Use this function to move the load status to released. You can now print the transport documentation (this is immediate, if you have set the flag for the transport centre). You can limit this function to certain planners.

Hold. Use this function to hold a released load and set the status back to pending. You can now change the load information again.



Note: You can reset a load status to pending at any stage before you post payments to the General Ledger. If you have posted the load rating details to the GL, via AFI, you need to enter a manual journal to balance the postings.

F14

Drops. Use this function to display the drops for the load. You can then select the drops to move them to another load, or remove the drops and re-instate them as outstanding.

If you release a load, you cannot change any information.

F15

Orders. Use this function to display the orders for a load. You can amend the orders, move them to another load or remove them from this load.

If you release a load, you cannot change any information.

F16

Totals. Use this function to display the load totals enquiry. This shows the totals for capacities, drops, orders, rating and payment details.



Note: If the load is a master load, then the displayed totals do not include the capacities for

the sub-loads.

F17

Sub-loads/consolidation loads. If the current load is a master load, use this function to display the details of the master load and the sub-loads associated with it. If the current load is a sub-load, use this function to display the sub-load's details.

If the current load is a primary consolidation load, use this function to display the details of the consolidation load and the secondary loads associated with it. If the current load is a secondary load, use this function to display details of itself.

F20

Consignee. Use this function to enter the name and address details that you want printed on the bill of lading.

F21

Text. Enter the load text to print on all bill of lading documentation.



To save the details and return to the menu,
select **F8=Update**.

Select Drops for a Load Screen (F14)



To display this window, on the Maintain Load Detail Window, select **F14=Drops**.

You use this screen to select the drop you want to maintain.

TP775	Z1 - UK Demonstration Company	User GBJBAPS	26/11/97
	TP COURSE TPCN		9:48:26
Select Drops on a oac			
Load number	L5	Load status.....	Pending
Ship date	20/11/97	Ship time.....	7:00
Route	LOAB	London to Aberdeen	
S	Drop	Weight	Volume Containers Customer name
█	012	468.0	210.0 5.0 TP CUST - Natti
1=Select 2=Delivery profile enquiry			
F3=Exit F12=Previous			

Fields:

S

Select. Enter one of the following:

- 1 - To select the drop you want to maintain.
- 2 - To display the Delivery Profile Enquiry for this drop.



To save any changes and return to the previous screen, select **F3=Exit**.

Move Drop Details Window (Option 1)



On the Select Drops for a Load Screen, select the drop to maintain.

You use this window to remove drop details or move drops onto a new load.



Note: This also moves all order details associated with the drop.

TP775	Z1 - Demonstration Company Demonstration Transport Centre	User SP1	9 /03/95 13:38:53
-------	--	----------	----------------------

Select Drops for a Load

Load number A4 Load status..... Pending
 Ship date 9/03/95 Ship time..... 16:00
 Route YORKS1 Yorkshire Route 1

S	Drop
1	010

Move Drop Details

Customer..... GC01 /000
 Reeves Chemist's

From

Route..... YORKS1 Yorkshire Route 1
 Drop..... 010
 Load..... A4

To

Route...?.. _____
 Drop..... _____
 Load..... _____

1=Select F4=Prompt F5=Refresh F8=Update F24=More keys
 F3=Exit F12=Previous

Fields:

Route

Enter the route to move the drop onto.

Drop

Enter the drop sequence assigned to the customer delivery point for this route.

Load

Enter the new load number for the drop.

If you enter a route or drop but leave the load blank, Transport Planning displays all loads associated with the route on the required date, so you can select the required load.

Functions:



Note: Transport Planning refreshes drop requirements to latest details. If the drop is no longer on the load, you cannot amend it.

F11

Remove drop. Use this function to remove the drop from the load. This sets the drop to outstanding, and is visible within the build loads function.

F14

Orders. Use this function to display all the orders associated with the drops so you can move or amend them.



F16

Pending loads. This function displays pending load's headers that conform to selection criteria such as ship dates, route entered (all routes if blank), and all carriers.

Pending loads. Use this function to display the load headers that conform to the entered details.



To save the details and return to the previous screen, select **F8=Update**.



Move Order Details Window (Option 1)



To display this window, on the Select Orders For A Load Screen, select an order.

Use this window to remove orders from the load or move orders onto a new load.



Note: This also updates all drop details associated with the order.

TP780A	Z1 - Demonstration Company	User SP1	9 /03/95
	Demonstration Transport Centre		13:39:29
Enquire on Orders for a Load			
Load number.....	A4	Load status.....	Pending
Ship date.....	9/03/95	Ship time.....	16:00
Route.....	YORKS1	Yorkshire Route 1	
S Drop			
1	010		
Move Order Details			
Order.....	0000122		
Stockroom....	01	Central Stockroom	
From			
Route.....	YORKS1	Yorkshire Route 1	
Drop.....	010		
Load.....	A4		
To			
Route....?			
Drop.....			
Load.....			
1=Select 2=Ame F4=Prompt F5=Refresh F8=Update F24=More keys			
F3=Exit F12=Previous			

Fields:

Route

Enter the route to move the order onto.

Drop

Enter the drop sequence to assign to the customer delivery point.

Load

Enter the load number to move the order onto.

If you enter a route or a drop, and leave the load blank, Transport Planning displays all the loads associated with the route on the required date.

Functions:

F11

Remove order. Use this function to remove the order from the load and re-instate it as outstanding.

F14

Lines. Use this function to select specific order line to move to a different load.

F16

Pending loads. Use this function to display the pending loads that conform to selection criteria such as ship dates, route entered (all routes if blank), and all carriers.



To save the details and return to the previous screen, select **F8=Update**.



Note: Transport Planning refreshes order requirements to latest detail. If the order is no longer on the load, you cannot continue to amend it.

Maintain Load Select Order Lines Screen (F14)



To display this screen, on the Move Order Details Window, select **F14=Lines**.

Use this screen to select order lines to move from this load.

TP781	Z1 - Demonstration Company	User SP1	9/03/95		
	Demonstration Transport Centre		13:41:02		
Select Order Lines					
Order number	0000122	Stockroom	01 Central Stockroom		
Despatch date ...	9/03/95	Despatch time ...	16:00		
Load number	A4	Load status	Pending		
Route	YORKS1	Drop	010		
	Yorkshire Route 1				
	Line	Quantity	Weight	Volume	Containers
1	1	100.000	23.0	30.0	.5
-	2	50.000	11.6	15.0	.3
-	3	75.000	13.5	15.0	.2
1=Select		2=Order line enquiry			
F3=Exit		F12=Previous			

Fields:

(Untitled)

Select. Enter one of the following:

- 1 - To select the order line to move to a different load.
- 2 - To view the order line details.



To display the Move Order Line Details Window, select an order line and press **Enter**.

Move Order Line Details Window (Option 1)



To display this window, on the Maintain Load
Select Order Lines Screen, select an order line
and press **Enter**.

Use this screen to move order or despatch note line details onto a new load on a different route.

TP781	Z1 - Demonstration Company	User SP1	9 /03/95
	Demonstration Transport Centre		13:41:02
Select Order Lines			
Order number	0000122	Stockroom	01 Central Stockroom
Despatch date ...	9/03/95	Despatch time ...	16:00
Load number	A4	Load status	Pending
Drop		Drop	010
Route			

Line	Order	Item	Stockroom	From	To
1	1	5001	01	YORKS1 Yorkshire Route 1	
-	2			Drop..... 010	
-	3			Load..... A4	
				Route....?..	
				Drop.....	
				Load.....	

1=Select	F4=Prompt	F5=Refresh	F8=Update	F24=More keys
F3=Exit	F12=Previous			

Fields:

Route

Enter the route to move the order line to.

Drop

Enter the drop sequence assigned to the customer delivery point.

Load

Enter the load number to move the order line to.

If you enter a route or drop but leave the load blank, Transport Planning displays all loads associated with the route on the required date.

Functions:

F11

Remove Line. Use this function to remove the order line from the load and re-instate its requirements as outstanding.

F16

Pending loads. Use this function to display the pending load headers that conform to selection criteria, such as ship dates, route entered (all routes if blank), and all carriers.



To save the details and return to the previous screen, select **F8=Update**.

Amend Order Details Window



To display this window, on the Select Orders for a Load Screen, select an order with 2 - Amend.

Use this screen to maintain the capacity details for the order or despatch note requirements. You can also confirm the details as ready for loading. (Transport Planning automatically does this when you confirm the order as despatched in Sales Order Processing or Warehousing).

TP780A	Z1 - Demonstration Company	User SP1	9/03/95
	Demonstration Transport Centre		13:40:35
Enquire on Orders for a Load			
Load number.....	A4	Load status.....	Pending
Ship date.....	9/03/95	Ship time.....	16:00
Route.....	YORKS1	Yorkshire Route 1	
S Drop	Wei	Amend Order Details	
2	010	Order..... 0000122 Stockroom..... 01 Central Stockroom Gross weight..... 48.1 Net weight..... 47.0 Tare weight..... 1.1 Volume..... 60.0 Containers..... 1.0 Ready for loading.. 0 (0=No, 1=Yes)	
1=Select 2=Amend 3=Ord		F5=Refresh F8=Update F24=More keys	
F3=Exit F12=Previous			

Fields:

Gross Weight

Enter the gross weight.

Net Weight

Enter the total weight of the actual goods.

Tare Weight

Enter the total weight of the containers for the order.



Note: The gross weight must always equal the sum of the net and tare weights.

Volume

Enter the total volume for the order.

Containers

Enter the total number of containers for the order requirement.

Ready For Loading

Enter one of the following:

0 - If the goods are not confirmed despatched.

1 - If the goods are confirmed despatched, and ready to load.

Functions:

F5

Refresh. Use this function to refresh the order details. If the order is no longer on the load, you cannot continue to amend it.

F14

Lines. Use this function to display the order lines for the load, so you can move them to another load.



To save the details and return to the previous screen, select **F8=Update**.

Sub Loads Window (F17)



To display this window, on the Maintain Load Details Screen, select **F17=Sub Loads**.

OR on the Rate Loads Manually Detail Screen, select **F18=Sub Loads**.

If the current load is a master load, use this window to view the details of the load plus the sub-loads associated with it.



Note: If the current load is a master load, then the first line shows the capacity requirements for any drops directly associated with it.

If the current load is a sub-load, use this window to view the details of the load.

TP430B	Z1 - Demonstration Company	User SP1	23/03/95
	Demonstration Transport Centre		11:39:00

Maintain Load		Master Load	
Load number	A8		
Master load			
Master drop			
Ship date	23/03/95		
Route	BHAM		
Carrier	CARRIER1		
Vehicle type	16T		
Origin	TC01		
Vehicle			
Driver			
Temperatures			
Agent contact			
Exclusive load	0		
Confirmation	0		
Bill required	0		
Bill format			
Copies	1		

Sub loads			
Load.....	A8	More:	
Weight.....			2787.0
Route.....	BHAM	Carrier....	CARRIER1
Load	Route	Carrier	Weight
A8	BHAM	CARRIER1	1426.0
A9	BHAM	CARRIER1	123.0
A10	BHAM	CARRIER1	1238.0

F14=Volume	F16=Containers	F12=Previous
Rate code?.. C01STD		

F16=Totals	F17 =Sub loads	F20=Consignee	F24=More keys
------------	----------------	---------------	---------------

Functions:

F14

Volume. Use this function to view the capacity requirements of the load in units of volume.

F15

Weight. Use this function to view the capacity requirements of the load in units of weight.

F16

Containers. Use this function to view the capacity requirements of the load in numbers of containers.



To return to the previous screen, select **F12=Previous**.

Consolidation Details Window (F17)



To display this window, on the Maintain Load Details Screen, select **F17=Consolidation Load**.

OR on the Rate Loads Manually Detail Screen, select **F18=Consolidation Loads**.

If the current load is a primary (consolidation) load, use this window to view the details of this load plus the secondary loads associated with it.

If the current load is a secondary load, use this window to view details of the current load.

TP430B		Z1 - Demonstration Company		User SP1		23/03/95	
		Demonstration Transport Centre				11:39:27	
Maintain Load				Consolidated Load			
Load number	A11	Load	Consolidation Details				
Master load		Conso	Load.....	A11	More:		
Master drop		Maste	Weight.....		12133.0		
Ship date	23/03/95	Ship	Load	Route	Weight		
Route	YORKS1	Yorks	A11	YORKS1	8537.0		
Carrier	OWN	Demon	A12	YORKS1	2843.0		
Vehicle type ?..	3BT	3B To	A13	YORKS1	753.0		
Origin	TC01	Desti					
Vehicle		Seal					
Driver		Crew					
Temperatures		Skele					
Agent contact ...		Payme					
Exclusive load ..	0	P & L					
Confirmation	0	Ratin					
Bill required ...	0	Rate					
Bill format ..?		Rate code	C01STD				
Copies	1						
F16=Totals		F17=Consolidation Loads		F20=Consignee		F24=More keys	

Functions:

F14

Volume. Use this function to view the capacity requirements of the load in units of volume.

F15

Weight. Use this function to view the capacity requirements of the load in units of weight.

F16

Containers. Use this function to view the capacity requirements of the load in numbers of containers.



To return to the previous screen, select **F12=Previous**.

Consignee Details Window (F20)



To display this window, on the Maintain Load Details Screen, select **F20=Consignee Details**.

Use this screen to enter the name and address details you want to print on the bill of lading.



Note: This does not appear on Bill of Lading format 02 - One document per drop or delivery, this uses delivery names and addresses.

TP430B	Z1 - Demonstration Company	User SP1	9/03/95
	Demonstration Transport Centre		13:40:26
Maintain Load			
Load number	A4	Load status	Pending
Master load		Consolidation Load	
Master drop		Master Area	
Ship date	9/03/95	Ship time	16:00
Route	YORKS1	Yorkshire Route 1	
Carrier	OWN	Demonstration Fleet	
Vehicle type	38T	38 Tonne Artic	
Origin	I		
Vehicle			
Driver			
Temperatures			
Agent contact			
Exclusive load	0		
Confirmation	0		
Bill required	0		
Bill format			
Copies			

Consignee Details

Name..... Demonstration Fleet

Address..... IN-HOUSE VEHICLES

Post code.....

F5=Refresh F8=Update F12=Previous

F3=Exit F4=Prompt F5=Refresh F8=Update F24=More keys

Fields:

Name

Enter the name to appear on the bill of lading.

Address

Enter the address to appear on the bill of lading.

Post Code

Enter the post code to appear on the bill of lading.



To save the details and return to the previous screen, select **F8=Update**.

Transport Load Text Window (F21)



To display this window, on the Maintain Load Details Screen, select **F21=Text**.

Use this screen to enter the text printed on the bill of lading.

TP430B		Z1 - Demonstration Company		User SP1		24/03/95	
		Demonstration Transport Centre				16:47:03	
Maintain Load				Master Load			
Load number	A8	Load status	Pending				
Master load		Consolidation Load ..					
Master drop		Master Area	?				
Ship date	23/03/95	Ship time	10:30				
Route	BHAM	Birmingham Route					
Carrier	CARRIERT	BMZ Distribution Services					
Vehicle type ?..	16T	16	Transport load text				
Origin	TC01	Des					
Vehicle		Sea					
Driver		Cre					
Temperatures		Ske					
Agent contact ...							
Exclusive load ..	0	Pay					
Confirmation	0	P &					
Bill required ...	0	Rat					
Bill format ..?		Rat					
Copies	1	Rat					
F21=Text				F24=More keys			

Lin External Text

1	Note: This is a master load.
2	Sub-loads are A9 and A10.
3	
4	
5	
6	

Position to ___ Insert ___ after ___
Delete ___ from ___

F5=Refresh F8=Update F12=Previous

Fields:

Text

Enter any text to print on the bill of lading.

Position To

Enter the line you want to move the cursor to.

Insert

Enter the number of the lines to insert.

After

Enter the line number to insert the lines after.

Delete

Enter the number of lines to delete.

From

Enter the number of the line to start the deletion from.



To save the details and return to the previous screen, select **F8=Update**.

Rate Loads Automatically

4/TPP

Use this function to calculate the expected carrier charge for specified loads via a batch job. You can enter a rate method to select all loads rated by that particular method, for the specified ship date.

For more details about the automatic rating calculation, see Carrier Rates Maintenance.

The batch run produces an exception report, showing the details of all the loads it could not rate.



Note: If you do not enter a rate method or load, the batch job rates all loads requiring rating for the ship date.

You can only select a load after you have printed the transport documentation and set the rating status to 2 (rated automatically).

For consolidated loads, you can only select the primary load, as the system automatically rates the associated secondary loads.

For master loads, you rate the sub-loads separately from the master load, since the carriers and rate tables are often different.

To re-rate a load:

1. Use Maintain Loads to set the load back to a pending state, using function **F13=Hold**.
2. Make any required changes, reset the rated flag, and re-release the load using Maintain Loads using function **F13=Release**.
3. Print the bill of lading documentation and load sheets, or both.
4. Re-rate the load using the automatic or manual method.



Note: If you have posted the load rate value to the GL as an accrual, you must enter a manual journal (or journals) to balance this original value.

Rate Loads Automatically Screen



Select Rate Loads Automatically.

Use this screen to select the loads you want to rate automatically.

TP440	Z1 - Demonstration Company	User SP1	10/03/95
	Demonstration Transport Centre		16:23:50
Rate Loads Automatically			
Ship date	10/03/95		
Rate method	?.. _		
OR			
Load number	A3		
F3=Exit F4=Prompt F8=Submit F16=Printed Loads			

Fields:

Ship Date

Enter the ship date for the loads. This defaults to today's date plus the planner's time fence days.

Rate Method

To specify the rate method to automatically rate, enter one of the following:

- 01 - Load and rate table.
- 02 - Drop and rate table.
- 03 - Fixed rate per area.
- 04 - Area and rate table.

Load Number

Enter a load reference to rate. The load must be at status 60 - awaiting rating.

Functions:

F16

Printed loads. Use this function to display the loads, which are awaiting rating, for the entered ship date.



To submit the batch job, select **F8=Submit**.

Rate Load Manually



5/TPP

Use this option to manually calculate the expected carrier charge for a selected load.

You must have printed the transport documentation and set the rated status to 2 (rate manually). If the status is 1, a warning message displays to suggest that you should automatically rate this load. You can override this warning.

For consolidated loads, the calculated grand total and drop charges are apportioned automatically across each of the loads, based on their relative capacity (weight, volume or number of containers) and the number of drops.

For master loads, the calculated grand total is the total gross capacity (weight, volume, or number of containers) of its sub-loads plus any customer drops directly assigned to the master load itself.

Rate Loads Manually Selection Screen



Select Rate Load Manually.

Use this screen to select the loads you want to rate manually.

```

TP450A          Z1 - Demonstration Company      User SP1      13/03/95
                Demonstration Transport Centre    12:43:41

Rate Loads Manually

Load number ..... A4


```


Rate Loads Manually Detail Screen



To display this screen, on the Rate Loads Manually Selection Screen, enter a load number and press **Enter**.

Use this screen to enter the details for the loads you want to manually rate.

If the load is a master load, then the screen displays "Master Load" and the number of sub-loads. You can use the function **F18** to view the sub-loads. The capacity (weight, volume or containers) is the consolidated capacity of all the sub-loads, plus any customer drops assigned to the master load.

If the load is a consolidation (primary) load, the screen displays "Consolidated Load" and the number of sub-loads. You can use **F18=Consolidation** to view these sub-loads. The capacity (weight, volume or containers) is the consolidated capacity of all these loads.

TP450B	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		12:44:08
Rate Loads Manually			
Load number	A4	Route.....	YORKS1
		Carrier.....	CARRIER1
Load gross weight.....			48.1
VAT code.....?	001		
Rate.....			3.00
Conversion factor.....	1.00000		
Minimum weight.....			40.0
Surcharge percentage.....	5.00		
Surcharge value.....			.00
Total charges.....			144.30
Drop charges.....			2.00
Penalties.....			.00
Surcharges.....			7.32
Load grand total.....			153.62
F3=Exit	F4=Prompt	F5=Refresh	F8=Update
F16=Volume	F17=Containers	F12=Previous	

Fields:

VAT Code

Enter the VAT code. If you have General Ledger attached, you must define the VAT code to the General Ledger. If you do not have General Ledger attached, you must define the VAT code to the Inventory descriptions file under a major type of VAT.

Transport Planning only applies VAT when you transfer the carrier invoice to Accounts Payable.

Rate

Enter the rate for single unit of capacity (gross weight, volume or number of containers depending on the capacity type).

Conversion Factor

Enter the conversion factor. Transport Planning divides the load gross weight, volume or number of containers by this factor, before calculating a rate for a given quantity.

Minimum Weight

Enter the minimum weight. If the load is less than the minimum weight, Transport Planning calculates the penalty to add to the rate.

Surcharge Value / Percentage

Enter a value or percentage to apply to calculated load charges for unforeseen extras such as government fuel tax charges.



Note: You can either enter a surcharge percentage or value but not both.

Total Charge

If you have not entered a charge rate, enter the total charge.

If you have entered a charge rate, the total charge is:

$(\text{Gross Weight} \times \text{Rate}) / \text{Conversion Factor}$

Drop Charge

Enter the fixed charge for the drops. For master and consolidated loads, duplicated drop numbers count as a single drop. On master loads, each sub-load counts as a drop.

Penalties

This is the calculated penalty charge.

Surcharge

This is the calculated or entered surcharge.

Load Grand Total

Grand total charge calculated as follows:

Total charge + drop charge + penalty charge + surcharge

Functions:

F15

Weight. Use this function to set the capacity to weight.

F16

Volume. Use this function to set the capacity to volume.

F17

Containers. Use this function to set the capacity to containers.

F18

Consolidation loads. Use this function to display the details of the loads consolidated together for rating (where the current load is a primary load).

Sub-loads. Use this to display the details of the sub-loads (where the current load is a master load).

If the load is not a primary or master load, this function is not available.



To save the information and return to the menu,
select **F8=Update**.

Confirm Despatch Of Load



6/TPP

Use this function to, optionally, date stamp the load, to confirm that the load has left the transport centre. You by-pass this if you set Bypass Confirm Load Despatch, for the transport centre, to 1 - Yes.



Note: If the load needs authorisation of payments, that is rating has taken place, the load status is awaiting payment. If rating is not applicable, you by-pass payment authorisation, and the load status is awaiting drop to history.

Confirm Despatch Of Load Selection Screen



Select Confirm Despatch.

Use this screen to select the load you want to despatch.

TP460A	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		13:37:00
Confirm Despatch of Load			
Ship date 13/03/95			
Route?.. _____			
OR			
Carrier?.. _____			
OR			
Origin?.. _____			
Destination ..?.. _____			
OR			
Load number A4 _____			
F3=Exit F4=Prompt F16=Select Load			

Fields:

Ship Date

Enter a ship date for the loads.

Route

Enter the route for the loads.

Carrier

Enter the carrier for the loads.

Origin

Enter the origin or start point for the loads.

Destination

Enter the destination or end point for the loads.

Load Number

Enter a particular load reference to review.

Functions:

F16

Select loads. Use this function to display the load headers for printed, and where applicable, rated loads, that conform to the selection criteria.



To display the Confirm Despatch of Load Detail Screen, enter the required selection details, and press **Enter**.

Confirm Despatch Of Load Detail Screen



To display this screen, on the Confirm Despatch of Load Selection Screen, enter the required selection details, and press **Enter**.

This screen displays load header information for you to review and confirm.

TP460B	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		13:37:09
Confirm Despatch of Load			
Load number	A4	Load status	A'COD
Ship date	9/03/95	Ship time	16:00
Route	YORKS1	Yorkshire Route 1	
Carrier	CARRIER1	BMZ Distribution Services	
Vehicle type	38T	38 Tonne Artic	
Origin	TC01	Destination	YORKS
Vehicle		Seal number	
Driver		Crew	
Temperatures		Skeleton Load	0
Agent contact ...			
Exclusive load ..	0	Payment method.....	01
Confirmation	0	P & L override	
Bill required ...	0	Rating status	2 3
Bill format		Rate method	01
Copies	1	Rate code	C01STD
F3=Exit F8=Update F12=Previous F20=Consignee details			
F21=Text			

Functions:

F20

Consignee Details. Use this function to display the name and address details that print on the bill of lading.

F21

Text. Use this function to display the text which prints on the transport documentation.



To confirm the despatch of the load, select **F8=Update**.

Authorise Payments



7/TPP

Use this function to match and record payments, on receipt of an external carrier's invoice. You match invoice details against the calculated load charges. If there is any discrepancy, authorised users can authorise the payment. Once authorised, Transport Planning automatically transfers the invoice and load details to the invoice log in Accounts Payable (if installed). In addition, you can update accrual accounts within the General Ledger if you have Advanced Financial Integrator installed.



Note: Once authorised the load status updates so you can drop it to history.



Note: When authorising multiple loads to a single carrier invoice, you can transfer one invoice or one invoice per load to Accounts Payable. This depends on the setting of the appropriate flag on the company profile.



Note: For consolidated loads, you cannot authorise the secondary load if you have not rated the primary load.

Authorise Payments Carrier Selection Screen



Select Authorise Payments.

Use this screen to enter the carrier to authorise payments against.

TP490A	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		16:45:03
Authorise Payments			
Carrier?.. <u>CARRIER1</u>			
F3=Exit F4=Prompt			

Fields:

Carrier

Enter the external carrier the invoice is for.



Press **Enter** to display the detail screen.

Authorise Payments Invoice Details Screen



To display this screen, on the Authorise Payments Carrier Selection Screen, enter a carrier and press **Enter**.

Use this screen to enter the payment and invoice details for the selected carrier.

TP490B	Z1 - Demonstration Company	User SPI	13/03/95
	Demonstration Transport Centre		16:45:19
Authorise Payments			
Carrier	CARRIER1	BMZ Distribution Services	
Carrier invoice number	0012394		
Carrier invoice date	130395		
Invoiced freight amount			
Load number			
OR			
Load number range	0/00/00	0/00/00	
Ship date range	0	1=Yes, 0=No	
Auto Authorize			
F3=Exit F12=Previous F16=Unpaid Loads			

Fields:

Carrier Invoice Number

Enter the invoice number.

Carrier Invoice Date

Enter the date of the invoice.

Invoiced Freight Amount

Enter the total amount detailed on the invoice. This can be zero for free of charge.

Load Number

If there is only one load on the invoice, enter the load reference. The load must be at status 80 - awaiting authorisation of payments.

Load Number Range

If the invoice has multiple loads, enter the range of load numbers.



Note: If you leave both the Load Number Range and the Load Number fields blank, then Transport Planning considers all loads awaiting payment.

Ship Date Range

When matching to multiple loads, enter a range of ship dates. If you leave this field blank, then Transport Planning considers all ship dates.

Auto Authorise

Enter one of the following:

0 - To manually select the loads for authorisation.

1 - To set all selected loads to authorise on the Authorise Payments Load List Screen.

Functions:

F16

Unpaid loads. Use this function to display all the loads that conform to the selection criteria.



To display the next screen, press **Enter**.

Authorise Payments Details Screen



To display this screen, on the Authorise Payments Invoice Details Screen, enter a single load number and press **Enter**.

Use this screen to enter the payment details for an invoice for a single load.

TP490C	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		16:54:27
Authorise Payments			
Carrier	CARRIER1	BMZ Distribution Services	
Carrier invoice number	0012394		
Carrier invoice date	13/03/95		
Invoiced freight amount	1922.20		
Load number	A7		
Route	CAMBS	Cambridge Route	
Ship date	13/03/95		
Calculated amount	1758.58		
Payment amount excluding VAT	1798.58		
Payment reference	A7		
F3=Exit F8=Update F12=Previous			

Fields:

Payment Amount Excluding VAT

Enter the amount, excluding tax, to authorise for payment. This normally equals the calculated amount and the invoiced amount.

Payment Reference

Enter the payment reference to associate with the payment to the carrier. You can carry this reference forward into the financial systems for reference. This defaults to the load reference.



To authorise the payment, select **F8=Update**.



Note: This also transfers to the Accounts Payable invoice log, if there no adjustment.



Note: If the payment amount is not the same as the calculated charge amount, Transport Planning displays an additional adjustments screen.

Authorise Payments Load List Screen



To display this screen, on the Authorise Payments Invoice Details Screen, enter the load selection criteria and press **Enter**.

Use this screen to select the load or loads to authorise payments for.

TP490H	Z1 - Demonstration Company	USER SP1	13/03/95
	Transport Centre TC01		16:46:05
Authorise Payments Load List			
Carrier		CARRIER1 BMZ Distribution Services	
Carrier invoice number		0012394	
Invoiced freight amount.....		.00	
Load number	Ship date	Route	Payment /Weight
A4	9/03/95	YORKS1	153.62
A7	13/03/95	CAMBS	1758.58
		Rated Value /Volume Container	
		153.62	1758.58
		1758.58	
Total Payment		.00	
1=Authorise 2=Enquire 3=Adjust 4=Deselect			
F3=Exit F8=Update F12=Previous F14=Addition F15=Fold			

Fields:

(Untitled)

Select. Enter one of the following:

- 1 - To select the load for authorisation when you select **F8=Update**, confirming the payment value to be made to the carrier.
- 2 - To display the load details enquiry screen.
- 3 - To display the adjust payment details screen, so you can change the payment amount.
- 4 - To remove the load from the list of loads to authorise.

Functions:

F14

Addition. Use this function to add loads awaiting payment to the list.

F15

Fold. Use this function to toggle the display, between 1 and 2 lines per load.



To display the Authorise Payments summary Screen, select **F8=Update**.

Authorise Payments Summary Screen



To display this screen, on the Authorise Payments Load List Screen, select at least one load and then select **F8=Update**.

Use this screen to enter the payment reference.

TP490J	Z1 - Demonstration Company	User SP1	13/03/95
	Transport Centre TC01		16:58:03
Authorize Payments Summary			
Carrier	CARRIER1 BMZ Distribution Services		
Carrier invoice number	0012394		
Carrier invoice date	13/03/95		
Number of loads selected ... 0001			
Invoice freight amount	1922.20		
Total freight selected	153.62		
+ Sum of adjustments	10.00		
= Payment amount	163.62		
F3=Exit F8=Update F12=Previous			

Fields:

Payment Reference

Enter a payment reference for this group of loads. Transport Planning passes this reference to the ledgers.



To update the selected loads and transfer the invoice details to the Accounts Payable invoice log as a matched invoice, select **F8=Update**.

Authorise Payments Add New Loads (F14)

 To display this screen, on the Authorise Payments Load List Screen, select **F14=Addition**.

Use this screen to add loads awaiting payments to the list to authorise.

TP490K

Z1 - UK Demonstration Company

USER GBJBAPS

28/11/97

Transport Centre

8:20:55

Add New Loads

Carrier

CARRIER1 BMZ Distribution Services

Carrier invoice number

Carrier invoice date

27/11/97

Load number

Load Number

Load Number

834

L23

F3=Exit

F8=Update

F12=Previous

Fields:

Load number

Enter the load number you want to add to the list of loads to authorise.

 To add the entered loads to the load list, and return to the previous screen, select **F8=Update**.

Authorise Adjustments Window



This window displays automatically when the payment and calculated amounts are different.

Use this window to enter the adjustment reason and reference.

TP490C	Z1 - Demonstration Company	User SP1	13/03/95
	Demonstration Transport Centre		16:54:27
Authorise Payments			
Carrier CARRIER1 BMZ Distribution Services			
Carrier invoice number 0012394			
C	Authorise adjustments		
I	Adjustment amount	40.00	
L	Adjustment reason?	01	
R	Adjustment reference	A002/07	
S			
F4=Prompt F8=Update F12=Previous			
Calculated amount 1758.58			
Payment amount excluding VAT 1798.58			
Payment reference A7			
F3=Exit F8=Update F12=Previous			

Fields:

Adjustment Reason

Enter a reason for the adjustment. You can maintain reason codes on the Inventory descriptions file under a major type of TPAR. You can use this for analysis purposes or to control the posting of adjustments to General Ledger via AFI.

Adjustment Reference

Enter a reference for the adjustment.



To update the payment and adjustment details, select **F8=Update**.

Authorise Payments Authorisation Warning

If there is a discrepancy between the calculated charges and the entered payment amount, and you are not authorised to make payment adjustments, a warning displays.



*Note: You can bypass the payment entry by pressing **Enter**. If you enter the payment details, a user authorised to make adjustments must review the details before you can complete the payment transaction (via this Authorise Payments option).*

Authorise Manual Payments



8/TPP

Use this option when you have paid the carrier directly, through Accounts Payable, for delivery of a load. You do not need to match the carrier invoice and the load completes without posting the invoice since it is settled.

Otherwise this process is similar to the Authorise Payments option, except you can only authorise one load at a time.

Cancel Load



9/TPP

Use this option to cancel load headers. This puts all associated transport order requirements back to an outstanding state. You can review the transport requirements again using the Build Loads option.

Once you cancel the load, you can delete it using the Update Load History utility.

You can process cancellation load details via AFI to ensure that you can make balancing GL accrual postings (where the load has been rated and posted).

When you try to cancel a secondary load, where the primary load has been rated, Transport Planning issues a warning message to suggest that the primary load is rerated. You cannot cancel a primary load whilst secondary loads are still attached.

The same rules apply for master and sub-loads as for primary and secondary consolidated loads. Also, if you have printed the master load, the warning suggests it is reprinted if you cancel any sub-loads.

Cancel Load Selection Screen



Select Cancel Load.

Use this screen to select the load you want to cancel.

TP470A	Z1 - Demonstration Company	User SP1	23/03/95
	Demonstration Transport Centre		9:18:21
Cancel Load			
Ship date 23/03/95			
Route?.. _____			
OR			
Carrier?.. _____			
OR			
Origin?.. _____			
Destination ..?.. _____			
OR			
Load number A7 _____			
F3=Exit F4=Prompt F16=Select Load			

Fields:

Ship Date

Enter the ship date for the load.

Route

Enter the route for the load.

Carrier

Enter the carrier for the load.

Origin

Enter the origin or start point for the load.

Destination

Enter the destination or end point for the load.

Load Number

Enter the number of the load you want to cancel.

Functions:

F16

Select loads. Use this function to display loads that conform to the selection criteria irrespective of their status. This does not display loads dropped to history or posted to GL via AFI.



To display the Cancel Load Detail Screen, enter a load number and press **Enter**.

Cancel Load Detail Screen



To display this screen, on the Cancel Load Selection Screen, enter a load number and press **Enter**.

This screen displays load header information for you to review and confirm.

TP470B	Z1 - Demonstration Company Demonstration Transport Centre	User SP1	23/03/95 9:18:58
Cancel Load			
Load number	A7	Load status	A'ledg.post
Master load		Consolidation load ..	
Master drop		Master Area	
Ship date	13/03/95	Ship time	16:00
Route	CAMBS	Cambridge Route	
Carrier	CARRIER1	BMZ Distribution Services	
Vehicle type	38T	38 Tonne Artic	
Origin		Destination	
Vehicle		Seal number	
Driver		Crew	
Temperatures		Skeleton load	0
Agent contact ...			
Exclusive load ..	0	Payment method	01
Confirmation	0	P & L override	
Bill required ...	0	Rating status	3 1
Bill format		Rate method	01
Copies	1	Rate code	C01STD
F3=Exit F8=Update F12=Previous F20=Consignee details F21=Text			

Functions:

F20

Consignee details. Use this function to view the name and address printed on the bill of lading.

F21

Text. Use this function to view the text printed on the bill of lading and load sheets.



To cancel the load, and return to the menu, select **F8=Update**.

Cancellation Reason Window (F8)

- To display this window, on the Cancel Load Detail Screen, select **F8=Update** to cancel a load.

Use this window to enter a reason for the cancellation.

TP470B	Z1 - Demonstration Company	User SP1	23/03/95
	Demonstration Transport Centre		9:18:58
Cancel Load			
Load number	A7	Load status	A'ledg.post
Master load		Consolidation load ..	
Master drop		Master Area	
Ship date	13/03/95	Ship time	16:00
Route	CAMBS	Cambridge Route	
Carrier	CARRIER1	BMZ Distribution Services	
Vehicle type	38T	38 Tonne Artic	
Origin		Destination	
Vehicle		Seal number	
Driver			
Temperatures			
Agent contact ...			
Exclusive load ..			
Confirmation			
Bill required ...			
Bill format		Rate method	01
Copies	1	Rate code	C01STD
Cancellation Reason Reason code.....?.. <u>1</u> Customer Cancelled F4=Prompt F8=Update F12=Previous			
F3=Exit F8= Update F12=Previous F20=Consignee details F21=Text			

Fields:

Reason Code

Enter the reason for the cancellation. You define reason codes to the Inventory descriptions file under a major type RSNC.

- To save the details and return to the menu, select **F8=Update**.

Request Pick Notes



10/TPP

Use this option to print pick notes based on a range of attributes. The warehouse personnel use this to optimise picks, based on transport requirements or planned loads.

You produce pick notes per order, but you can sequence them by carrier, route or load, with the drop sequence being ascending or descending.



Note: If you install Warehouse Management, you can use the equivalent selections within the Request Picking List For Sales option. This produces a single consolidated pick list for the carrier route or load selected.

Request Pick Notes Select Screen



Select Request Pick Notes.

Use this screen to specify the sequence and selections of the pick notes that you want to create.

TP501	Z1 - Demonstration Company	USER SP1	23/03/95
	Demonstration Transport Centre		9:20:52
Request Pick Notes			
Pick note sequence.....	3	1-Carrier 2-Route 3-Load	
Drop sequence.....	1	1-Ascending 2-Descending	
Selection	<---From--->	<---To--->	
Order.....?	Z1	Z1	
Customer.....?	Z1	Z1	
Delivery required date.	07/00/00	07/00/00	
Carrier.....?			
Route.....?			
Load.....?			
F3=Exit F4=Prompt F8=Submit			

Fields:

Pick Note Sequence

This determines the (ascending) sequence in which the pick notes are to be produced - either carrier code, route code or load number. This field is mandatory and must contain 1 (carrier), 2 (route) or 3 (load), with load being the default when the screen is first displayed.

Drop Sequence

This determines if the drop sequence (within pick note sequence) is to be ascending or descending. This is only relevant if the pick note sequence is by route or load, that is to print pick notes in route/drop or load/drop sequence.

You can specify any combination of valid ranges for the selection criteria described below.

These are AND conditions, that is an order line awaiting pick note request must meet all of the specified selection criteria. If a range is not specified, then it is ignored. If a From is specified without a To then all lines with a value less than the From value are ignored. Similarly, if a To value is specified without a From, then all lines with a value greater than the To value are ignored.

Order

Enter a range of sales company/order numbers. The sales company defaults from the company profile in Transport Planning. The order number(s) must be

awaiting the request of a pick note, that is have allocated lines not yet on a pick note.

Customer

Enter a range of sales company/customer account/delivery sequence numbers.
The customer account/delivery sequence specified must have a delivery profile in Transport Planning.

Delivery Required Date

Enter a valid range of due dates for order lines.

Carrier

Enter a valid range of carrier codes.

Route

Enter a valid range of route codes.

Load

Enter a valid range of load numbers.



To submit the batch job, select **F8=Submit**.

Manual Requirement Creation



11/TPP

Use this function to add requirements which are not included on an order, into Transport Planning.

Typically this is where you optimise a load by carrying loads for a third party, for example, another company which has insufficient transport capacity. In this case the order belongs to the third party and is not known to Transport Planning. You add it to Transport Planning, via this function, so you can plan its delivery.

Manual Requirement Creation Screen



Select Manual Requirements

Use this screen to enter up to five new requirement for a customer. You can immediately add these requirements to a specified load or leave them as outstanding, so you can plan them via the Load Build function.

You must use the Build Loads or Maintain Loads options to amend these requirements.

TP412	Z1 - Demonstration Company Demonstration Transport Centre	USER SP1	23/03/95 9:22:19
Manual Requirement Creation			
Miscellaneous order number.....		Last requirement number... M599999	
Sales company.? <u>Z1</u>			
Customer....?..	Name.....		
	Address....		
Date.....	<u>23/03/95</u>		
Route.....?..			
Requirement:	Item (?)	Weight	Volume Cont.
Assign to load.....?..		Drop sequence.....	
F3=Exit		F4=Prompt	F8=Update
F15=Requirements			

Fields:

Miscellaneous Order Number

For reference, enter an order number.

Sales Company

Enter a sales company.

Customer

Enter a customer account and delivery sequence. It must have a delivery profile defined within Transport Planning.

Date

Enter a ship date for the load. This defaults to today's date.

Route

Enter the route for the order.

Requirement

You can enter up to five lines per requirement number. Enter either an Inventory item codes (for stocked items) or a description of the requirement (for non-stocked items).

Item / Requirement

Enter or select an item code.



Note: If this field is Item, you must enter a valid inventory item code. If this field is requirement, you can enter a non-stocked item.



Note: The title of this field depends upon which screen you are displaying, you can select F15 to change the display.

Weight

Enter the gross weight of the item.

Volume

Enter the volume of the item.

Cont.

Enter the number of containers for the item.

Assign To Load

Enter an outstanding load to add the requirements to.

If you leave this field blank, the requirements are outstanding, and therefore available to the Load Build option.



Note: Transport Planning issues a warning message, if either the route, or ship date, on the load does not match the details on the screen.

Drop Sequence

If you specify a load, enter a drop sequence.

Functions:

F5

Copy Previous Order. Use this function to copy the previously entered manual requirement and use it as the basis for the current requirement. This function is only available when you have already entered a requirement and not left the screen.

F15

Requirements/Items. Use this function to toggle between entry of requirements as descriptions or as item codes.



To add the manual requirement, select **F8=Update**.

Create Loads



12/TPP

You can create new pending loads by entering a minimum of information. You can then plan these loads. You can accept automatically generated load numbers or enter a new load number (provided that the load does not already exist). You can generate loads based on existing skeleton loads. These represent standard loads, which are carried on a regular basis. You can define skeleton loads with default header and text information for a route.

To add a skeleton load, add a normal load header and then define it as a skeleton via maintain loads, at which point any additional details and instructions are added to it. You cannot process skeleton loads further, that is they cannot be released via maintain loads.

Create Pending Load Window



To display this window, select Create Load

OR From the Build Loads Details Screen, select
F13=Create Pending Load.

TPP	Z1 - Demonstration Company	User SP1	08/03/95 16:09:03
Transport Planning Processing Menu			
Processing		Enquiry	
1. Create load schedule		14. Outstanding orders	
2. Build loads		15. Load details	
3. Maintain load		16. Loads by order	
4. Rate loads automatically			
5. Rate load manually			
6. Conf			
7. Auth			
8. Auth			
9. Canc			
10. Requ			
11. Manu			
Create Pending Load			
Load number <u>A1</u>			
Based on?..			
Ship date <u>8/03/95</u>			
Route?.. <u>BHAM</u> Birmingham Route			
Carrier?.. <u>CARRIER1</u> BMZ Distribution Services			
Vehicle type ..?.. <u>16T</u> 16 Tonne Rigid			
Ship time <u>10:30</u>			
Option Search F4=Prompt F8=Update F12=Previous			
F3=Exit F4=Prompt F6=Messages F12=Previous			
F16=Change Company F18=Prints F20=Change Centre F21=Create Load			

Fields:

Load Number

Enter the load reference. This must be unique within a transport centre or within the transport company (depending on the company profile setting). When you create pending loads via the Build Loads option or load schedule creation, Transport Planning assigns load numbers.

Based On Load

Enter the load number of a skeleton load to use as a base for creating a new load number. This copies any load header information and associated text.

Ship Date

Enter the planned ship date. The ship date defaults to today's date plus the planner's time fence days.

Route

Enter the route for the load. You assign each customer or delivery point a particular drop sequence along a route.

Carrier

Enter the internal or external carrier that handle the transport requirements. If you leave the carrier blank, it defaults to the one specified as a default for the route record.

Vehicle Type

Enter the type of vehicle for a load. You can define weight and volume capacities to vehicle types. If you leave this field blank, it defaults to the vehicle type specified as a default for the route record.

Ship Time

Enter the ship time for a load. If you leave this field blank, it defaults to the ship time specified as a default for the route record.



To save the load select **F8=Update**.

Create Requirements (TP Centre)



20/TPP

This option transfers order requirements into Transport Planning when the order line's due date falls on or inside the time fence horizon. The time fence horizon is today's date plus the transport requirement lead time defined on the company profile. Use this option to avoid passing order lines for which you do not yet need to plan the transport requirements.

You only need to invoke this option where a transport requirement lead time is set for the company. You can schedule the option within Machine Manager to run automatically.

This option only considers order requirements within the transport centre currently being used.

This utility is run as a batch job with no selection criteria.

Change Default Transport Centre



80/TPP

Use this option to select the transport centre you want to process. This is the centre you maintain loads, build loads and authorise payments for.




Note: If you want to make changes to the loads, you must be authorised to the transport centre. Use the Planner Profile Maintenance utility to authorise planners to a transport centre.

Change Default Transport Centre Window

 Select Change Default Transport Centre.

Use this window to select the transport centre for which you want to process loads.



TPP Z1 - UK Demonstration Company User: GBJBAPS 28/11/97
11:34:36

Transport Planning Processing Menu

Processing Enquiry

2. Build loads Change Transport Centre

3. Maintain load Default transport centre

4. Rate loads au Sel Centre Name

5. Rate load man 1 LG99 TP COURSE TPCN ** KEEP OUT **

6. Confirm despa TC01 Demonstration Transport Centre

7. Authorise pay TC02 dddddd

8. Authorise man

9. Cancel load

10. Request pick

11. Manual requir

12. Create Load

Option 80 Bottom

Search 1=Select Position to:

F3=Exit F12=Previous

F16=Change Company F18=Prints

Fields:

Sel

Select. Enter 1 alongside the transport centre you want to set as your default transport centre.

Position to

Enter the transport centre to position the cursor to.

 To set the default transport centre select a centre and press **Enter**.